

# Keyfactor Web APIs 10.1

Reference Guide

## **Table of Contents**

1.0 Introduction	1
2.0 Web APIs Reference	2
2.1 Overview	
2.1.1 Transaction Security	
2.1.2 Architecture	
2.1.3 Web API Common Features	3
2.1.4 Versioning	
2.2 Keyfactor API	
2.2.1 Agents	8
2.2.1.1 GET Agents ID	
2.2.1.2 GET Agents	12
2.2.1.3 POST Agents Reset	
2.2.1.4 POST Agents Disapprove	
2.2.1.5 POST Agents Disapprove 2.2.1.6 POST Agents ID Reset	
2.2.1.7 POST Agents ID FetchLogs	18
2.2.1.8 POST Agents Set Auth Certificate Reenrollment	19
2.2.2 Agent BluePrint	
2.2.2.1 DELETE Agent BluePrint ID	21
2.2.2.2 GET Agent BluePrint ID	21
2.2.2.3 GET Agent BluePrint	22
2.2.2.4 GET Agent BluePrint ID Jobs	23
2.2.2.5 GET Agent BluePrint ID Stores	26
2.2.2.6 POST AgentBluePrint ApplyBluePrint	28
2.2.2.7 POST AgentBluePrint GenerateBluePrint	
2.2.3 Agent Pools	30
2.2.3.1 DELETE Agent Pools ID 2.2.3.2 GET Agent Pools ID	
2.2.3.3 GET Agent Pools	
2.2.3.4 POST Agent Pools	
2.2.3.5 PUT Agent Pools	
2.2.3.6 GET Agent Pools Agents	38
2.2.4 Alerts	
2.2.4.1 Alerts Denied	
2.2.4.2 Alerts Expiration	
2.2.4.3 Alerts Issued	
2.2.4.4 Alerts Key Rotation	
2.2.4.5 Alerts Pending	
2.2.5 Audit	100
2.2.5.1 GET Audit ID  2.2.5.2 GET Audit ID Validate	107
2.2.5.3 GET Audit	
2.2.5.4 GET Audit Download	
2.2.5.5 GET Audit Related Entities	202
2.2.6 Certificates	. 208
2.2.6.1 GET Certificates ID Security	. 209
2.2.6.2 GET Certificates ID Validate	
2.2.6.3 GET Certificates Locations ID	
2.2.6.4 GET Certificates Identity Audit ID	
2.2.6.5 DELETE Certificates ID	
2.2.6.6 GET Certificates ID	221
2.2.6.7 GET Certificates Metadata Compare	
2.2.6.8 GET Certificates ID History 2.2.6.9 DELETE Certificates	
2.2.6.10 GET Certificates	
2.2.6.11 PUT Certificates Metadata	

2.2.6.12 PUT Certificates Metadata All	
2.2.6.13 POST Certificates Import	255
2.2.6.14 POST Certificates Revoke	
2.2.6.15 POST Certificates Analyze	260
2.2.6.16 POST Certificates Recover	261
2.2.6.17 POST Certificates Download	263
2.2.6.18 POST Certificates Revoke All	265
2.2.6.19 DELETE Certificates Query	
2.2.6.20 DELETE Certificates Private Key	267
2.2.6.21 DELETE Certificates Private Key ID	268
2.2.7 Certificate Authority	269
2.2.7 Certificate Authority	269
2.2.7.2 GET Certificate Authority ID	270
2.2.7.3 GET Certificate Authority	283
2.2.7.4 POST Certificate Authority	
2.2.7.5 PUT Certificate Authority	
2.2.7.6 POST Certificate Authority Test	
2.2.7.7 POST Certificate Authority PublishCRL	351
2.2.8 Certificate Collections	351
2.2.8.1 GET Certificate Collections ID	357
2.2.8.2 GET Certificate Collections Name	353
2.2.8.3 GET Certificate Collections	
2.2.8.4 POST Certificate Collections	
2.2.8.5 PUT Certificate Collections	
2.2.8.6 POST Certificate Collections Copy	247
2.2.8.7 POST Certificate Collections ID Permissions	272
2.2.9 Certificate Stores	
2.2.9.1 DELETE Certificate Stores	
2.2.9.2 GET Certificate Stores	570
2.2.9.3 POST Certificate Stores	
2.2.9.4 PUT Certificate Stores	
2.2.9.5 DELETE Certificate Stores ID	
2.2.9.6 GET Certificate Stores ID	425
2.2.9.7 GET Certificate Stores ID Inventory	438
2.2.9.8 GET Certificate Stores Server	
2.2.9.9 POST Certificate Stores Server	
2.2.9.10 PUT Certificate Stores Server	446
2.2.9.11 PUT Certificate Stores Password	450
2.2.9.12 PUT Certificate Stores Discovery Job	
2.2.9.13 PUT Certificate Stores Assign Container	
2.2.9.14 POST Certificate Stores Approve	466
2.2.9.15 POST Certificate Stores Schedule	475
2.2.9.16 POST Certificate Stores Reenrollment	477
2.2.9.17 POST Certificate Stores Certificates Add	480
2.2.9.18 POST Certificate Stores Certificates Remove	485
2.2.10 Certificate Store Containers	488
2.2.10.1 GET Certificate Store Containers	488
2.2.10.2 POST Certificate Store Containers	491
2.2.10.3 PUT Certificate Store Containers	495
2.2.10.4 DELETE Certificate Store Containers ID	499
2.2.10.5 GET Certificate Store Containers ID	
2.2.11 Certificate Store Types	
2.2.11.1 DELETE Certificate Store Types ID	505
2.2.11.2 GET Certificate Store Types ID	506
2.2.11.3 GET CertificateStoreTypes Name Name	511
2.2.11.4 DELETE Certificate Store Types	
2.2.11.5 GET Certificate Store Types	
2.2.11.6 POST Certificate Store Types	
2.2.11.7 PUT Certificate Store Types	
2.2.11.7 FOT Certificate store types 2.2.12 CSR Generation	
2.2.12.13 DELETE CSR Generation Pending ID	
2.2.12.1 DELETE CSR Generation Pending ID  2.2.12.2 GET CSR Generation Pending ID	
Z.Z.IZ.Z GET CON GEHERARIOH FEHARING ID	

	DELETE CSR Generation Pending	
2.2.12.4	GET CSR Generation Pending	550
2.2.12.5	POST CSR Generation Generate	. 551
2.2.13 Cus	tom Job Types	554
2.2.13.1	DELETE Custom Job Types ID	555
	GET Custom Job Types ID	
	GET Custom Job Types	
	POST Custom Job Types	
	PUT Custom Job Types	
2.2.13.3	ollment	.501
2.2.14 [1110	GET Enrollment Settings ID	505
2.2.14.1	GET Enrollment Settings ID	.500
2.2.14.2	GET Enrollment CSR Content My	5/3
2.2.14.3	GET Enrollment PFX Content My	585
	GET Enrollment Available Renewal ID	
	GET Enrollment Available Renewal Thumbprint	
2.2.14.6	POST Enrollment CSR	600
2.2.14.7	POST Enrollment PFX	605
2.2.14.8	POST Enrollment CSR Parse	.618
	POST Enrollment PFX Deploy	
2.2.14.10	POST Enrollment PFX Replace	625
	POST Enrollment Renew	
	inse	
2.2.13 E166	GET License	620
	CEnrollment	
	GET MacEnrollment	
2.2.10.1	UE1 MUCEITOITTE	(22
	PUT MacEnrollment	
2.2.1/ Met	adataFields	634
2.2.1/.1	DELETE MetadataFields ID	.635
	GET MetadataFields ID	
2.2.17.3	GET MetadataFields Name	639
	GET MetadataFields ID InUse	
	DELETE MetadataFields	
2.2.17.6	GET MetadataFields	643
2.2.17.7	POST MetadataFields	647
	PUT MetadataFields	
	nitoring Revocation	
	DELETE Monitoring Revocation ID	
2.2.10.1	GET Monitoring Revocation ID	660
2.2.10.2	GET Monitoring Revocation	664
	POST Monitoring Revocation	
2.2.10.4	PUT Monitoring Revocation	271
2.2.10.5	POST Monitoring Revocation	0/4
2.2.18.6	POST Monitoring Resolve OSCP	080
2.2.18./	POST Monitoring Revocation Test	.681
2.2.18.8	POST Monitoring Revocation Test All	683
2.2.19 Orc	hestrator Jobs	685
	GET Orchestrator Jobs Job Status Data	
	GET Orchestrator Jobs Job History	
2.2.19.3	GET Orchestrator Jobs Scheduled Jobs	692
	POST Orchestrator Jobs Custom	
	POST Orchestrator Jobs Reschedule	
	POST Orchestrator Jobs Unschedule	
	POST Orchestrator Jobs Acknowledge	
2.2.17.7	POST Orchestrator Jobs Custom Bulk	704
	W Providers	
	DELETE PAM Providers ID	
	GET PAM Providers ID	
2.2.20.3	GET PAM Providers Types	./ 18
	POST PAM Providers Types	
	GET PAM Providers	
	POST PAM Providers	
	PUT PAM Providers	
2.2.21 Rep	orts	765

0.004.0 DELETE D	766
2.2.21.2 DELETE Reports Custom ID	
2.2.21.3 GET Reports Custom ID	773
2.2.21.4 DELETE Reports Schedules ID	
2.2.21.5 GET Reports Schedules ID	
2.2.21.6 GET Reports ID Parameters	
2.2.21.7 PUT Reports ID Parameters	
2.2.21.8 GET Reports	782
2.2.21.9 PUT Reports	
2.2.21.10 GET Reports Custom	
2.2.21.11 POST Reports Custom	790
2.2.21.12 PUT Reports Custom	/92
2.2.21.13 GET Reports ID Schedules	
2.2.21.14 POST Reports ID Schedules	
2.2.21.15 PUT Reports ID Schedules	
2.2.22 Security Identities 2.2.22.1 DELETE Security Identities ID	015
2.2.22.1 GET Security Identities ID	
2.2.22.3 GET Security Identities ID	010
2.2.22.4 GET Security Identities Lookup	820
2.2.22.5 POST Security Identities	
2.2.23 Security Roles Permissions	
2.2.23.1 GET Security Roles ID Permissions	
2.2.23.2 GET Security Roles ID Permissions Global	
2.2.23.3 POST Security Roles ID Permissions Global	844
2.2.23.4 PUT Security Roles ID Permissions Global	864
2.2.23.5 GET Security Roles ID Permissions Containers	885
2.2.23.6 POST Security Roles ID Permissions Containers	886
2.2.23.7 PUT Security Roles ID Permissions Containers	
2.2.23.8 GET Security Roles ID Permissions Collections	
2.2.23.9 POST Security Roles ID Permissions Collections	
2.2.23.10 PUT Security Roles ID Permissions Collections	891
2.2.24 Security Roles	893
2.2.24.1 DELETE Security Roles ID	
	894
2.2.24.2 GET Security Roles ID	895
2.2.24.2 GET Security Roles ID	895 897
2.2.24.2 GET Security Roles ID 2.2.24.3 GET Security Roles ID Identities 2.2.24.4 PUT Security Roles ID Identities	895 897 898
2.2.24.2 GET Security Roles ID 2.2.24.3 GET Security Roles ID Identities 2.2.24.4 PUT Security Roles ID Identities 2.2.24.5 GET Security Roles	895 897 898 898
2.2.24.2 GET Security Roles ID 2.2.24.3 GET Security Roles ID Identities 2.2.24.4 PUT Security Roles ID Identities 2.2.24.5 GET Security Roles 2.2.24.6 POST Security Roles	895 897 898 898
2.2.24.2 GET Security Roles ID 2.2.24.3 GET Security Roles ID Identities 2.2.24.4 PUT Security Roles ID Identities 2.2.24.5 GET Security Roles 2.2.24.6 POST Security Roles 2.2.24.7 PUT Security Roles	
2.2.24.2 GET Security Roles ID 2.2.24.3 GET Security Roles ID Identities 2.2.24.4 PUT Security Roles ID Identities 2.2.24.5 GET Security Roles 2.2.24.6 POST Security Roles 2.2.24.7 PUT Security Roles 2.2.24.8 POST Security Roles ID Copy	
2.2.24.2 GET Security Roles ID 2.2.24.3 GET Security Roles ID Identities 2.2.24.4 PUT Security Roles ID Identities 2.2.24.5 GET Security Roles 2.2.24.6 POST Security Roles 2.2.24.7 PUT Security Roles 2.2.24.8 POST Security Roles ID Copy 2.2.25 SSH	
2.2.24.2 GET Security Roles ID 2.2.24.3 GET Security Roles ID Identities 2.2.24.4 PUT Security Roles ID Identities 2.2.24.5 GET Security Roles 2.2.24.6 POST Security Roles 2.2.24.7 PUT Security Roles 2.2.24.8 POST Security Roles ID Copy 2.2.25 SSH 2.2.25.1 SSH Keys	
2.2.24.2 GET Security Roles ID 2.2.24.3 GET Security Roles ID Identities 2.2.24.4 PUT Security Roles ID Identities 2.2.24.5 GET Security Roles 2.2.24.6 POST Security Roles 2.2.24.7 PUT Security Roles 2.2.24.8 POST Security Roles ID Copy 2.2.25 SSH 2.2.25 SSH 2.2.25.1 SSH Keys 2.2.25.2 SSH Logons	
2.2.24.2 GET Security Roles ID 2.2.24.3 GET Security Roles ID Identities 2.2.24.4 PUT Security Roles ID Identities 2.2.24.5 GET Security Roles 2.2.24.6 POST Security Roles 2.2.24.7 PUT Security Roles 2.2.24.8 POST Security Roles ID Copy 2.2.25 SSH 2.2.25.1 SSH Keys 2.2.25.3 SSH Logons 2.2.25.3 SSH Servers	
2.2.24.2 GET Security Roles ID 2.2.24.3 GET Security Roles ID Identities 2.2.24.4 PUT Security Roles ID Identities 2.2.24.5 GET Security Roles 2.2.24.6 POST Security Roles 2.2.24.7 PUT Security Roles 2.2.24.8 POST Security Roles ID Copy 2.2.25 SSH 2.2.25.1 SSH Keys 2.2.25.2 SSH Logons 2.2.25.3 SSH Servers 2.2.25.4 SSH Server Groups	
2.2.24.2 GET Security Roles ID 2.2.24.3 GET Security Roles ID Identities 2.2.24.4 PUT Security Roles ID Identities 2.2.24.5 GET Security Roles 2.2.24.6 POST Security Roles 2.2.24.7 PUT Security Roles 2.2.24.8 POST Security Roles ID Copy 2.2.25 SSH 2.2.25.1 SSH Keys 2.2.25.2 SSH Logons 2.2.25.3 SSH Servers 2.2.25.4 SSH Server Groups 2.2.25.5 SSH Service Accounts	
2.2.24.2 GET Security Roles ID 2.2.24.3 GET Security Roles ID Identities 2.2.24.4 PUT Security Roles ID Identities 2.2.24.5 GET Security Roles 2.2.24.6 POST Security Roles 2.2.24.7 PUT Security Roles 2.2.24.8 POST Security Roles ID Copy 2.2.25 SSH 2.2.25.1 SSH Keys 2.2.25.2 SSH Logons 2.2.25.3 SSH Servers 2.2.25.3 SSH Server Groups 2.2.25.5 SSH Service Accounts 2.2.25.6 SSH Users	
2.2.24.2 GET Security Roles ID 2.2.24.3 GET Security Roles ID Identities 2.2.24.4 PUT Security Roles ID Identities 2.2.24.5 GET Security Roles 2.2.24.6 POST Security Roles 2.2.24.7 PUT Security Roles 2.2.24.8 POST Security Roles ID Copy 2.2.25 SSH 2.2.25.1 SSH Keys 2.2.25.2 SSH Logons 2.2.25.3 SSH Servers 2.2.25.3 SSH Servers 2.2.25.4 SSH Server Groups 2.2.25.5 SSH Service Accounts 2.2.25.6 SSH Users 2.2.26 SMTP	
2.2.24.2 GET Security Roles ID 2.2.24.3 GET Security Roles ID Identities 2.2.24.4 PUT Security Roles ID Identities 2.2.24.5 GET Security Roles 2.2.24.6 POST Security Roles 2.2.24.7 PUT Security Roles 2.2.24.8 POST Security Roles 2.2.25.1 SSH 2.2.25.1 SSH Keys 2.2.25.2 SSH Logons 2.2.25.2 SSH Logons 2.2.25.3 SSH Servers 2.2.25.3 SSH Servers 2.2.25.4 SSH Server Groups 2.2.25.5 SSH Service Accounts 2.2.25.6 SSH Users 2.2.26.1 GET SMTP	
2.2.24.2 GET Security Roles ID 2.2.24.3 GET Security Roles ID Identities 2.2.24.4 PUT Security Roles ID Identities 2.2.24.5 GET Security Roles 2.2.24.6 POST Security Roles 2.2.24.7 PUT Security Roles 2.2.24.8 POST Security Roles 2.2.25 SSH 2.2.25.1 SSH Keys 2.2.25.2 SSH Logons 2.2.25.2 SSH Logons 2.2.25.3 SSH Servers 2.2.25.3 SSH Servers 2.2.25.4 SSH Server Groups 2.2.25.5 SSH Service Accounts 2.2.25.6 SSH Users 2.2.26.1 GET SMTP 2.2.26.1 GET SMTP 2.2.26.2 PUT SMTP	
2.2.24.2 GET Security Roles ID 2.2.24.3 GET Security Roles ID Identities 2.2.24.4 PUT Security Roles ID Identities 2.2.24.5 GET Security Roles 2.2.24.6 POST Security Roles 2.2.24.7 PUT Security Roles 2.2.24.8 POST Security Roles 2.2.25 SSH 2.2.25.1 SSH Keys 2.2.25.2 SSH Logons 2.2.25.2 SSH Logons 2.2.25.3 SSH Servers 2.2.25.3 SSH Server Groups 2.2.25.4 SSH Service Accounts 2.2.25.5 SSH Users 2.2.26.6 SMTP 2.2.26.1 GET SMTP 2.2.26.3 POST SMTP Test	
2.2.24.2 GET Security Roles ID 2.2.24.3 GET Security Roles ID Identities 2.2.24.4 PUT Security Roles ID Identities 2.2.24.5 GET Security Roles 2.2.24.6 POST Security Roles 2.2.24.7 PUT Security Roles 2.2.24.8 POST Security Roles 2.2.25.1 SSH Keys 2.2.25 SSH 2.2.25.1 SSH Keys 2.2.25.2 SSH Logons 2.2.25.3 SSH Servers 2.2.25.3 SSH Servers 2.2.25.4 SSH Server Groups 2.2.25.5 SSH Service Accounts 2.2.25.6 SSH Users 2.2.26.1 GET SMTP 2.2.26.3 POST SMTP Test 2.2.26.3 POST SMTP Test 2.2.27 SSL	
2.2.24.2 GET Security Roles ID 2.2.24.3 GET Security Roles ID Identities 2.2.24.4 PUT Security Roles ID Identities 2.2.24.5 GET Security Roles 2.2.24.6 POST Security Roles 2.2.24.7 PUT Security Roles 2.2.24.8 POST Security Roles 2.2.25.1 SSH Keys 2.2.25 SSH 2.2.25.1 SSH Keys 2.2.25.2 SSH Logons 2.2.25.2 SSH Servers 2.2.25.3 SSH Servers 2.2.25.4 SSH Server Groups 2.2.25.5 SSH Service Accounts 2.2.25.6 SSH Users 2.2.26.1 GET SMTP 2.2.26.1 GET SMTP 2.2.26.3 POST SMTP Test 2.2.27 SSL 2.2.27 SSL 2.2.27 SSL 2.2.27.1 GET SSL Parts ID	
2.2.24.2 GET Security Roles ID 2.2.24.3 GET Security Roles ID Identities 2.2.24.4 PUT Security Roles ID Identities 2.2.24.5 GET Security Roles 2.2.24.6 POST Security Roles 2.2.24.7 PUT Security Roles 2.2.24.8 POST Security Roles ID Copy 2.2.25 SSH 2.2.25.1 SSH Keys 2.2.25.2 SSH Logons 2.2.25.3 SSH Servers 2.2.25.3 SSH Servers 2.2.25.4 SSH Server Groups 2.2.25.5 SSH Users 2.2.25.6 SSH Users 2.2.26.1 GET SMTP 2.2.26.1 GET SMTP 2.2.26.3 POST SMTP Test 2.2.27 SSL 2.2.27 SSL 2.2.27 SSL 2.2.27.1 GET SSL Parts ID 2.2.27.2 GET SSL Endpoints ID	
2.2.24.2 GET Security Roles ID 2.2.24.3 GET Security Roles ID Identities 2.2.24.4 PUT Security Roles ID Identities 2.2.24.5 GET Security Roles 2.2.24.6 POST Security Roles 2.2.24.7 PUT Security Roles 2.2.24.8 POST Security Roles 2.2.25.1 SSH Keys 2.2.25.1 SSH Keys 2.2.25.2 SSH Logons 2.2.25.3 SSH Servers 2.2.25.4 SSH Server Groups 2.2.25.5 SSH Service Accounts 2.2.25.6 SSH Users 2.2.26 SMTP 2.2.26.3 POST SMTP 2.2.26.3 POST SMTP Test 2.2.27 SSL 2.2.27.1 GET SSL Parts ID 2.2.27.2 GET SSL Endpoints ID 2.2.27.3 DELETE SSL NetworkRanges ID	
2.2.24.2 GET Security Roles ID 2.2.24.3 GET Security Roles ID Identities 2.2.24.4 PUT Security Roles ID Identities 2.2.24.5 GET Security Roles 2.2.24.6 POST Security Roles 2.2.24.7 PUT Security Roles 2.2.24.8 POST Security Roles 2.2.25.1 SSH Keys 2.2.25.1 SSH Keys 2.2.25.2 SSH Logons 2.2.25.3 SSH Servers 2.2.25.4 SSH Server Groups 2.2.25.5 SSH Service Accounts 2.2.25.6 SSH Users 2.2.26.3 POST SMTP 2.2.26.1 GET SMTP 2.2.26.2 PUT SMTP 2.2.26.3 POST SMTP Test 2.2.27.1 GET SSL Parts ID 2.2.27.2 GET SSL Endpoints ID 2.2.27.3 DELETE SSL NetworkRanges ID 2.2.27.4 GET SSL NetworkRanges ID	
2.2.24.2 GET Security Roles ID 2.2.24.3 GET Security Roles ID Identities 2.2.24.4 PUT Security Roles ID Identities 2.2.24.5 GET Security Roles 2.2.24.6 POST Security Roles 2.2.24.7 PUT Security Roles 2.2.24.8 POST Security Roles 2.2.25.8 SSH 2.2.25.1 SSH Keys 2.2.25.2 SSH Logons 2.2.25.3 SSH Servers 2.2.25.3 SSH Server Groups 2.2.25.4 SSH Server Groups 2.2.25.5 SSH Service Accounts 2.2.25.6 SSH Users 2.2.25.6 SSH Users 2.2.25.7 SSL SSH Service Accounts 2.2.25.6 SSH Users 2.2.26.1 GET SMTP 2.2.26.2 PUT SMTP 2.2.26.3 POST SMTP Test 2.2.27.3 DELETE SSL NetworkRanges ID 2.2.27.3 DELETE SSL NetworkRanges ID 2.2.27.5 GET SSL NetworkRanges ID 2.2.27.5 GET SSL NetworkRanges ID 2.2.27.5 GET SSL NetworkRanges ID	
2.2.24.2 GET Security Roles ID 2.2.24.3 GET Security Roles ID Identities 2.2.24.4 PUT Security Roles ID Identities 2.2.24.5 GET Security Roles 2.2.24.6 POST Security Roles 2.2.24.7 PUT Security Roles 2.2.24.8 POST Security Roles 2.2.25.2 SSH 2.2.25.1 SSH Keys 2.2.25.2 SSH Logons 2.2.25.3 SSH Servers 2.2.25.3 SSH Servers 2.2.25.4 SSH Server Groups 2.2.25.5 SSH Service Accounts 2.2.25.6 SSH Users 2.2.26.7 SSH Users 2.2.26.8 MTP 2.2.26.1 GET SMTP 2.2.26.1 PUT SMTP 2.2.26.2 PUT SMTP 2.2.26.3 POST SMTP Test 2.2.27.3 DELETE SSL NetworkRanges ID 2.2.27.3 DELETE SSL NetworkRanges ID 2.2.27.5 GET SSL Networks Identifier 2.2.27.6 GET SSL	
2.2.24.2 GET Security Roles ID 2.2.24.3 GET Security Roles ID Identities 2.2.24.4 PUT Security Roles ID Identities 2.2.24.5 GET Security Roles 2.2.24.6 POST Security Roles 2.2.24.7 PUT Security Roles 2.2.24.8 POST Security Roles 2.2.25.8 SSH 2.2.25.1 SSH Keys 2.2.25.2 SSH Logons 2.2.25.3 SSH Servers 2.2.25.3 SSH Server Groups 2.2.25.4 SSH Server Groups 2.2.25.5 SSH Service Accounts 2.2.25.6 SSH Users 2.2.25.6 SSH Users 2.2.25.7 SSL SSH Service Accounts 2.2.25.6 SSH Users 2.2.26.1 GET SMTP 2.2.26.2 PUT SMTP 2.2.26.3 POST SMTP Test 2.2.27.3 DELETE SSL NetworkRanges ID 2.2.27.3 DELETE SSL NetworkRanges ID 2.2.27.5 GET SSL NetworkRanges ID 2.2.27.5 GET SSL NetworkRanges ID 2.2.27.5 GET SSL NetworkRanges ID	

2.2.27.10 GET SSL Endpoints ID History	1139
2.2.27.11 GET SSL Networks ID Parts	1145
2.2.27.12 POST SSL NetworkRanges	1146
2.2.27.13 PUT SSL NetworkRanges	1147
2.2.27.14 PUT SSL Endpoints Review Status	1147
2.2.27.15 PUT SSL Endpoints Monitor Status	1148
2.2.27.16 PUT SSL Endpoints Review All	
2.2.27.17 PUT SSL Endpoints Monitor All	11/10
2.2.27.18 POST SSL Networks ID Scan	
2.2.27.19 POST SSL Networks ID Reset	1150
2.2.27.20 POST SSL NetworkRanges Validate	1150
2.2.27.21 DELETE SSL Networks ID	
2.2.28 Status	
2.2.28.1 GET Status Endpoints	
2.2.29 Templates	
2.2.29.1 GET Templates ID	
2.2.29.2 GET Templates Settings	
2.2.29.3 PUT Templates Settings	1171
2.2.29.4 GET Templates Subject Parts	1184
2.2.29.5 GET Templates	
2.2.29.6 PUT Templates	
2.2.29.7 POST Templates/Import	1222
2.2.30 Workflow Certificates	1222
2.2.30.1 GET Workflow Certificates ID	
2.2.30.2 GET Workflow Certificates Denied	1225
2.2.30.3 GET Workflow Certificates Pending	
2.2.30.4 GET Workflow Certificates External Validation	1229
2.2.30.5 POST Workflow Certificates Deny	
2.2.30.6 POST Workflow Certificates Approve	
2.2.31 Workflow Definitions	
2.2.31.1 GET Workflow Definitions Steps Extension Name	1234
2.2.31.2 DELETE Workflow Definitions Definition ID 2.2.31.3 GET Workflow Definitions Definition ID	1220
2.2.31.4 PUT Workflow Definitions Definition ID	
2.2.31.5 GET Workflow Definitions	
2.2.31.6 POST Workflow Definitions	
2.2.31.7 GET Workflow Definitions Steps	
2.2.31.8 GET Workflow Definitions Types	. 1289
2.2.31.9 PUT Workflow Definitions Definition ID Steps	1291
2.2.31.10 POST Workflow Definitions Definition ID Publish	
2.2.32 Workflow Instances	1325
2.2.32.1 DELETE Workflow Instances Instance Id	. 1326
2.2.32.2 GET Workflow Instances Instance ID	
2.2.32.3 GET Workflow Instances	
2.2.32.4 GET Workflow Instances My	1351
2.2.32.5 GET Workflow Instances AssignedToMe	. 1354
2.2.32.6 POST Workflow Instances Instance Id Stop	
2.2.32.7 POST Workflow Instances Instance ID Signals	
2.2.32.8 POST Workflow Instances Instance Id Restart	
2.3 Classic API	
2.3.1 Security Role Overview	
2.3.2 ApiApp	
2.3.2.1 ApiAPP GetApiApps	1364
2.3.2.2 ApiApp AddApiApp	
2.3.2.3 ApiApp EditApiApp	
2.3.2.4 ApiApp DeleteApiApp	
2.3.3 CertEnroll	
2.3.3.1 CertEnroll Token	13/1
2.3.3.2 CertEnroll Templates	
2.3.3.3 CertEnroll Pkcs10	
2.3.3.4 CertEnroll Pkcs12	
2335 CertEnroll Renew	1381

2.3.4 Certificates	1382
2.3.4.1 Certificates Metafield	1383
2.3.4.2 Certificates Import	1384
2.3.4.3 Certificates Contents	1385
2.3.4.4 Certificates PublishCRL	
2.3.4.5 Certificates Recover	
2.3.4.6 Certificates Revoke	
2.3.4.7 Certificates Search and Count	1388
2.3.5 Certstore	1391
2.3.5.1 CertStore AddCert	
2.3.5.2 CertStore AddCertStore	
2.3.5.3 CertStore AddCertStore  2.3.5.3 CertStore AddCertStore	1207
2.3.5.4 CertStore AddCertStoreType	
2.3.5.5 CertStore AddCertStorerype	1405
2.3.5.6 CertStore AddPFA	1403
2.3.5.7 CertStore EditCertStore	1407
2.3.5.8 CertStore EditCertStoreServer	
2.3.5.9 CertStore GetCertStoreTypes	1408
2.3.5.10 CertStore Inventory	1409
2.3.5.11 CertStore Keystores	
2.3.5.12 CertStore Remove	
2.3.5.13 CertStore ScheduleInventory	
2.3.6 Metadata	1414
2.3.6.1 Metadata V2	
2.3.6.2 Metadata V3	
2.3.7 Security	
2.3.7.1 Security GetIdentities	
2.3.7.2 Security AddIdentity	1423
2.3.7.3 Security DeleteIdentity	1424
2.3.7.4 Security GetRoles	1424
2.3.7.5 Security AddRole	
2.3.7.6 Security EditRole	1428
2.3.7.7 Security DeleteRole	1429
2.3.8 SSL	
2.3.8.1 SSL AddEndpoint	
2.3.8.2 SSL AddEndpointGroup	1431
2.3.8.3 SSL Agents	1432
2.3.8.4 SSL EndpointGroups	
2.3.9 Workflow	1433
2.3.9.1 Workflow Approve and Deny	1434
2.3.9.2 PendingList	1437
2.3.10 Workflow Expiration Alerts	1440
2.3.10.1 Workflow Expiration Alerts Endpoints	1440
2.3.10.2 Workflow Expiration Alert Event Handler Parameters API	1444
2.3.10.3 Workflow Expiration Alert Registered Event Handlers API	1448
2.3.10.4 Workflow Expiration Alert Schedule API	
2.3.11 Status	
2.3.12 vSCEP	
2.4 API Change Log	
2.4.1 v9 API Change Log	
2.4.1.1 API Change Log v9.0	
2.4.1.2 API Change Log v9.1	
2.4.1.3 API Change Log v9.2	
2.4.1.4 API Change Log v9.3	
2.4.1.5 API Change Log v9.4	
2.4.1.6 API Change Log v9.5	
2.4.1.7 API Change Log v9.6	
2.4.1.8 API Change Log v9.7	
2.4.1.9 API Change Log v9.8	
2.4.1.10 API Change Log v9.9	
2.4.2 v10 API Change Log	
2.4.2.1 API Change Log v10.0	1458

3.0	Glossary	1464
4.0	Copyright Notice	1472

# List of Figures

Figure 1: Documentation in the Help Dropdown	8
Figure 2: Microsoft Issuance Requirements on a Template for Manager Approval	1163
Figure 3: Microsoft Issuance Requirements on a Template for Manager Approval	1194
Figure 4: Microsoft Issuance Requirements on a Template for Manager Approval	1208
Figure 5: Microsoft Issuance Requirements on a Template for Manager Approval	1220
Figure 6: Pkcs#10-Based Enrollment Request	1373
Figure 7: Pkcs#12-Based Enrollment Request	1377

## List of Tables

Table 1: Common Request Headers	3
Table 2: Common Response Headers	4
Table 3: HTTP Statuses	5
Table 4: Classic API Certificate Lookup Structure	5
Table 5: Agents Endpoints	8
Table 6: GET Agents{id} Input Parameters	9
Table 7: GET Agent {id} Response Data	10
Table 8: GET Agents Input Parameters	13
Table 9: GET Agent Response Data	14
Table 10: POST Agents Reset Input Parameters	17
Table 11: POST Agents Approve Input Parameters	17
Table 12: POST Agents Disapprove Input Parameters	17
Table 13: POST Agents {id} Reset Input Parameters	18
Table 14: POST Agents {id} FetchLogs Input Parameters	18
Table 15: POST Agents Set Auth Certificate Reenrollment Input Parameters	19
Table 16: POST Agents Set Auth Certificate Reenrollment Response Data	20
Table 17: Agent BluePrint Endpoints	20
Table 18: DELETE AgentBluePrint {id} Input Parameters	21
Table 19: GET AgentBluePrint {id} Input Parameters	22
Table 20: GET AgentBluePrint {id} Response Data	22
Table 21: GET AgentBluePrint Input Parameters	22
Table 22: GET AgentBluePrint Response Data	23
Table 23: GET AgentBluePrint {id} Jobs Input Parameters	23
Table 24: GET AgentBluePrint {id} Jobs Response Data	24
Table 25: GET AgentBluePrint {id} Stores Input Parameters	27
Table 26: GET AgentBluePrint {id} Stores Response Data	28
Table 27: POST AgentBluePrint Apply Input Parameters	29
Table 28: POST AgentBluePrint Generate Input Parameters	29
Table 29: POST AgentBluePrint Generate Response Data	30
Table 30: Agent Pool Endpoints	30
Table 31: DELETE AgentPools {id} Input Parameters	31
Table 32: GET AgentPools {id} Input Parameters	31
Table 33: GET AgentPools {id} Response Data	32
Table 34: GET AgentPools Input Parameters	33
Table 35: GET AgentPools Response Data	34
Table 36: POST AgentPools Input Parameters	35
Table 37: POST AgentPools Response Data	36
Table 38: PUT AgentPools Input Parameters	37
Table 39: PUT AgentPools Response Data	38
Table 40: GET AgentPools Default Agent Pool Agents Input Parameters	39
Table 41: GET AgentPools Default Agent Pool Agents Response Data	40
Table 42: Alerts Denied	40
Table 43: DELETE Alerts Denied {id} Input Parameters	41
Table 44: GET Alerts Denied {id} Input Parameters	42
Table 45: GET Alerts Denied {id} Response Data	43
Table 46: GET Alerts Denied Input Parameters	46
Table 47: GET Alerts Denied Response Data	47
Table 48: POST Alerts Denied Input Parameters	50
Table 49: POST Alerts Denied Response Data	54
Table 50: PUT Alerts Denied Input Parameters	58
Table 51: PUT Alerts Denied Response Data	62
Table 52: Alerts Expiration	64
Table 53: DELETE Alerts Expiration (id) Input Parameters	65

Table 54: GET Alerts Expiration (id) Input Parameters	66
Table 55: GET Alerts Expiration {id} Response Data	67
Table 56: GET Alerts Expiration Schedule Response Data	70
Table 57: PUT Alerts Expiration Schedule Input Parameters	71
Table 58: PUT Alerts Expiration Schedule Response Data	72
Table 59: GET Alerts Expiration Input Parameters	73
Table 60: GET Alerts Expiration Response Data	74
Table 61: POST Alerts Expiration Input Parameters	77
Table 62: POST Alerts Expiration Response Data	81
Table 63: PUT Alerts Expiration Input Parameters	84
Table 64: PUT Alerts Expiration Response Data	88
Table 65: POST Alerts Expiration Test Input Parameters	91
Table 66: POST Alerts Expiration Test Response Data	92
Table 67: POST Alerts Expiration Test All Input Parameters	93
Table 68: POST Alerts Expiration Test All Response Data	94
Table 69: Alerts Issued	94
Table 70: DELETE Alerts Issued (id) Input Parameters	95
Table 71: GET Alerts Issued (id) Input Parameters	96
Table 72: GET Alerts Issued (id) Response Data	97
Table 73: GET Alerts Issued Schedule Response Data	101
Table 74: PUT Alerts Issued Schedule Input Parameters	102
Table 75: PUT Alerts Issued Schedule Response Data	103
Table 76: GET Alerts Issued Input Parameters Table 77: GET Alerts Issued Response Data	104 105
Table 77: GET Alerts Issued Response Data  Table 78: POST Alerts Issued Input Parameters	109
Table 79: POST Alerts Issued Response Data	113
Table 80: PUT Alerts Issued Input Parameters	117
Table 81: PUT Alerts Issued Response Data	121
Table 82: Alerts Key Rotation	124
Table 83: DELETE Alerts Key Rotation (id) Input Parameters	125
Table 84: GET Alerts Key Rotation (id) Input Parameters	125
Table 85: GET Alerts Key Rotation (id) Response Data	126
Table 86: GET Alerts Key Rotation Schedule Response Data	129
Table 87: PUT Alerts Key Rotation Schedule Input Parameters	130
Table 88: PUT Alerts Key Rotation Schedule Response Data	131
Table 89: GET Alerts Key Rotation Input Parameters	132
Table 90: GET Alerts Key Rotation Response Data	133
Table 91: POST Alerts Key Rotation Input Parameters	136
Table 92: POST Alerts Key Rotation Response Data	140
Table 93: PUT Alerts Key Rotation Input Parameters	143
Table 94: PUT Alerts Key Rotation Response Data	147
Table 95: POST Alerts Key Rotation Test Input Parameters	150
Table 96: POST Alerts Key Rotation Test Response Data	151
Table 97: POST Alerts Key Rotation Test All Input Parameters	152
Table 98: POST Alerts Key Rotation Test All Response Data	153
Table 99: Alerts Pending	153
Table 100: DELETE Alerts Pending (id) Input Parameters	154
Table 101: GET Alerts Pending {id} Input Parameters	155
Table 102: GET Alerts Pending {id} Response Data	156
Table 103: GET Alerts Pending Schedule Response Data	160
Table 104: PUT Alerts Pending Schedule Input Parameters	161
Table 105: PUT Alerts Pending Schedule Response Data	162
Table 106: GET Alerts Pending Input Parameters	163
Table 107: GET Alerts Pending Response Data	164
Table 108: POST Alerts Pending Input Parameters	168
Table 109: POST Alerts Pending Response Data	172
Table 110: PUT Alerts Pendina Input Parameters	176

Table 111: PUT Alerts Pending Response Data	180
Table 112: POST Alerts Pending Test Input Parameters	185
Table 113: POST Alerts Pending Test Response Data	185
Table 114: POST Alerts Pending Test All Input Parameters	187
Table 115: POST Alerts Pending Test All Response Data	188
Table 116: Audit Endpoints	189
Table 117: GET Audit (id) Input Parameters	189
Table 118: GET Audit {id} Response Data	190
Table 119: GET Audit {id} Validate Input Parameters	194
Table 120: GET Audit {id} Validate Response Data	194
Table 121: GET Audit Input Parameters	195
Table 122: GET Audit Response Data	196
Table 123: GET Audit Download Input Parameters	200
Table 124: GET Audit Download Response Data	201
Table 125: GET Audit Related Entities Input Parameters	203
Table 126: GET Audit Related Entities Response Data	204
Table 127: Certificates Endpoints	208
Table 128: GET Certificates {id} Security Input Parameters	210
Table 129: GET Certificates {id} Security Response Data	210
Table 130: GET Certificates {id} Validate Input Parameters	211
Table 131: GET Certificates {id} Validate Response Data	212
Table 132: GET Certificates Locations (id) Input Parameters	217
Table 133: GET Certificates Locations (id) Response Data	218
Table 134: GET Certificates (id) History Input Parameters	220
Table 135: GET Certificates (id) History Response Data	220
Table 136: DELETE Certificates (id) Input Parameters	221
Table 137: GET Certificates (id) Input Parameters	222 223
Table 138: GET Certificates {id} Response Data Table 139: GET Certificates Metadata Compare Input Parameters	234
Table 139: GET Certificates Metadata Compare input Parameters  Table 140: GET Certificates {id} History Input Parameters	235
Table 140: GET Certificates {id} History Response Data	236
Table 142: DELETE Certificates Input Parameters	237
Table 143: GET Certificates Input Parameters	238
Table 144: GET Certificates Response Data	241
Table 145: PUT Certificates Metadata Input Parameters	251
Table 146: PUT Certificates Metadata All Input Parameters	252
Table 147: POST Certificates Import Input Parameters	256
Table 148: POST Certificates Import Response Data	258
Table 149: POST Certificates Revoke Input Parameters	259
Table 150: POST Certificates Analyze Input Parameters	260
Table 151: POST Certificates Analyze Response Data	260
Table 152: POST Certificates Recover Input Parameters	262
Table 153: POST Certificates Recover Response Data	263
Table 154: POST Certificates Download Input Parameters	264
Table 155: POST Certificates Download Response Data	265
Table 156: POST Certificates Revoke All Input Parameters	265
Table 157: DELETE Certificates Query Input Parameters	267
Table 158: DELETE Certificates Private Key Input Parameters	268
Table 159: DELETE Certificates Private Key {id} Input Parameters	268
Table 160: Certificate Authority Endpoints	269
Table 161: DELETE Certificate Authority (id) Input Parameters	269
Table 162: GET Certificate Authority (id) Input Parameters	270
Table 163: GET Certificate Authority {id} Response Data	271
Table 164: GET Certificate Authority Input Parameters	283
Table 165: GET Certificate Authority Response Data	284
Table 166: POST Certificate Authority Input Parameters	297
Table 167: POST Certificate Authority Response Data	310

Table 168: PUT Certificate Authority Input Parameters	323
Table 169: PUT Certificate Authority Response Data	337
Table 170: POST Certificate Authority Test Input Parameters	350
Table 171: POST Certificate Authority Test Response Data	351
Table 172: POST Certificate Authority PublishCRL Input Parameters	351
Table 173: Certificate Collections Endpoints	351
Table 174: GET CertificateCollections (id) Input Parameters	352
Table 175: GET CertificateCollections {id} Response Data	353
Table 176: GET CertificateCollections Name Input Parameters	354
Table 177: GET CertificateCollections ID Response Data	355
Table 178: GET Certificate Collections Input Parameters	356
Table 179: GET CertificateCollections Response Data	357
Table 180: POST Certificate Collections Input Parameters	359
Table 181: POST Certificate Collections Response Data	363
Table 182: PUT CertificateCollections Input Parameters	365
Table 183: PUT CertificateCollections Response Data	367
Table 184: POST Certificate Collections Copy Input Parameters	369
Table 185: POST Certificate Collections Copy Response Data	373
Table 186: POST CertificateCollections (id) Permissions Input Parameters	374
Table 187: Certificate Stores Endpoints	375
Table 188: DELETE Certificate Stores Input Parameters	377
Table 189: GET Certificate Stores Input Parameters	378
Table 190: GET Certificate Stores Response Data	379 386
Table 191: POST Certificate Stores Input Parameters Table 192: POST Certificate Stores Response Data	399
	406
Table 193: PUT Certificate Stores Input Parameters Table 194: PUT Certificate Stores Response Data	419
Table 195: DELETE Certificate Stores Input Parameters	425
Table 196: GET Certificate Stores (id) Input Parameters	425
Table 197: GET Certificate Stores (id) Response Data	426
Table 198: GET Certificate Stores (id) Inventory Input Parameters	438
Table 199: GET Certificate Stores (id) Inventory Response Data	439
Table 200: GET Certificate Stores Server Input Parameters	440
Table 201: GET Certificate Stores Server Response Data	441
Table 202: POST Certificate Stores Server Input Parameters	443
Table 203: POST Certificate Stores Server Response Data	446
Table 204: PUT Certificate Stores Server Input Parameters	448
Table 205: PUT Certificate Stores Server Response Data	450
Table 206: PUT Certificate Stores Password Input Parameters	452
Table 207: PUT Certificate Stores Discovery Job Input Parameters	454
Table 208: PUT Certificate Stores Assign Container Input Parameters	460
Table 209: PUT Certificate Stores Assign Container Response Data	461
Table 210: POST Certificate Stores Approve Input Parameters	468
Table 211: POST Certificate Stores Schedule Input Parameters	476
Table 212: POST Certificates Stores Reenrollment Input Parameters	479
Table 213: POST Certificate Stores Certificates Add Input Parameters	481
Table 214: POST Certificate Stores Certificates Remove Input Parameters	486
Table 215: Certificate Store Containers Endpoints	488
Table 216: GET Certificate Store Containers Input Parameters	489
Table 217: GET Certificate Stores Containers Response Data	490
Table 218: POST Certificate Stores Containers Input Parameters	492
Table 219: POST Certificate Stores Containers Response Data	494
Table 220: PUT Certificate Store Containers Input Parameters	496
Table 221: PUT Certificate Store Containers Response Data	498
Table 222: DELETE Certificate Store Containers {id} Input Parameters	499
Table 223: GET Certificate Store Containers {id} Input Parameters	500
Table 224: GFT Certificate Stores Containers (id) Response Data	501

Table 225: Certificate Store Type Endpoints	505
Table 226: DELETE Certificate Store Types {id} Input Parameters	506
Table 227: GET Certificate Store Types {id} Input Parameters	506
Table 228: GET Certificate Store Types {id} Response Data	507
Table 229: GET Certificate Store Types Name {ShortName} Input Parameters	512
Table 230: GET Certificate Store Types Name {ShortName} Response Data	513
Table 231: DELETE Certificate Store Types Input Parameters	518
Table 232: GET Certificate Store Types Input Parameters	518
Table 233: GET Certificate Store Types Response Data	519
Table 234: POST Certificate Store Types Input Parameters	524
Table 235: POST Certificate Store Types Response Data	531
Table 236: PUT Certificate Store Types Input Parameters	537
Table 237: PUT Certificate Store Types Response Data	544
Table 238: CSR Generation Endpoints	548
Table 239: DELETE CSR Generation Pending {id} Input Parameters	549
Table 240: GET CSR Generation Pending (id) Input Parameters	549
Table 241: GET CSR Generation Pending (id) Response Data	550
Table 242: DELETE CSR Generation Pending Input Parameters	550
Table 243: GET CSR Generation Pending Input Parameters	551
Table 244: GET CSR Generation Pending Response Data	551
Table 245: POST CSR Generation Generate Input Parameters	552
Table 246: POST CSR Generation Generate Response Data	554
Table 247: Custom Job Types Endpoints	554
Table 248: DELETE JobTypes Custom (id) Input Parameters	555
Table 249: GET JobTypes Custom (id) Input Parameters	555
Table 250: GET JobTypes Custom (id) Response Data	556 557
Table 251: GET JobTypes Custom Input Parameters Table 252: GET JobTypes Custom Response Data	557
	559
Table 253: POST JobTypes Custom Input Parameters Table 254: POST JobTypes Custom Response Data	561
Table 255: PUT JobTypes Custom Input Parameters	563
Table 256: PUT JobTypes Custom Response Data	565
Table 257: Enrollment Endpoints	566
Table 258: GET Enrollment Settings {id} Input Parameters	567
Table 259: GET Enrollment Settings (id) Response Body	568
Table 260: GET Enrollment CSR Content My Response Body	574
Table 261: GET Enrollment PFX Content My Response Body	586
Table 262: GET Enrollment Available Renewal ID (id) Input Parameters	597
Table 263: GET Enrollment Available Renewal ID (id) Response Body	598
Table 264: GET Enrollment Available Renewal Thumbprint (thumbprint) Input Parameters	599
Table 265: GET Enrollment Available Renewal Thumbprint (thumbprint) Response Body	600
Table 266: POST Enrollment CSR Input Parameters	602
Table 267: POST Enrollment CSR Response Data	605
Table 268: POST Enrollment PFX v2 Input Parameters	607
Table 269: POST Enrollment PFX v2 Response Data	612
Table 270: POST Enrollment PFX v1 Input Parameters	614
Table 271: POST Enrollment PFX v1 Response Data	617
Table 272: POST Enrollment CSR Parse Input Parameters	618
Table 273: POST Enrollment CSR Parse Response Data	619
Table 274: POST Enrollment PFX Deploy Input Parameters	621
Table 275: POST Enrollment PFX Deploy Response Data	625
Table 276: POST Enrollment PFX Replace Input Parameters	626
Table 277: POST Enrollment PFX Replace Response Data	627
Table 278: POST Enrollment Renew Input Parameters	628
Table 279: POST Enrollment Renew Response Data	629
Table 280: License Endpoint	629
Table 281: GFT License Response Data	630

Table 282: MacEnrollment Endpoints	632
Table 283: GET MacEnrollment Response Data	632
Table 284: PUT MacEnrollment Response Data	633
Table 285: PUT MacEnrollment Response Data	634
Table 286: MetadataFields Endpoints	634
Table 287: DELETE MetadataFields {id} Input Parameters	635
Table 288: GET MetadataFields {id} Input Parameters	636
Table 289: GET MetadataFields {id} Response Data	637
Table 290: GET MetadataFields {name} Input Parameters	639
Table 291: GET MetadataFields {name} Response Data	640
Table 292: GET MetadataFields {id} In Use Input Parameters	642
Table 293: GET MetadataFields {id} In Use Response Data	643
Table 294: DELETE MetadataFields Input Parameters	643
Table 295: GET MetadataFields Input Parameters	644
Table 296: GET MetadataFields Response Data	645
Table 297: POST MetadataFields Input Parameters	648
Table 298: POST MetadataFields Response Data	651
Table 299: PUT MetadataFields Input Parameters	654
Table 300: PUT MetadataFields Response Data	657
Table 301: Monitoring Revocation Endpoints	659
Table 302: DELETE Monitoring Revocation (id) Input Parameters	660
Table 303: GET Monitoring Revocation (id) Input Parameters	661
Table 304: GET Monitoring Revocation (id) Response Data	662
Table 305: GET Monitoring Revocation Input Parameters	665
Table 306: GET Monitoring Revocation Response Data	666
Table 307: POST Monitoring Revocation Input Parameters	669
Table 308: POST Monitoring Revocation Response Data	672
Table 309: PUT Monitoring Revocation (id)Input Parameters	675
Table 310: PUT Monitoring Revocation (id) Response Data	678
Table 311: POST Monitoring Resolve OCSP Input Parameters	681
Table 312: POST Monitoring Resolve OCSP Response Data	681
Table 313: POST Monitoring Revocation Test Input Parameters	682 683
Table 314: POST Monitoring Revocation Test Response Data	684
Table 315: POST Monitoring Revocation Test All Input Parameters	685
Table 316: POST Monitoring Revocation Test All Response Data Table 317: Orchestrator Jobs Endpoints	685
	686
Table 318: GET Orchestrator Jobs Job Status Data Input Parameters Table 319: GET Orchestrator Jobs Job Status Data Response Data	687
Table 317. GET Orchestrator Jobs Job History Input Parameters	688
Table 321: GET Orchestrator Jobs Job History Response Data	689
Table 322: GET Orchestrator Jobs Scheduled Jobs Input Parameters	693
Table 323: GET Orchestrator Jobs Scheduled Jobs Response Data	694
Table 324: POST Orchestrator Jobs Custom Input Parameters	697
Table 325: POST Orchestrator Jobs Custom Response Data	700
Table 326: POST Orchestrator Jobs Reschedule Input Parameters	701
Table 327: POST Orchestrator Jobs Unschedule Input Parameters	703
Table 328: POST Orchestrator Jobs Acknowledge Input Parameters	704
Table 329: POST Orchestrator Jobs Custom Bulk Input Parameters	705
Table 330: POST Orchestrator Jobs Custom Bulk Response Data	709
Table 331: PamProviders Endpoints	709
Table 331: Pain Poviders Enapoints  Table 332: DELETE PamProviders {id} Input Parameters	710
Table 333: GET PamProviders (id) Input Parameters	710
Table 334: GET PamProviders (id) Response Data	710
Table 335: GET PamProviders Types Response Data	719
Table 336: POST PamProviders Types Input Parameters	722
Table 337: GET PamProviders Types input Parameters	725
Table 338: GET PamProviders Response Data	725

Table 339: POST PamProviders Input Parameters	734
Table 340: POST PamProviders Response Data	742
Table 341: PUT PamProviders Input Parameters	750
Table 342: PUT PamProviders Response Data	758
Table 343: Reports Endpoints	765
Table 344: GET Reports {id} Input Parameters	766
Table 345: GET Reports {id} Response Data	767
Table 346: DELETE Reports Custom {id} Input Parameters	773
Table 347: GET Reports Custom {id} Input Parameters	774
Table 348: GET Reports Custom {id} Response Data	774
Table 349: DELETE Reports Schedules {id} Input Parameters	775
Table 350: GET Reports Schedules {id} Input Parameters	775
Table 351: GET Reports Schedules {id} Response Data	776
Table 352: GET Reports (id) Parameters Input Parameters	779
Table 353: GET Reports {id} Parameters Response Data	780
Table 354: PUT Reports (id) Parameters Input Parameters	781
Table 355: PUT Reports {id} Parameters Response Data	782
Table 356: GET Reports Input Parameters	783
Table 357: GET Reports Response Data	784
Table 358: PUT Reports Input Parameters	786
Table 359: PUT Reports Response Data	787
Table 360: GET Reports Custom Input Parameters	789
Table 361: GET Reports Custom Response Data	790
Table 362: POST Reports Custom Input Parameters	791
Table 363: POST Reports Custom Response Data	791
Table 364: PUT Reports Custom Input Parameters	792
Table 365: PUT Reports Custom Response Data	793
Table 366: GET Reports (id) Schedules Input Parameters	793 794
Table 367: GET Reports (id) Schedules Response Data	794
Table 368: POST Reports (id) Schedules Input Parameters	803
Table 369: POST Reports {id} Schedules Response Data Table 370: PUT Reports {id} Schedules Input Parameters	807
Table 370: PUT Reports (id) Schedules Response Data	812
Table 371: For Reports (id) 3chedoles Response Data  Table 372: Security Identities Endpoints	815
Table 372: 3econty identities Enapoints  Table 373: DELETE Security Identities {id} Input Parameters	815
Table 374: GET Security Identities (id) Input Parameters	816
Table 374: GET Security Identities {id} Response Data	817
Table 376: GET Security Identities Lookup Input Parameters	819
Table 377: GET Security Identities Lookup Response Data	820
Table 377: GET Security Identities Input Parameters	820
Table 379: GET Security Identities Response Data	821
Table 380: POST Security Identities Input Parameters	839
Table 381: POST Security Identities Response Data	840
Table 382: Security Roles Permissions Endpoints	841
Table 383: GET Security Roles (id) Permissions Input Parameters	842
Table 384: GET Security Roles (id) Permissions Response Data	843
Table 385: GET Security Roles (id) Global Permissions Input Parameters	843
Table 386: GET Security Roles {id} Global Permissions Response Data	844
Table 387: POST Security Roles {id}Global Permissions Input Parameters	845
Table 388: POST Security Roles (id) Global Permissions Response Data	864
Table 389: PUT Security Roles (id)Global Permissions Input Parameters	866
Table 390: PUT Security Roles (id) Global Permissions Response Data	885
Table 391: GET Security Roles (id) Permissions Containers Input Parameters	886
Table 392: GET Security Roles {id} Permissions Containers Response Data	886
Table 393: POST Security Roles {id} Permissions Containers Input Parameters	887
Table 394: POST Security Roles (id) Permissions Containers Response Data	887
Table 395: PUT Security Roles (id) Permissions Containers Input Parameters	888

Table 396: PUT Security Roles {id} Permissions Containers Response Data	889
Table 397: GET Security Roles {id} Permissions Collections Input Parameters	889
Table 398: GET Security Roles {id} Permissions Collections Response Data	890
Table 399: POST Security Roles {id} Permissions Collections Input Parameters	891
Table 400: POST Security Roles {id} Permissions Collections Response Data	891
Table 401: PUT Security Roles {id} Permissions Collections Input Parameters	892
Table 402: PUT Security Roles {id} Permissions Collections Response Data	893
Table 403: Security Roles Endpoints	894
Table 404: DELETE Security Roles {id} Input Parameters	894
Table 405: GET Security Roles {id} Input Parameters	895
Table 406: GET Security Roles {id} Response Data	896
Table 407: GET Security Roles {id} Identities Input Parameters	897
Table 408: GET Security Roles {id} Identities Response Data	897
Table 409: PUT Security Roles {id} Identities Input Parameters	898
Table 410: PUT Security Roles {id} Identities Response Data	898
Table 411: GET Security Roles Input Parameters	899
Table 412: GET Security Roles Response Data	900
Table 413: POST Security Roles Input Parameters	902
Table 414: POST Security Roles Response Data	917
Table 415: PUT Security Roles Input Parameters	919
Table 416: PUT Security Roles Response Data	934
Table 417: POST Security Roles (id) Copy Input Parameters	935
Table 418: POST Security Roles {id} Copy Response Data	936
Table 419: SSH Endpoints	937
Table 420: SSH Keys Endpoints	941
Table 421: DELETE SSH Keys Unmanaged (id) Input Parameters	942
Table 422: GET SSH Keys Unmanaged {id} Input Parameters Table 423: GET SSH Keys Unmanaged {id} Response Data	942 943
	943
Table 424: GET SSH Keys My Key Input Parameters Table 425: GET SSH Keys My Key Response Data	944
	947
Table 426: POST SSH Keys My Key Input Parameters Table 427: POST SSH Keys My Key Response Data	947
Table 428: PUT SSH Keys My Key Input Parameters	950
Table 429: PUT SSH Keys My Key Response Data	951
Table 430: DELETE SSH Keys Unmanaged Input Parameters	952
Table 431: GET SSH Keys Unmanaged Input Parameters	953
Table 432: GET SSH Keys Unmanaged Response Data	954
Table 433: SSH Logon Endpoints	954
Table 434: DELETE SSH Logons {id} Input Parameters	955
Table 435: GET SSH Logons (id) Input Parameters	956
Table 436: GET SSH Keys Unmanaged {id} Response Data	957
Table 437: GET SSH Logons Input Parameters	958
Table 438: GET SSH Logons Response Data	959
Table 439: POST SSH Logons Input Parameters	960
Table 440: POST SSH Logons Response Data	961
Table 441: POST SSH Logons Access Input Parameters	962
Table 442: POST SSH Logons Access Response Data	962
Table 443: SSH Servers Endpoints	963
Table 444: DELETE SSH Servers {id} Input Parameters	964
Table 445: GET SSH Servers {id} Input Parameters	964
Table 446: GET SSH Servers {id} Response Data	965
Table 447: GET SSH Servers Access {id} Input Parameters	968
Table 448: GET SSH Servers Access {id} Response Data	969
Table 449: GET SSH Servers Input Parameters	970
Table 450: GET SSH Servers Response Data	971
Table 451: POST SSH Servers Input Parameters	975
Table 452: POST SSH Servers Response Data	976

Table 453: PUT SSH Servers Input Parameters	980
Table 454: PUT SSH Servers Response Data	981
Table 455: DELETE SSH Servers Access Input Parameters	985
Table 456: DELETE SSH Servers Access Response Data	986
Table 457: POST SSH Servers Access Input Parameters	987
Table 458: POST SSH Servers Access Response Data	988
Table 459: SSH Server Groups Endpoints	988
Table 460: DELETE SSH Server Groups {id} Input Parameters	989
Table 461: GET SSH Server Groups {id} Input Parameters	990
Table 462: GET SSH Server Groups {id} Response Data	991
Table 463: GET SSH Server Groups {name} Input Parameters	994
Table 464: GET SSH Server Groups {name} Response Data	995
Table 465: GET SSH Server Groups Access {id} Input Parameters	998
Table 466: GET SSH Server Groups Access {id} Response Data	999
Table 467: GET SSH Server Groups Input Parameters	1000
Table 468: GET SSH Server Groups Response Data	1001
Table 469: POST SSH Server Groups Input Parameters	1005
Table 470: POST SSH Server Groups Response Data	1008
Table 471: PUT SSH Server Groups Input Parameters	1012
Table 472: PUT SSH Server Groups Response Data	1015
Table 473: DELETE SSH Server Groups Access Input Parameters	1018
Table 474: DELETE SSH Server Groups Access {id} Response Data	1019
Table 475: POST SSH Server Groups Access Input Parameters	1020
Table 476: POST SSH Server Groups Access (id) Response Data	1021
Table 477: SSH Service Accounts Endpoints	1022
Table 478: DELETE SSH Service Accounts {id} Input Parameters	1023
Table 479: GET SSH Service Accounts (id) Input Parameters	1024
Table 480: GET SSH Service Accounts {id} Response Data	1025
Table 481: GET SSH Service Accounts Key {id} Input Parameters	1031
Table 482: GET SSH Service Accounts Key {id} Response Data	1033
Table 483: DELETE SSH Service Accounts Input Parameters	1035
Table 484: GET SSH Service Accounts Input Parameters	1037
Table 485: GET SSH Service Accounts Response Data	1038
Table 486: POST SSH Service Accounts Input Parameters	1044
Table 487: POST SSH Service Accounts Response Data	1047
Table 488: PUT SSH Service Accounts Input Parameters	1053
Table 489: PUT SSH Service Accounts Response Data	1054
Table 490: GET SSH Service Accounts Rotate {id} Input Parameters	1060
Table 491: GET SSH Service Accounts Rotate {id} Response Data	1062
Table 492: SSH Users Endpoints	1063
Table 493: DELETE SSH Users {id} Input Parameters	1063
Table 494: GET SSH Users {id} v2 Input Parameters	1064
Table 495: GET SSH Users {id} v2 Response Data	1065
Table 496: GET SSH Users {id} v1 Input Parameters	1066
Table 497: GET SSH Users {id} v1 Response Data	1067
Table 498: GET SSH Users v2 Input Parameters	1069
Table 499: GET SSH Users v2 Response Data	1071
Table 500: GET SSH Users v1 Input Parameters	1073
Table 501: GET SSH Users v1 Response Data	1075
Table 502: POST SSH Users Input Parameters	1077
Table 503: POST SSH Users Response Data	1077
Table 504: PUT SSH Users Input Parameters	1078
Table 505: POST SSH Users Response Data	1078
Table 506: POST SSH Users Access Input Parameters	1079
Table 507: POST SSH Users Access Response Data	1080
Table 508: SMTP Endpoints	1081
Table 509: GET SMTP Response Data	1083

Tarle 510 DUT CMTD large to Descript the	1005
Table 510: PUT SMTP Input Parameters	1085
Table 511: POST SMTP Test Response Data	1086
Table 512: POST SMTP Test Input Parameters	1087
Table 513: POST SMTP Test Response Data	1089
Table 514: SSL Endpoints	1090
Table 515: GET SSL Parts {id} Input Parameters	1091
Table 516: GET SSL Parts {id} Response Data	1092
Table 517: GET SSL Endpoints {id} Input Parameters	1093
Table 518: GET SSL Endpoints {id} Response Data	1094
Table 519: DELETE SSL Network Ranges {id} Input Parameters	1094
Table 520: GET SSL Network Ranges {id} Input Parameters	1095
Table 521: GET SSL Network Ranges {id} Response Data	1095
Table 522: GET SSL Networks {id} Input Parameters	1096
Table 523: GET SSL Networks {id} Response Data	1097
Table 524: GET SSL Input Parameters	1105
Table 525: GET SSL Response Data	1106
Table 526: GET SSL Networks Input Parameters	1107
Table 527: GET SSL Networks Response Data	1108
Table 528: POST SSL Networks Input Parameters	1116
Table 529: POST SSL Networks Response Data	1125
Table 530: PUT SSL Networks Input Parameters	1128
Table 531: PUT SSL Networks Response Data	1137
Table 532: GET SSL Endpoints {id} History Input Parameters	1140
Table 533: GET SSL Endpoints {id} History Response Data	1141
Table 534: GET SSL Networks (id) Parts Input Parameters	1145
Table 535: GET SSL Networks {id} Parts Response Data	1146
Table 536: POST SSL Network Ranges Input Parameters	1146
Table 537: PUT SSL Network Ranges {id} Input Parameters	1147
Table 538: PUT SSL Endpoints Review Status Input Parameters	1148
Table 539: PUT SSL Endpoints Monitor Status Input Parameters	1148
Table 540: PUT SSL Endpoints Review All Input Parameter	1149
Table 541: PUT SSL Endpoints Monitor All Input Parameter	1149
Table 542: POST SSL Networks (id) Scan Input Parameters	1150
Table 543: POST SSL Networks {id} Reset Input Parameters	1150
Table 544: POST SSL Network Ranges Validate Input Parameters	1151
Table 545: DELETE SSL Networks (id) Input Parameters	1151
Table 546: Status Endpoints	1151
Table 547: Templates Endpoints	1152
Table 548: GET Templates {id} Input Parameters	1152
Table 549: GET Templates (id) Response Data	1153
Table 550: GET Templates Settings Response Data	1166
Table 551: PUT Templates Settings Response Bata  Table 551: PUT Templates Settings Input Parameters	1173
Table 552: PUT Templates Settings Response Data	1179
Table 552: FOT Templates Settings Response Data  Table 553: GET Templates Subject Parts Response Data	1185
Table 553: GET Templates Subject raits Response Data  Table 554: GET Templates Input Parameters	1186
Table 555: GET Templates Response Data	1187
Table 555: PUT Templates Input Parameters	1196
Table 557: PUT Templates Response Body	1210
Table 558: POST Templates/Import Input Parameters	1210
Table 558: Workflow Certificates Endpoints	1222
	1223
Table 560: GET Workflow Certificates {id} Input Parameters Table 561: GET Workflow Certificates {id} Input Parameters	1223
Table 562: GET Workflow Certificates Penied Input Parameters  Table 562: GET Workflow Certificates Denied Input Parameters	1224
Table 563: GET Workflow Certificates Denied Response Data	1227
Table 564: GET Workflow Certificates Pending Input Parameters	1227
Table 565: GET Workflow Certificates Pending Input Parameters  Table 565: GET Workflow Certificates Pending Response Data	1228
	1229
Table 566: GET Workflow Certificates External Validation Input Parameters	1230

Table 567: GET Workflow Certificates External Validation Response Data	1231
Table 568: POST Workflow Certificates Deny Input Parameters	1232
Table 569: POST Workflow Certificates Deny Response Data	1233
Table 570: POST Workflow Certificates Approve Input Parameters	1234
Table 571: POST Workflow Certificates Approve Response Data	1234
Table 572: Workflow Definitions Endpoints	1235
Table 573: GET Workflow Definitions Steps {extensionName} Input Parameters	1236
Table 574: GET Workflow Definitions Steps {extensionName} Response Data	1237
Table 575: DELETE Workflow Definitions (definitionid) Input Parameters	1238
Table 576: GET Workflow Definitions {definitionid} Input Parameters	1238
Table 577: GET Workflow Definitions (definitionsid) Response Data	1239
Table 578: PUT Workflow Definitions {definitionid} Input Parameters	1254
Table 579: PUT Workflow Definitions {definitionid} Response Body	1255
Table 580: GET Workflow Definitions Input Parameters	1270
Table 581: GET Workflow Definitions Response Data	1271
Table 582: POST Workflow Definitions Input Parameters	1272
Table 583: POST Workflow Definitions Response Body	1273
Table 584: GET Workflow Definitions Steps Input Parameters	1288
Table 585: GET Workflow Definitions Steps Response Data	1289
Table 586: GET Workflow Definitions Types Input Parameters	1290
Table 587: GET Workflow Definitions Types Response Data	1291
Table 588: PUT Workflow Definitions {definitionid} Steps Input Parameters	1293
Table 589: PUT Workflow Definitions (definitionid) Steps Response Body	1295
Table 590: POST Workflow Definitions (definitionid) Publish Input Parameters	1310
Table 591: POST Workflow Definitions {definitionid} Publish Response Body	1311
Table 592: Workflow Instances Endpoints	1325
Table 593: DELETE Workflow Instances (instanceid) Input Parameters	1326
Table 594: GET Workflow Instances (instanceId) Input Parameters	1327
Table 595: GET Workflow Instances (instanceId) Response Data	1328
Table 596: GET Workflow Instances Input Parameters	1349
Table 597: GET Workflow Instances Response Data	1350
Table 598: GET Workflow Instances My Input Parameters	1352
Table 599: GET Workflow Instances My Response Data	1353
Table 600: GET Workflow Instances AssignedToMe Input Parameters	1355
Table 601: GET Workflow Instances AssignedToMe Response Data	1356
Table 602: POST Workflow Instances {instanceid} Stop Input Parameters	1358
Table 603: POST Workflow Instances {instanceid} Signals Input Parameters	1359
Table 604: POST Workflow Instances {instanceid} Restart Input Parameters	1360
	1361
Table 605: Classic API Security Role Requirements	
Table 606: ApiApp Endpoints	1364
Table 607: AddApiApp Parameters	1365
Table 608: AddApiApp Parameters	1366
Table 609: CertEnroll Endpoints	1368
Table 610: CertEnroll Security Headers	1369
Table 611: CertEnroll HMAC computations in Python	1370
Table 612: GET /2/Templates and /3/Templates Response Body	1371
Table 613: POST /1/Pkcs10 and /2/Pkcs10 Request Body	1374
Table 614: POST /3/Pkcs10 Request Body	1374
Table 615: POST /*/Pkcs10 Response Body	1375
Table 616: POST /1/Pkcs12 and /2/Pkcs12 Request Body	1378
Table 617: POST /3/Pkcs12 Request Body	1379
Table 618: POST /*/Pkcs12 Response Body	1379
Table 619: POST /3/Renew Request Body	1381
Table 620: POST /3/Renew Response Body	1381
Table 621: Certificates Endpoints	1382
Table 622: POST /1/Metafield Request Body	1383
Table 623: POST /2/Import Request Body	1384

Table 624: POST /3/Contents Request Body	1385
Table 625: POST /3/PublishCRL Request Body	1386
Table 626: POST /3/Recover Request Body	1387
Table 627: POST /3/Revoke Request Body	1387
Table 628: Certificate Revocation Details	1388
Table 629: POST /3/Search and /3/Count Request Body	1389
Table 630: POST /3/Search Response Body	1389
Table 631: Certstore Endpoints	1392
Table 632: POST /AddCert Request Body	1393
Table 633: POST /AddCert Response Body	1393
Table 634: POST /AddCertStore Request Body	1395
Table 635: POST /AddCertStore Response Body	1396
Table 636: POST /AddCertStoreServer Request Body	1397
Table 637: POST /AddCertStoreServer Response Body	1398
Table 638: POST /AddCertStoreType Request Body	1399
Table 639: POST /AddCertStoreType Response Body	1401
Table 640: POST /AddPfx Request Body	1405
Table 641: POST /CreateJKS Request Body	1406
Table 642: POST /EditCertStore Request Body	1407
Table 643: POST /EditCertStoreServer Request Body	1408
Table 644: GET /GetCertStoreTypes Response Body	1409
Table 645: POST /Inventory Response Body	1409
Table 646: POST /Inventory Response Certificates Fields	1410
Table 647: GET / Keystores Response Body	1411
Table 648: POST /Remove Request Body	1412
Table 649: POST /ScheduleInventory Request Body	1413
Table 650: Metadata Endpoints	1415
Table 651: POST Metadata/2/* Request Body	1415
Table 652: Metadata V3 Request Body	1418
Table 653: Metadata V3 Security Bitflags	1418
Table 654: POST /GetDefinition Response Body	1420
Table 655: Security Endpoints	1422
Table 656: POST AddIdentity Request Parameter	1423
Table 657: POST DeleteIdentity Request Parameter	1424
Table 658: POST /GetRoles Response Body	1425
Table 659: Keyfactor Command Permissions List	1426
Table 660: POST /AddRole Request Parameters	1427
Table 661: POST /EditRole Request Parameters	1428
Table 662: SSL Endpoints	1430
Table 663: POST /AddEndpoint Request Body	1430
Table 664: POST /AddEndpointGroup Request Body	1431
Table 665: POST /AddEndpointGroup Response Body	1432
Table 666: GET / Agents Response Body	1432
Table 667: Workflow Endpoints	1433
Table 668: POST /Approve and /Deny Request Body	1434
Table 669: POST /Approve and /Deny PendingRequests Details	1434
Table 670: POST /Approve and /Deny Response Body	1435
Table 671: POST /Approve and /Deny Result Details	1435
Table 672: POST /PendingList Request Body	1437
Table 673: POST / PendingList Response Body	1438
Table 674: POST /PendingList SubjectAlternativeName Details	1439
Table 675: Workflow Expiration Alerts Endpoints	1440
Table 676: Workflow Expiration Alert Parameters	1441
Table 677: Workflow Expiration Alerts Event Handler Parameters Endpoints	1444
Table 678: Workflow Expiration Alert Handler Parameters	1445
Table 679: Workflow Expiration Alerts Registered Event Handlers Endpoints	1448
Table 680: Workflow Expiration Alert Registered Event Handlers Parameters	1448

Table 681: Workflow Expiration Alerts Schedule Endpoints	1449
Table 682: Workflow Expiration Alert Schedule Parameters	1449
Table 683: GET /CMSValidation/api/vSCEP Query String Parameters	1452
Table 684: GET /CMSValidation/api/vSCEP Response Body	1452
Table 685: API Change Log v9.0	1454
Table 686: API Change Log v9.1	1455
Table 687: API Change Log v9.2	1456
Table 688: API Change Log v9.3	1456
Table 689: API Change Log v9.4	1457
Table 690: API Change Log v9.5	1457
Table 691: API Change Log v9.7	1457
Table 692: API Change Log v9.9	1458
Table 693: API Change Log v10.0	1458

## 1.0 Introduction

The Keyfactor Command Documentation Suite includes:

- Keyfactor Command Reference Guide
- Keyfactor Web APIs Reference Guide
- Keyfactor Command Server Installation Guide
- Keyfactor Orchestrators Installation and Configuration Guide
- Keyfactor Command Release Notes

In addition, Keyfactor offers documentation for products that are not part of the *Keyfactor Command Documentation Suite*, including the *Keyfactor Command Upgrade Overview* and installation guides for third-party CA gateways that interface with Keyfactor, which are available upon request.

## 2.0 Web APIs Reference

The Keyfactor Command solution by Keyfactor exposes Web APIs to allow third-party software to integrate with the advanced certificate enrollment and management features of Keyfactor Command in a secure manner and to provide a mechanism for automating routine or bulk tasks that would be cumbersome to perform through the browser-based user interface. The APIs complement the web components of Keyfactor Command and offer a number of HTTP method calls that provide similar functionality to that available within the portal's user interface, but which can be accessed programmatically by any system capable of making web requests. These APIs have the following goals and constraints:

- Provide a simple interface to make integration easy for third parties.
- Develop interoperability between different technology frameworks and operating systems.
- Support common certificate enrollment and management tasks.
- Deliver a securable interface.
- · Preserve backward-compatibility so that existing clients continue to work, where possible.

#### 2.1 Overview

Keyfactor exposes two APIs for external use:

- The Keyfactor API was introduced in Keyfactor Command version 6.1 and is the newer API. Customers should be using this API going forward.
- The Classic API has been provided in the product for several product generations and is continuing to be supported for legacy implementations but should not be used for new implementations.

### 2.1.1 Transaction Security

The Keyfactor Web APIs rely on SSL/TLS to protect the HTTP communications between the client and Keyfactor Command server. In a typical deployment, the APIs will be configured for Basic authentication, where client credentials are provided in an HTTP header, formatted as "DOMAIN\user:Password" and base-64-encoded. Basic Authentication itself is not a secure way to pass a set of user credentials. However, it is very interoperable and works well across all of the various technologies that use these APIs. SSL is used to protect the confidentiality of user credentials; therefore, SSL should be used with the Keyfactor Web APIs.

Keyfactor recommends that any device using these APIs already be configured to trust the SSL certificate presented by Keyfactor Command, allowing the SSL connection to be established without error. The process for this will depend on the platform and operating environment of the connecting client, but the appropriate documentation or support for your platform should outline the necessary steps for this.

There is no longer the need to configure an API application with a key and secret and a particular template in the portal to allow for enrollment for a certificate with the API. Certificate enrollment no longer requires a key and secret and enrollment permissions are now controlled on the template level.

Finally, access to the API methods can be limited per client to a maximum request frequency. The amount of time required between calls can also be configured in the Keyfactor Command Management Portal Application Settings for the APIs. Increasing this interval can mitigate certain threats such as denial of service or dictionary attacks against passwords and other sensitive data. However, setting this too high can negatively impact performance of client applications that need to make a large number of requests.

#### 2.1.2 Architecture

By default, all Web API methods start with a base path, which varies depending on the API and corresponds to an application under IIS; this path is configurable at install time. For the Keyfactor API, the default base path is *KeyfactorApi*. The API component name, version number (only applicable to the Classic API), and method name then comprise the second through fourth parts of the URL, each separated by a forward slash. For example, "/KeyfactorApi/Certificates/Import" would be the URL format for the Import method of the Certificates component in the Keyfactor API and "/CMSApi/CertEnroll/1/Token" would be the URL format for the Token method of version 1 of the CertEnroll API component in the Classic API. Version numbers are only used in the URL for the Classic API.

#### 2.1.3 Web API Common Features

Some aspects of the Web API request and response formats are consistent across all endpoints. This includes a small set of HTTP headers, HTTP statuses returned by the server for successful requests, and various error conditions. Common request headers are given in <u>Table 1: Common Request Headers</u>, common response headers (for successful requests and certain unsuccessful requests) are given in <u>Table 2: Common Response Headers</u>, and HTTP statuses are given in Table 3: HTTP Statuses.

Additionally, many Classic API methods operate on a certificate resource stored in Keyfactor Command, and a standardized way to identify the certificate for the operation is used in the request structure across several Classic API components; this is described in <u>Table 4: Classic API Certificate Lookup Structure</u>. This table does not apply to the Keyfactor API.

Table 1: Common Request Headers

Header Name	API Version	Header Value	Description
Content-Type	Both	application/json OR application/xml	POST methods use application/json. When application/xml is needed, it is specifically indicated on the endpoint page.
Accept	Both	application/json; charset=utf-8	Most methods returning complex values will use this content type.
Authorization	Both	Basic <base-64 domain\user:pass=""></base-64>	In most cases, Web API clients will use Basic authentication over SSL/TLS.
Host	Both	<keyfactor command="" hostname="" server=""></keyfactor>	Address of Keyfactor Command server. Automatically generated in most clients.
Content-Length	Both	Request length in bytes	Optional, but automatically generated by most

Header Name	API Version	Header Value	Description
			clients.
X-Keyfactor- Requested-With	Both	XMLHttpRequest	This is mandatory to send in a request to the Keyfactor API on POSTs, PUTs, and DELETEs, and the value is case sensitive. This is for security.
X-Keyfactor-API- Version	Keyfactor API	1 or 2	Desired version of the endpoint. If not provided, this defaults to version 1.

Table 2: Common Response Headers

Header Name	API Version	Header Value	Description
Cache-Control	Both	no-cache	API requests are generally not cacheable. Note that this is not respected by all client systems.
Pragma	Both	no-cache	API requests are generally not cacheable. Note that this is not respected by all client systems.
Content-Length	Both	<varies></varies>	Length of the HTTP response.
Content-Type	Both	application/json	Most calls return application/json, but occasionally text/plain or text/xml.
Expires	Both	-1	Usually ignored.
Server	Both	<varies></varies>	Software version reported by IIS platform hosting Keyfactor Command.
X-CSS-CMS-APIVer- sion	Classic API	2.0	Classic API version accessed (see usage in <u>Versioning on page 6</u> ).
X-CSS-CMS-CMSVersion	Classic API	10.1	Keyfactor Command platform version.
X-Keyfactor- Product-Version	Keyfactor API	<varies></varies>	Keyfactor Command platform version.
X-Total-Count	Keyfactor API	<varies></varies>	Total number of elements returned.
X-AspNet-Version	Both	<varies></varies>	Version of ASP.NET supporting Keyfactor Command installation.
X-Powered-By	Both	ASP.NET	Header added by underlying ASP.NET implementation.

Header Name	API Version	Header Value	Description
Date	Both	<varies></varies>	Timestamp of the HTTP response.

Table 3: HTTP Statuses

Number/Name	Description
200 OK	Request successful; results in response body
204 No Content	Request successful; no content in response body
400 Bad Request	Malformed or invalid data; additional information may be available in the response body and/or Keyfactor Command server logs
401 Unauthorized	Invalid credentials (user unauthenticated)
403 Forbidden	Can often indicate that the credentials map to a user without permissions for this action in Keyfactor Command (user unauthorized)
404 Page not Found	Invalid request path
500 Internal Server Error	Keyfactor Command encountered an unexpected error attempting to handle the request. See response body and Keyfactor Command server logs for details.
502 Bad Gateway	Keyfactor Command attempted to contact a CA or other upstream server to process the request, but was unable to. See Keyfactor Command server logs for details.

Table 4: Classic API Certificate Lookup Structure

Parameter Name	Parameter Value
Туре	One of "Serial", "Thumbprint", and "CMSID".
SerialNumber	Hexadecimal serial number of referenced certificate. Required only if Type is "Serial".
IssuerDN	Distinguished Name of the issuer of the referenced certificate. Required only if Type is "Serial".
Thumbprint	SHA-1 thumbprint of the referenced certificate. Required only if Type is "Thumbprint".
CMSID	Identifier assigned by Keyfactor Command to the referenced certificate. Required only if Type is "CMSID".

### 2.1.4 Versioning

The Keyfactor Web APIs are versioned as a set and released in conjunction with Keyfactor Command at the same version level (e.g. version 10.1). In addition, both the Keyfactor API and the Classic API<sup>1</sup> have multiple versions of select endpoints.

The current strategy is to increment the version of an API when changes are made that might break backwards compatibility for existing clients. New endpoints are generally implemented in the most recent version of their API.

Generally, updates to an existing version of an endpoint are restricted to updates that should not break existing clients. Updates may be made that add HTTP response headers or response body parameters, or that correct existing bugs, or must be made to conform to newer or more granular security constraints. When an update cannot be made without breaking existing clients, a new endpoint is added in a later API version.

The Classic API provides various methods to retrieve the version of Keyfactor Command. For example, values for both the Classic API version and the Keyfactor Command version are returned in HTTP headers with each response to an API call. Additionally, the *Status* endpoint (see <u>Status on page 1450</u>) provides additional information about the capabilities of the Classic API in its installed version. The Keyfactor API does not presently have an equivalent functionality.

Most Keyfactor API endpoints have only one version, though a second version has been released for a select few endpoints. The Keyfactor API uses the *x-keyfactor-api-version* request header to differentiate between versions 1 and 2 of a given endpoint. If a version isn't specified, version 1 is assumed.

Several endpoints of the Classic API have their own incremental versioning. For example, the CertEnroll endpoint has three versions, the most recent of which is three:

- CertEnroll/1
- CertEnroll/2
- CertEnroll/3

As the Keyfactor Web APIs have evolved and continue to evolve, an additional security constraint is available to limit access to deprecated legacy versions of API endpoints. In many cases, newer versions of an endpoint are more secure and robust, easier to use, and offer more functionality. Keyfactor highly recommends use of the newest endpoints wherever possible. To this end, it is possible to disable deprecated API endpoints in the Classic API from the API Application Settings within the Keyfactor Command Management Portal. In Keyfactor Command 10.1, this setting will disable the following endpoints:

- CertEnroll/1/Token<sup>2</sup>
- CertEnroll/1/Status<sup>1</sup>
- CertEnroll/1/Certificates/Pkcs10<sup>1</sup>
- CertEnroll/1/Certificates/Pkcs12<sup>1</sup>

<sup>&</sup>lt;sup>1</sup>The Classic API was historically versioned on a different release schedule to Keyfactor Command and so has separate reporting of versions for itself and Keyfactor Command.

<sup>&</sup>lt;sup>2</sup>The CertEnroll v1 endpoints are deprecated.

- Metadata/2/Set
- Metadata/2/Get
- Metadata/2/Compare
- · Certificates/1/Metafield
- Certificates/1/Import<sup>1</sup>

If the *Allow Deprecated API Calls* setting is disabled, any client attempting to access one of these endpoints will receive an error message instead of the expected results. This will, of course, prevent client applications that rely on these endpoints from functioning, and if these applications cannot be updated to the newer endpoints then the *Allow Deprecate API Calls* setting must be enabled. Otherwise, Keyfactor recommends that these endpoints be disabled to reduce exposure to unauthorized or unintended use.

The following endpoints have been removed from the Classic API and are no longer supported:

• CertEnroll/1/Templates



**Note:** API versioning strategy in Keyfactor Command shifted somewhat between versions 4.0 and 5.0 (when the product was known as Certificate Management System or CMS). As such, the API versioning mechanisms described in CMS 4.0-4.5 documentation, while still generally correct, are no longer our primary recommendation.

## 2.2 Keyfactor API

The Keyfactor API is the Web API introduced in Keyfactor Command version 6.1. It is designed to support the updated platform architecture in the new version of the main Keyfactor Command solution and to, in time, replace the Classic API. The Keyfactor API allows for integration with other systems to automate certificate lifecycle management tasks. It will continue to be developed going forward to expose more core functionality that is built into the main product to allow for more in-depth integrations.

Documentation for the Keyfactor API is available as two companion pieces—this document (the *Keyfactor Web APIs Reference Guide*), which provides an overview of the API's endpoints, parameters to be provided in them, and data expected back from them, and the interactive code examples installed with your Keyfactor Command instance in the *Keyfactor API Endpoint Utility*.



Tip: Click the help icon (②) at the top of the Keyfactor Command Management Portal page next to the **Logout** button to find the embedded web copies of the *Keyfactor Command Documentation Suite* and the *Keyfactor API Endpoint Utility*.

<sup>&</sup>lt;sup>1</sup>The Certificates/1/Import endpoint, using a multipart/form-data request, is no longer supported by Keyfactor for customers that are not currently using it.



Figure 1: Documentation in the Help Dropdown

You can also browse to the *Keyfactor API Endpoint Utility* directly using the following link (where *keyfactor.keyexample.com* is the fully qualified domain name of your Keyfactor Command server or the DNS alias you are using to reference your Keyfactor Command server, if applicable):

https://keyfactor.keyexample.com/KeyfactorAPI/ref/index#
This link assumes that the Keyfactor API has been installed in the default IIS virtual directory
(KeyfactorAPI). If you have installed in an alternate virtual directory, your path will be different.

A static reference (without the interactive utility you can find in the Keyfactor Command Management Portal) is available as a zip file in the Keyfactor Client Portal<sup>1</sup>.

### 2.2.1 Agents

The Agents component of the Keyfactor API includes methods necessary to list orchestrators and agents and schedule jobs to retrieve log files for orchestrators and agents that support that functionality.

Table 5: Agents Endpoints

Endpoint	Method	Description	Link
/{id}	GET	Returns details for a single orchestrator or agent.	GET Agents ID on the next page
/	GET	Returns a list of all orchestrators and agents according to the provided filters and input parameters.	GET Agents on page 12
/Reset	POST	Resets one or more orchestrators or agents to a new state and clears jobs.	POST Agents Reset on page 16
/Approve	POST	Approves an orchestrator.	POST Agents Approve on

<sup>&</sup>lt;sup>1</sup>Embedded links to external documents point to the document on the Keyfactor Client Portal. Access to the portal requires a login. See your administrator or your Keyfactor Client Success representative to obtain a login to the portal.

Endpoint	Method	Description	Link
			page 17
/Disapprove	POST	Disapproves an orchestrator.	POST Agents Disapprove on page 17
/{id}/Reset	POST	Resets a single orchestrator or agent to a new state and clears jobs.	POST Agents ID Reset on page 18
/{id}/FetchLogs	POST	Schedules a job on the orchestrator or agent to retrieve log files.	POST Agents ID FetchLogs on page 18
/SetAuthCertificateReenrollment	POST	Configures an orchestrator or agent to either request or require a new client authentication certificate on its next session registration.	POST Agents Set Auth Certificate Reenrollment on page 19

### 2.2.1.1 GET Agents ID

The GET /Agents/{id} method is used to retrieve a single orchestrator or agent registered in Keyfactor Command. This method returns HTTP 200 OK on a success with a list of all orchestrator details.



Table 6: GET Agents{id} Input Parameters

Name	In	Description
id	Path	Required. The GUID of the orchestrator to retrieve.  Use the GET /Agents method (see GET Agents on page 12) to retrieve a list of all the orchestrators to determine the orchestrator GUID.

Table 7: GET Agent {id} Response Data

Name	Description			
AgentId	A string indicating the GUID of the orchestrator.			
ClientMachine	A string indicating the client machine on which the orchestrator is installed.			
Username	A string indicating the Active Directory user or service account the orchestrator is using to connect to Keyfactor Command.			
AgentPlatform	An integer indicating the platform for the orchestrator.			
	Value	Parame	ter Value	
	0	Unknown	1	
	1	Keyfactor	r Windows Orchestrator	
	2	Keyfactor	r Java Agent	
	3	Keyfactor Mac Auto-Enrollment Agent		
	4	Keyfactor Android Agent		
	5	Keyfactor Native Agent		
	6	Keyfactor Bash Orchestrator		
	7	Keyfactor Universal Orchestrator		
Version	A string indicating the v	version of th	ne orchestrator.	
Status	An integer indicating the orchestrator status.			
	Value		Parameter Value	
	1		New	
	2		Approved	
	3		Disapproved	
LastSeen	The time, in UTC, at which the orchestrator last contacted Keyfactor Command.			

Name	Description			
Capabilities	An array of strings indicating the capabilities reported by the orchestrator. These may be built-in or custom capabilities.			
	Value	Description		
	AWS	Amazon Web Services		
	NS	NetScaler		
	F5-CA-REST	F5 CA Bundles (REST)		
	F5-WS-REST	F5 Web Server (REST)		
	F5-SL-REST	F5 SSL Profile (REST)		
	IIS	IIS		
	FTP	File Transfer Protocol		
	F5	F5 SSL Profile and F5 Web Server (SOAP)		
	CA	Remote CA Management		
	SSL	SSL Discovery and Monitoring		
	MacEnrollment	Mac Autoenrollment		
	JKS	Java Keystore		
	PEM	PEM Store		
	LOGS	Fetch Logs		
	TemplateSync	Template Synchronization		
Blueprint	A string indicating the name of the blueprint associated with the orchestrator.			
Thumbprint	A string indicating the thumbprint of the certificate that Keyfactor Command is expecting the orchestrator to use for client certificate authentication.			
LegacyThumbprint	A string indicating the thumbprint of the certificate previously used by the orchestrator for client certificate authentication before a certificate renewal operation took place (rotating the current thumbprint into the legacy thumbprint). The legacy thumbprint is cleared once the orchestrator successfully registers with the new thumbprint.			
AuthCertificateReenrollment	An integer indicating the value of the orchestrator certificate reenrollment request require status.			

Name	Description		
	Value	Description	
	0	None—Unset the value so that the orchestrator will not request a new client authentication certificate (based on this value).	
	1 Requested—The orchestrator will request a new client au tication certificate when it next registers for a session. Orc trator activity will be allowed to continue as usual.		
	2 Required—The orchestrator will request a new client auth tication certificate when it next registers for a session. A n session will not be granted and orchestrator activity will n allowed to continue until the orchestrator acquires a new ficate.		
LastThumbprintUsed	A string indicating the thumbprint of the certificate that the orchestrator most recently used for client certificate authentication. In most cases, this will match the <i>Thumbprint</i> .		
LastErrorCode	An integer indicating the last error code, if any, reported from the orchestrator when trying to register a session. This code is cleared on successful session registration.		
LastErrorMessage	A string indicating the last error message, if any, reported from the orchestrator when trying to register a session. This message is cleared on successful session registration.		

## 2.2.1.2 GET Agents

The GET /Agents method is used to retrieve a list of orchestrators and agents registered in Keyfactor Command. This method returns HTTP 200 OK on a success with a list of all orchestrator details.



Table 8: GET Agents Input Parameters

Name	In	Description
queryString	Query	A string containing a query to limit the results (e.g. field1 -eq value1 AND field2 -gt value2). The default is to return all records. Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns for the same feature. For querying guidelines, refer to the Keyfactor Command Reference Guide: Using the Orchestrator Management Search Feature. The query fields supported for this endpoint are:  • AgentId  • Blueprint  • Capabilities (See Table 9: GET Agent Response Data Capabilities)  • ClientMachine  • ErrorCode  • ErrorMessage (last error message)  • Identity (Username)  • LastSeen (DateTime)  • Platform (Platform types: 0-Unknown, 1NET, 2-Java, 3-Mac, 4-Android, 5-Native, 6-Bash, 7-Universal Orchestrator)  • Status (1-New, 2-Approved, 3-Disapproved)  • Version  Tip: Use the following query to return only approved orchestrators: Status -eq "2"  A value of 1 will return orchestrators with a status of New and a value of 3 will return orchestrators with a status of Disapproved.
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>AgentId</i> .
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.

Table 9: GET Agent Response Data

Name	Description			
AgentId	A string indicating the GUID of the orchestrator.			
ClientMachine	A string indicating the client machine on which the orchestrator is installed.			
Username	A string indicating the Active Directory user or service account the orchestrator is using to connect to Keyfactor Command.			
AgentPlatform	An integer indicating th	ne platform	for the orchestrator. Possible values are:	
	Value	Parame	eter Value	
	0	Unknow	n	
	1	Keyfacto	r Windows Orchestrator	
	2	Keyfacto	r Java Agent	
	3	Keyfactor Mac Auto-Enrollment Agent		
	4	Keyfactor Android Agent		
	5	Keyfactor Native Agent		
	6	Keyfactor Bash Orchestrator		
	7	Keyfactor Universal Orchestrator		
Version	A string indicating the v	version of tl	he orchestrator.	
Status	An integer indicating the orchestrator status. Possible values are:			
	Value		Parameter Value	
	1		New	
	2		Approved	
	3		Disapproved	
LastSeen	The time, in UTC, at which the orchestrator last contacted Keyfactor Command.			

Name	Description			
Capabilities	An array of strings indicating the capabilities reported by the orchestrator. These may be built-in or custom capabilities. Possible built-in values for common orchestrators include:			
	Value	Description		
	AWS	Amazon Web Services		
	NS	NetScaler		
	F5-CA-REST	F5 CA Bundles (REST)		
	F5-WS-REST	F5 Web Server (REST)		
	F5-SL-REST	F5 SSL Profile (REST)		
	IIS	IIS		
	FTP	File Transfer Protocol		
	F5	F5 SSL Profile and F5 Web Server (SOAP)		
	CA	Remote CA Management		
	SSL	SSL Discovery and Monitoring		
	MacEnrollment	Mac Autoenrollment		
	JKS	Java Keystore		
	PEM	PEM Store		
	LOGS	Fetch Logs		
	TemplateSync	Template Synchronization		
Blueprint	A string indicating the name of	f the blueprint associated with the orchestrator.		
Thumbprint	A string indicating the thumbprint of the certificate that Keyfactor Command is expecting the orchestrator to use for client certificate authentication.			
LegacyThumbprint	A string indicating the thumbprint of the certificate previously used by the orchestrator for client certificate authentication before a certificate renewal operation tool place (rotating the current thumbprint into the legacy thumbprint). The legacy thumbprint is cleared once the orchestrator successfully registers with the new thumbprint			
AuthCertificateReenrollment	An integer indicating the value of the orchestrator certificate reenrollment request or require status. Possible values are:			

Name	Description		
	Value	Description	
	0	None—Unset the value so that the orchestrator will not request a new client authentication certificate (based on this value).	
	1	Requested—The orchestrator will request a new client authentication certificate when it next registers for a session. Orchestrator activity will be allowed to continue as usual.	
	2	Required—The orchestrator will request a new client authentication certificate when it next registers for a session. A new session will not be granted and orchestrator activity will not be allowed to continue until the orchestrator acquires a new certificate.	
LastThumbprintUsed	A string indicating the thumbprint of the certificate that the orchestrator most recently used for client certificate authentication. In most cases, this will match the <i>Thumbprint</i> .		
LastErrorCode	An integer indicating the last error code, if any, reported from the orchestrator when trying to register a session. This code is cleared on successful session registration.		
LastErrorMessage	A string indicating the last error message, if any, reported from the orchestrator when trying to register a session. This message is cleared on successful session registration.		

# 2.2.1.3 POST Agents Reset

The POST /Agents/Reset method is used to reset one or more orchestrators, including:

- Remove all current orchestrator jobs for the selected orchestrator(s).
- Delete all associated certificate stores.
- Set the orchestrator status to new.
- For orchestrators configured to use client certificate authentication, clear the certificate thumbprints stored for the orchestrator(s) to allow them to be reconfigured with a new certificate.

This endpoint returns 204 with no content upon success. On a failure, a 400 is returned with an error message.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature:

AgentManagement: *Read* AgentManagement: *Modify* 

Table 10: POST Agents Reset Input Parameters

Name	In	Description
agentIds	Body	<b>Required</b> . An array of GUIDs of the orchestrators to reset.  Use the <i>GET /Agents</i> method (see <u>GET Agents on page 12</u> ) to retrieve a list of all the orchestrators to determine the orchestrator GUIDs.

### 2.2.1.4 POST Agents Approve

The POST /Agents/Approve method is used to approve one or more orchestrators (a.k.a. agents). An orchestrator must be approved before jobs for it can be scheduled or carried out. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see Security Overview) are required to use this feature:

AgentManagement: Read AgentManagement: Modify

Table 11: POST Agents Approve Input Parameters

Name	In	Description
agentIds	Body	<b>Required</b> . An array of strings indicating the GUIDs of the orchestrators to approve.  Use the <i>GET Agents</i> method (see <u>GET Agents on page 12</u> ) to retrieve a list of all the orchestrators to determine the orchestrator GUIDs and current status of the orchestrators.

### 2.2.1.5 POST Agents Disapprove

The POST /Agents/Disapprove method is used to disapprove one or more orchestrators (a.k.a. agents). When an orchestrator is disapproved, operations with Keyfactor Command can no longer be carried out by this orchestrator. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see Security Overview) are required to use this feature:

AgentManagement: *Read* AgentManagement: *Modify* 

Table 12: POST Agents Disapprove Input Parameters

Name	In	Description
agentIds	Body	<b>Required</b> . An array of strings indicating the orchestrator GUIDs to disapprove.  Use the <i>GET Agents</i> method (see <u>GET Agents on page 12</u> ) to retrieve a list of all the orchestrators to determine the orchestrator GUIDs and current status of the orchestrators.

### 2.2.1.6 POST Agents ID Reset

The POST /Agents/{id}/Reset method is used to reset a single orchestrator, including:

- Remove all current orchestrator jobs for the selected orchestrator.
- Delete all associated certificate stores.
- Set the orchestrator status to new.
- For orchestrators configured to use client certificate authentication, clear the certificate thumbprints stored for the orchestrator to allow it to be reconfigured with a new certificate.

This endpoint returns 204 with no content upon success. On a failure, a 400 is returned with an error message.



Tip: The following permissions (see Security Overview) are required to use this feature:

AgentManagement: Read AgentManagement: Modify

Table 13: POST Agents {id} Reset Input Parameters

Name	In	Description
id	Path	Required. The GUID of the orchestrator to reset.  Use the GET /Agents method (see GET Agents on page 12) to retrieve a list of all the orchestrators to determine the orchestrator GUID.

### 2.2.1.7 POST Agents ID FetchLogs

The POST /Agents/{id}/FetchLogs method is used to schedule a job on a Native Agent to retrieve log files. The job will be scheduled to run immediately, which means it should complete within a few minutes depending on other activity occurring at the same time. This method is currently only supported for the Native Agent. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature:

AgentManagement: Read AgentManagement: Modify



**Tip:** To schedule a job to retrieve logs from a Keyfactor Universal Orchestrator, use the POST /OrchestratorJobs/Custom method (see <u>POST Orchestrator Jobs Custom on page 696</u>).

Table 14: POST Agents {id} FetchLogs Input Parameters

Name	In	Description
id	Path	<b>Required</b> . The GUID of the orchestrator to schedule the job for.  Use the <i>GET /Agents</i> method (see <u>GET Agents on page 12</u> ) to retrieve a list of all the orchestrators to determine the orchestrator GUID.

# 2.2.1.8 POST Agents Set Auth Certificate Reenrollment

The POST /Agents/SetAuthCertificateReenrollment method is used to request or require that one or more orchestrators (a.k.a. agents) enroll for a new client authentication certificate on the orchestrator's next session registration. This method returns HTTP 200 OK on a success with details



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature:

AgentManagement: *Read* AgentManagement: *Modify* 

Table 15: POST Agents Set Auth Certificate Reenrollment Input Parameters

Name	In	Description			
OrchestratorIds	Body	<b>Required</b> . An array of strings indicating the GUIDs of the orchestrators on which you want to change the AuthCertificateReenrollment value to request or require the orchestrator(s) to enroll for a new client authentication certificate on the next session registration.  Use the <i>GET Agents</i> method (see <u>GET Agents on page 12</u> ) to retrieve a list of all the orchestrators to determine the orchestrator GUIDs and current status of the orchestrators.			
Status	Status Body	An integer indic Status options a	rating the value that AuthCertificateReenrollment should be set to. are:		
		Value	Description		
		0	None—Unset the value so that the orchestrator will not request a new client authentication certificate (based on this value).		
				1	Requested—The orchestrator will request a new client authentication certificate when it next registers for a session. Orchestrator activity will be allowed to continue as usual.
				2	Required—The orchestrator will request a new client authentication certificate when it next registers for a session. A new session will not be granted and orchestrator activity will not be allowed to continue until the orchestrator acquires a new certificate.

Table 16: POST Agents Set Auth Certificate Reenrollment Response Data

Name	Description	
FailedOrchestratorIds	An array of stri	ngs indicating the GUIDs of orchestrators that failed to update.
Status	A string indication options are:	ing the value for AuthCertificateReenrollment that was requested. Status
	Value	Description
	0	None—Unset the value so that the orchestrator will not request a new client authentication certificate (based on this value).
	1	Requested—The orchestrator will request a new client authentication certificate when it next registers for a session. Orchestrator activity will be allowed to continue as usual.
	2	Required—The orchestrator will request a new client authentication certificate when it next registers for a session. A new session will not be granted and orchestrator activity will not be allowed to continue until the orchestrator acquires a new certificate.

# 2.2.2 Agent BluePrint

The Agent BluePrint component of the Keyfactor API includes methods necessary to list, generate, and apply orchestrator and orchestrator blueprints for orchestrators and agents that support blueprint functionality.

Table 17: Agent BluePrint Endpoints

Endpoint	Method	Description	Link
/{id}	DELETE	Deletes the orchestrator blueprint with the specified GUID.	DELETE Agent BluePrint  ID on the next page
/{id}	GET	Returns details for the orchestrator blueprint with the specified GUID.	GET Agent BluePrint ID on the next page
/	GET	Returns details for all orchestrator blueprints.	GET Agent BluePrint on page 22
/{id}/Jobs	GET	Returns details of the certificate store scheduled jobs for the orchestrator blueprint with the specified GUID.	GET Agent BluePrint ID Jobs on page 23
/{id}/Stores	GET	Returns details of the certificate stores for the orchestrator blueprint with the specified GUID.	GET Agent BluePrint ID Stores on page 26

Endpoint	Method	Description	Link
/ApplyBlueprint	POST	Applies an orchestrator blueprint to one or more orchestrators.	POST AgentBluePrint ApplyBluePrint on page 28
/GenerateBlueprint	POST	Creates a new orchestrator blueprint from an orchestrator.	POST AgentBluePrint GenerateBluePrint on page 29

### 2.2.2.1 DELETE Agent BluePrint ID

The DELETE /AgentBluePrint/{id} method is used to delete an existing orchestrator blueprint with the specified blueprint GUID. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see Security Overview) are required to use this feature:

AgentManagement: *Read*AgentManagement: *Modify* 

Table 18: DELETE AgentBluePrint {id} Input Parameters

Name	In	Description
id	Path	<b>Required</b> . A string indicating the GUID of the orchestrator blueprint that should be deleted. Use the <i>GET AgentBluePrint</i> method (see <u>GET Agent BluePrint</u> on the next page) to retrieve a list of all the blueprints to determine the orchestrator blueprint GUID.

### 2.2.2.2 GET Agent BluePrint ID

The GET /AgentBluePrint/{id} method is used to retrieve information about the orchestrator blueprint with the specified blueprint GUID. This method returns HTTP 200 OK on a success with information about the blueprint.



**Tip:** To see the certificate stores or scheduled jobs associated with the blueprint, use the GET /AgentBluePrint/{id}/Jobs method (see GET Agent BluePrint ID Jobs on page 23) or GET /AgentBluePrint/ (id)/Stores method (see GET Agent BluePrint ID Stores on page 26).



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: AgentManagement: *Read* 

Table 19: GET AgentBluePrint {id} Input Parameters

Name	In	Description
id	Path	<b>Required</b> . A string indicating the GUID of the orchestrator blueprint that should be retrieved. Use the <i>GET AgentBluePrint</i> method (see <u>GET Agent BluePrint below</u> ) to retrieve a list of all the blueprints to determine the orchestrator blueprint GUID.

Table 20: GET AgentBluePrint {id} Response Data

Name	Description
AgentBlueprintId	A string indicating the GUID of the blueprint.
Name	A string indicating the name of the blueprint.
RequiredCapabilities	An array of strings indicating the type of capabilities required by the orchestrators to which the blueprint will be applied (e.g. JKS, PEM).
LastModified	A string indicating the date and time the blueprint was created.

# 2.2.2.3 GET Agent BluePrint

The GET /AgentBluePrint method is used to retrieve a list of blueprints defined for the orchestrators and agents registered in Keyfactor Command. This method returns HTTP 200 OK on a success with a list of all blueprint details.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: AgentManagement: *Read* 

Table 21: GET AgentBluePrint Input Parameters

Name	In	Description
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>Name</i> .
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.

Table 22: GET AgentBluePrint Response Data

Name	Description
AgentBlueprintId	A string indicating the GUID of the blueprint.
Name	A string indicating the name of the blueprint.
RequiredCapabilities	An array of strings indicating the type of capabilities required by the orchestrators to which the blueprint will be applied (e.g. JKS, PEM).
LastModified	A string indicating the date and time the blueprint was created.

# 2.2.2.4 GET Agent BluePrint ID Jobs

The GET /AgentBluePrint/{id}/Jobs method is used to retrieve details of the scheduled certificate store jobs for the orchestrator blueprint with the specified blueprint GUID. This method returns HTTP 200 OK on a success with a list of all the blueprint scheduled job details, including certificate stores.



**Tip:** The following permissions (see  $\underline{\text{Security Overview}}$ ) are required to use this feature: AgentManagement: Read

Table 23: GET AgentBluePrint {id} Jobs Input Parameters

Name	In	Description
id	Path	Required. A string indicating the GUID of the orchestrator blueprint that should be retrieved.  Use the GET AgentBluePrint method (see GET Agent BluePrint on the previous page) to retrieve a list of all the blueprints to determine the orchestrator blueprint GUID.
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>StorePath</i> .
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.

Table 24: GET AgentBluePrint {id} Jobs Response Data

Name	Description
AgentBlueprintJobId	A string indicating the GUID of the certificate store job associated with the blueprint.
AgentBlueprintStoreId	A string indicating the GUID of the certificate store associated with the blueprint.
AgentBlueprintId	A string indicating the GUID of the blueprint.
JobType	A string indicating the GUID of the certificate store job type.
JobTypeName	A string indicating the certificate store job type (e.g. JksInventory).
OperationType	In integer indicating the type of operation (e.g. 2 = add to certificate store, 3 = remove from certificate store).
Thumbprint	A string indicating the thumbprint of the certificate to add to or remove from the certificate store. This field is populated only for management jobs.
Contents	A string containing the certificate to be added to the certificate store. This field is populated only for management add to certificate store jobs.
Alias	A string indicating the alias to be used for the certificate upon entry into or removal from the certificate store. The function of the alias varies depending on the certificate store type. For example, for a Java keystore, it is user-generated and stored in the keystore associated with the certificate while for PEM stores it is the thumbprint of the certificate. Some certificate store types don't require an alias and some do. See the <a href="Add Certificate">Add Certificate</a> section of the Keyfactor Command Reference Guide for more information. This field is populated only for management jobs.
PrivateKeyEntry	A Boolean indicating whether the certificate store has a separate private key file. This field is populated only for management jobs.
Overwrite	A Boolean indicating whether the certificate already in the certificate store should be overwritten with the new certificate, if applicable. This field is populated only for management jobs.
HasEntryPassword	A Boolean indicating whether the certificate in the certificate store has a different password from the certificate store itself. This field is populated only for management jobs.
HasPfxPassword	A Boolean indicating whether the certificate being added to the certificate store has a private key. This field is populated only for management jobs.
RequestTimestamp	A string indicating the time at which the management job was requested. This field is populated only for management jobs.

Name	Description	
KeyfactorSchedule	The schedule for the certificate store job. This field is populated only for inventory and discovery jobs.	
Subject	A string containing the reenrol only for reenrollment jobs.	Iment subject name using X.500 format. This field is populated
Directories	A string containing the director populated only for discovery jo	ry or directories to search during a discovery job. This field is obs.
IgnoredDirectories	A string containing the director jobs. This field is populated on	ries that should not be included in the search during discovery ly for discovery jobs.
SymLinks	ating systems and report both	the job should follow symbolic links on Linux and UNIX oper- the actual location of a found certificate store file in addition of the file during discovery jobs. This option is ignored on ed only for discovery jobs.
Compatibility	Java version 1.8 to locate both	the job will run using the compatibility mode introduced in JKS and PKCS12 type files (true) or not (false) during Java eld is populated only for discovery jobs.
FileExtensions	example, search for files with t	ensions for which to search during a discovery job. For the extension "jks" in order to exclude files with other extenpopulated only for discovery jobs.
FileNamePatterns		are the file names of certificate store files and return only d string (e.g. "myjks") during discovery jobs. This field is popu-
AgentBlueprintStores	An array that includes the cert store details are included:	ificate store information of the job. The following certificate
	Name	Description
	AgentBlueprintStoreId	A string indicating the GUID of the certificate store associated with the blueprint.
	AgnetBlueprintId	A string indicating the GUID of the blueprint.
	StorePath	A string indicating the path to the certificate store on the target. The format for this path will vary depending on the certificate store type. For example, for a Java keystore, this will be a file path (e.g. /opt/myap-p/store.jks). See the Adding or Modifying a Certificate Store section of the Keyfactor Command Reference Guide

Name	Description	
	Name	Description
		for more information.
	ContainerId	An integer indicating the ID of the certificate store's associated certificate store container, if applicable (see <u>GET</u> <u>Certificate Store Containers on page 488</u> ).
	CertStoreType	An integer indicating the ID of the certificate store type, as defined in Keyfactor Command, for this certificate store. (0-Javakeystore,2-PEMFile, 3-F5SSLProfiles,4-IISRoots, 5-NetScaler, 6-IISPersonal, 7-F5WebServer, 8-IISRevoked, 9-F5WebServerREST, 10-F5SSLProfilesREST, 11-F5CABundlesREST, 100-AmazonWebServices, 101-FileTransferProtocol)
	CertStoreTypeName	A string indicating a reference name for the certificate store type (e.g. Java Keystore, PEM File).
	Approved	A Boolean indicating whether a certificate store is approved (true) or not (false). If a certificate store is approved, it can be used and updated. A certificate store that has been discovered using the discover feature but not yet marked as approved will be false here.
	CreatelfMissing	A Boolean indicating whether a new certificate store should be created with the information provided (true) or not (false). This option is only valid for Java keystores and any custom certificate store types you have defined to support this functionality.
	Properties	Some types of certificate stores have additional properties that are stored in this parameter. The data is stored in a series of, typically, key value pairs that define the property name and value (see <u>GET Certificate Store Types on page 518</u> for more information).

# 2.2.2.5 GET Agent BluePrint ID Stores

The GET /AgentBluePrint/{id}/Stores method is used to retrieve details of the certificate stores for the orchestrator blueprint with the specified blueprint GUID. This method returns HTTP 200 OK on a success with a list of all the blueprint certificate store details.



Table 25: GET AgentBluePrint {id} Stores Input Parameters

Name	In	Description
id	Path	<b>Required</b> . A string indicating the GUID of the orchestrator blueprint that should be retrieved.  Use the <i>GET AgentBluePrint</i> method (see <u>GET Agent BluePrint on page 22</u> ) to retrieve a list of all the blueprints to determine the orchestrator blueprint GUID.
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>StorePath</i> .
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.

Table 26: GET AgentBluePrint {id} Stores Response Data

Name	Description
AgentBlueprintStoreId	A string indicating the GUID of the certificate store associated with the blueprint.
AgentBlueprintId	A string indicating the GUID of the blueprint.
StorePath	A string indicating the path to the certificate store on the target. The format for this path will vary depending on the certificate store type. For example, for a Java keystore, this will be a file path (e.g. /opt/myapp/store.jks). See the Adding or Modifying a Certificate Store section of the Keyfactor Command Reference Guide for more information.
ContainerId	An integer indicating the ID of the certificate store's associated certificate store container, if applicable (see <u>GET Certificate Store Containers on page 488</u> ).
CertStoreType	An integer indicating the ID of the certificate store type, as defined in Keyfactor Command, for this certificate store. (0-Javakeystore,2-PEMFile, 3-F5SSLProfiles,4-IISRoots, 5-NetScaler, 6-IISPersonal, 7-F5WebServer, 8-IISRevoked, 9-F5WebServerREST, 10-F5SSLProfilesREST, 11-F5CABundlesREST, 100-AmazonWebServices, 101-FileTransferProtocol)
CertStoreTypeName	A string indicating a reference name for the certificate store type (e.g. Java Keystore, PEM File).
Approved	A Boolean indicating whether a certificate store is approved (true) or not (false). If a certificate store is approved, it can be used and updated. A certificate store that has been discovered using the discover feature but not yet marked as approved will be false here.
CreatelfMissing	A Boolean indicating whether a new certificate store should be created with the information provided (true) or not (false). This option is only valid for Java keystores and any custom certificate store types you have defined to support this functionality.
Properties	Some types of certificate stores have additional properties that are stored in this parameter. The data is stored in a series of, typically, key value pairs that define the property name and value (see <u>GET Certificate Store Types on page 518</u> for more information).

# 2.2.2.6 POST AgentBluePrint ApplyBluePrint

The POST /AgentBluePrint/ApplyBluePrint method is used to apply a blueprint with associated certificate stores and scheduled jobs to an orchestrator. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature:

AgentManagement: *Read* AgentManagement: *Modify* 

Table 27: POST AgentBluePrint Apply Input Parameters

Name	In	Description	
agentids	Body	Required. An array of strings indicating the GUIDs of the orchestrators to which the blue-print should be applied.  Use the GET Agents method (see GET Agents on page 12) to retrieve a list of all the orchestrators to determine the orchestrator GUIDs and current status of the orchestrators.  Note: Orchestrators must be approved before a blueprint can be applied.	
templateId	Body	A string indicating the GUID of the blueprint to apply to the orchestrator(s).  Use the GET AgentBluePrint method (see GET Agent BluePrint on page 22) to retrieve a list of all the blueprints to determine the blueprint GUIDs.	

# 2.2.2.7 POST AgentBluePrint GenerateBluePrint

The POST /AgentBluePrint/GenerateBluePrint method is used to create a new blueprint based on the certificate stores and scheduled jobs of one orchestrator. This method returns HTTP 200 OK on a success with details of the new blueprint.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature:

AgentManagement: *Read*AgentManagement: *Modify* 

Table 28: POST AgentBluePrint Generate Input Parameters

Name	In	Description
agentIds	Body	<b>Required</b> . A string indicating the GUID of the orchestrator that should be used to generate the blueprint.  Use the <i>GET Agents</i> method (see <u>GET Agents on page 12</u> ) to retrieve a list of all the orchestrators to determine the orchestrator GUIDs and current status of the orchestrators.
name	Body	Required. A string indicating the name for the new blueprint.

Table 29: POST AgentBluePrint Generate Response Data

Name	Description	
AgentBlueprintId	A string indicating the GUID of the blueprint.	
Name	A string indicating the name of the blueprint.	
RequiredCapabilities	An array of strings indicating the type of capabilities required by the orchestrators to which the blueprint will be applied (e.g. JKS, PEM).	
RequiredCapabilities	An array of strings indicating the type of capabilities required by the orchestrators to which the blueprint will be applied (e.g. JKS, PEM).	

# 2.2.3 Agent Pools

The Agent Pools component of the Keyfactor API includes methods necessary to programmatically add, edit, get, and delete Agent Pools. An orchestrator (a.k.a. agent) pool is a group of Keyfactor Command Windows Orchestrators and/or Universal Orchestrators that have the SSL capability. Each pool is used to divide the work of scanning a network between all orchestrators that are members of it.

Table 30: Agent Pool Endpoints

Endpoint	Method	Description	Links
/{id}	DELETE	Deletes the specified orchestrator pool.	DELETE Agent Pools  ID below
/{id}	GET	Returns limited information about the orchestrators in the specified pool.	GET Agent Pools ID on the next page
/	GET	Returns a list of all orchestrator pools with limited information about the orchestrators assigned to each pool.	GET Agent Pools on page 32
/	POST	Creates an orchestrator pool based on information in the request.	POST Agent Pools on page 34
/	PUT	Updates an orchestrator pool based on information in the request.	PUT Agent Pools on page 36
/Agents	GET	Returns a list of orchestrators associated with the Default Agent Pool.	GET Agent Pools Agents on page 38

# 2.2.3.1 DELETE Agent Pools ID

The DELETE /AgentPools/{id} method is used to delete an existing orchestrator (a.k.a. agent) pool. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see Security Overview) are required to use this feature:

SslManagement: *Read*SslManagement: *Modify* 

Table 31: DELETE AgentPools {id} Input Parameters

Name	In	Description
id	Path	<b>Required</b> . A string indicating the GUID of the orchestrator pool to delete.  Use the <i>GET /AgentPools</i> method (see <u>GET Agent Pools on the next page</u> ) to retrieve a list of all the orchestrator pools to determine the orchestrator pool GUID. The Default Agent Pool cannot be deleted.

### 2.2.3.2 GET Agent Pools ID

The GET /AgentPools/{id} method is used to return information about a single orchestrator (a.k.a. agent) pool. This method returns HTTP 200 OK on a success with details about the requested orchestrator pool.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: SslManagement: *Read* 

Table 32: GET AgentPools {id} Input Parameters

Name	In	Description
id	Path	<b>Required</b> . A string indicating the GUID of the orchestrator pool to retrieve.  Use the <i>GET /AgentPools</i> method (see <u>GET Agent Pools on the next page</u> ) to retrieve a list of all the orchestrator pools to determine the orchestrator pool GUID.

Table 33: GET AgentPools {id} Response Data

Name	Description			
AgentPoolId	A string indicating the GUID of the orchestrator pool.			
Name	A string indicating the n	name of the orchestrator pool.		
DiscoverAgentsCount	An integer specifying th jobs.	ne number of orchestrators in the pool that can perform discovery		
MonitorAgentsCount	An integer specifying th jobs.	An integer specifying the number of orchestrators in the pool that can perform monitoring jobs.		
Agents	,	orchestrators that are assigned to the orchestrator pool, with accom- orchestrators. Orchestrator details include:		
	Name	Description		
	AgentId	A string indicating the GUID of the orchestrator.		
	EnableDiscover	A Boolean that indicates whether this orchestrator is allowed to perform discovery jobs for the orchestrator pool to which it has been assigned (true) or not (false).		
	EnableMonitor	A Boolean that indicates whether this orchestrator is allowed to perform monitoring jobs for the orchestrator pool to which it has been assigned (true) or not (false).		
	Version	A string indicating the version of the orchestrator.		
	AllowsDiscover	A Boolean that indicates whether this orchestrator has the capability to perform discovery jobs (true) or not (false).		
	AllowsMonitor	A Boolean that indicates whether this orchestrator has the capability to perform monitoring jobs (true) or not (false).		
	ClientMachine	A string indicating the client machine on which the orchestrator is installed.		

# 2.2.3.3 GET Agent Pools

The GET /AgentPools method is used to retrieve all orchestrator (a.k.a. agent) pools. This method returns HTTP 200 OK on a success with a list of all agent pool details.



**Tip:** The following permissions (see  $\underline{\text{Security Overview}}$ ) are required to use this feature: SslManagement: Read

Table 34: GET AgentPools Input Parameters

Name	In	Description
queryString	Query	A string containing a query to limit the results (e.g. field1 -eq value1 AND field2 -gt value2). The default is to return all records. Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns for the same feature. For querying guidelines, refer to the Keyfactor Command Reference Guide: Certificate Search Page. The query fields supported for this endpoint are:  • Id (AgentPoolID)  • Name
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>Name</i> .
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.

Table 35: GET AgentPools Response Data

Name	Description			
AgentPoolId	A string indicating the GUID of the orchestrator pool.			
Name	A string indicating the n	name of the orchestrator pool.		
DiscoverAgentsCount	An integer specifying th jobs.	ne number of orchestrators in the pool that can perform discovery		
MonitorAgentsCount	An integer specifying th jobs.	An integer specifying the number of orchestrators in the pool that can perform monitoring jobs.		
Agents	,	orchestrators that are assigned to the orchestrator pool, with accom- orchestrators. Orchestrator details include:		
	Name	Description		
	AgentId	A string indicating the GUID of the orchestrator.		
	EnableDiscover	A Boolean that indicates whether this orchestrator is allowed to perform discovery jobs for the orchestrator pool to which it has been assigned (true) or not (false).		
	EnableMonitor	A Boolean that indicates whether this orchestrator is allowed to perform monitoring jobs for the orchestrator pool to which it has been assigned (true) or not (false).		
	Version	A string indicating the version of the orchestrator.		
	AllowsDiscover	A Boolean that indicates whether this orchestrator has the capability to perform discovery jobs (true) or not (false).		
	AllowsMonitor	A Boolean that indicates whether this orchestrator has the capability to perform monitoring jobs (true) or not (false).		
	ClientMachine	A string indicating the client machine on which the orchestrator is installed.		

# 2.2.3.4 POST Agent Pools

The POST /AgentPools method is used to create a new orchestrator (a.k.a. agent) pool. This method returns HTTP 200 OK on a success with information about the orchestrator pool.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature:

SslManagement: *Read* SslManagement: *Modify* 

Table 36: POST AgentPools Input Parameters

Name	In	Description									
Name	Body	Required. A string indicating the name of the orchestrator pool.									
Agents	Body	A list of orchestrators that will be part of this orchestrator pool. The orchestrators <b>must not be</b> assigned to a different orchestrator pool (except the Default Agent Pool). Per orchestrator data that can be provided includes:									
		Name	Description								
							AgentId	<b>Required</b> . A string indicating the GUID of the orchestrator being assigned.			
		EnableMonitor	<b>Required</b> *. A Boolean that sets whether a monitoring job can be sent to this orchestrator. One of <i>EnabledDiscover</i> or <i>EnableMonitor</i> is <b>required</b> .								

Table 37: POST AgentPools Response Data

Name	Description			
AgentPoolId	A string indicating the GUID of the orchestrator pool.			
Name	A string indicating the n	name of the orchestrator pool.		
DiscoverAgentsCount	An integer specifying th jobs.	e number of orchestrators in the pool that can perform discovery		
MonitorAgentsCount	An integer specifying th jobs.	An integer specifying the number of orchestrators in the pool that can perform monitoring jobs.		
Agents		orchestrators that are assigned to the orchestrator pool, with accom- orchestrators. Orchestrator details include:		
	Name	Description		
	AgentId	A string indicating the GUID of the orchestrator.		
	EnableDiscover	A Boolean that indicates whether this orchestrator is allowed to perform discovery jobs for the orchestrator pool to which it has been assigned (true) or not (false).		
	EnableMonitor	A Boolean that indicates whether this orchestrator is allowed to perform monitoring jobs for the orchestrator pool to which it has been assigned (true) or not (false).		
	Version	A string indicating the version of the orchestrator.		
	AllowsDiscover	A Boolean that indicates whether this orchestrator has the capability to perform discovery jobs (true) or not (false).		
	AllowsMonitor	A Boolean that indicates whether this orchestrator has the capability to perform monitoring jobs (true) or not (false).		
	ClientMachine	A string indicating the client machine on which the orchestrator is installed.		

# 2.2.3.5 PUT Agent Pools

The PUT /AgentPools method is used to update an existing orchestrator (a.k.a. agent) pool. This method returns HTTP 200 OK on a success with information about the orchestrator pool.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature:

SslManagement: *Read* SslManagement: *Modify* 



Warning: Any previously populated fields that are not submitted with their full existing data using this method will be cleared of their existing data. When using this method, you should first do a GET to retrieve all the values for the record you want to update, enter corrected data into the field(s) you want to update, and then submit all the fields using PUT, including the fields that contain values but which you are not changing.

Table 38: PUT AgentPools Input Parameters

Name	In	Description			
AgentPoolId	Body	Required. A string indicating the GUID of the orchestrator pool that is to be updated.			
Name	Body	Required. A string indic	Required. A string indicating the name of the orchestrator pool.		
Agents	Agents Body	A list of orchestrators that will be part of this orchestrator pool. The orchestrators <b>must not be</b> assigned to a different orchestrator pool (except the Default Agent Pool). Per orchestrator data that can be provided includes:			
		Name	Description		
		AgentId	<b>Required</b> . A string indicating the GUID of the orchestrator being assigned.		
			EnableDiscover	<b>Required</b> *. A Boolean that sets whether a discovery job can be sent to this orchestrator. One of <i>EnabledDiscover</i> or <i>EnableMonitor</i> is <b>required</b> .	
		EnableMonitor	<b>Required</b> *. A Boolean that sets whether a monitoring job can be sent to this orchestrator. One of <i>EnabledDiscover</i> or <i>EnableMonitor</i> is <b>required</b> .		

Table 39: PUT AgentPools Response Data

Name	Description		
AgentPoolId	A string indicating the GUID of the orchestrator pool.		
Name	A string indicating the n	name of the orchestrator pool.	
DiscoverAgentsCount	An integer specifying th jobs.	e number of orchestrators in the pool that can perform discovery	
MonitorAgentsCount	An integer specifying th jobs.	e number of orchestrators in the pool that can perform monitoring	
Agents	,	orchestrators that are assigned to the orchestrator pool, with accom- orchestrators. Orchestrator details include:	
	Name	Description	
	AgentId	A string indicating the GUID of the orchestrator.	
	EnableDiscover	A Boolean that indicates whether this orchestrator is allowed to perform discovery jobs for the orchestrator pool to which it has been assigned (true) or not (false).	
	EnableMonitor	A Boolean that indicates whether this orchestrator is allowed to perform monitoring jobs for the orchestrator pool to which it has been assigned (true) or not (false).	
	Version	A string indicating the version of the orchestrator.	
	AllowsDiscover	A Boolean that indicates whether this orchestrator has the capability to perform discovery jobs (true) or not (false).	
	AllowsMonitor	A Boolean that indicates whether this orchestrator has the capability to perform monitoring jobs (true) or not (false).	
	ClientMachine	A string indicating the client machine on which the orchestrator is installed.	

# 2.2.3.6 GET Agent Pools Agents

The GET /AgentPools/Agents method is used to retrieve the orchestrators (a.k.a. agents) associated with the Default Agent Pool. This method has no required input parameters. It returns HTTP 200 OK on a success with information about the Default Agent Pool orchestrators.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: SslManagement: *Read* 

Table 40: GET AgentPools Default Agent Pool Agents Input Parameters

Name	In	Description
queryString	Query	A string containing a query to limit the results (e.g. field1 -eq value1 AND field2 -gt value2). The default is to return all records. Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns for the same feature. For querying guidelines, refer to the Keyfactor Command Reference Guide: Certificate Collection Manager. The query fields supported for this endpoint are:  • Id (Orchestrator ID, AgentID)  • ClientMachine  • EnableDiscover (true or false)  • EnableMonitor (true or false)
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>AgentId</i> .
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.

Table 41: GET AgentPools Default Agent Pool Agents Response Data

Name	Description		
AgentId	A string indicating the GUID of the orchestrator.		
EnableDiscover	A Boolean that indicates whether this orchestrator is allowed to perform discovery jobs for the orchestrator pool to which it has been assigned (true) or not (false).		
EnableMonitor	A Boolean that indicates whether this orchestrator is allowed to perform monitoring jobs for the orchestrator pool to which it has been assigned (true) or not (false).		
Version	A string indicating the version of the orchestrator.		
AllowsDiscover	A Boolean that indicates whether this orchestrator has the capability to perform discovery jobs (true) or not (false).		
AllowsMonitor	A Boolean that indicates whether this orchestrator has the capability to perform monitoring jobs (true) or not (false).		
ClientMachine	A string indicating the client machine on which the orchestrator is installed.		

### 2.2.4 Alerts

The Alerts component of the Keyfactor API includes methods necessary to create, update, retrieve, schedule, test and delete alerts for denied certificate requests, expired certificates, issued certificate requests, pending certificate requests and SSH Key Rotations.

- Alerts Denied below
- Alerts Expiration on page 64
- Alerts Issued on page 94
- Alerts Key Rotation on page 124
- Alerts Pending on page 153

#### 2.2.4.1 Alerts Denied

The Alerts Denied component of the Keyfactor API includes methods necessary to create, update, retrieve, and delete alerts for denied certificate requests.

Table 42: Alerts Denied

Endpoint	Method	Description	Link
/Alerts/Denied/{id}	DELETE	Deletes a denied certificate request alert for the specified ID.	DELETE Alerts Denied ID on the next page
/Alerts/Denied/{id}	GET	Retrieves details for a denied certificate request	GET Alerts Denied ID on

Endpoint	Method	Description	Link
		alert for the specified ID.	the next page
/Alerts/Denied	PUT	Updates a denied certificate request alert for the specified ID.	PUT Alerts Denied on page 56
/Alerts/Denied	GET	Retrieves details for all configured denied certificate request alerts.	GET Alerts Denied on page 45
/Alerts/Denied	POST	Creates a new denied certificate request alert.	POST Alerts Denied on page 49

#### **DELETE Alerts Denied ID**

The DELTE /Alerts/Denied/{id} method is used to delete the denied certificate request alert with the specified ID. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: WorkflowManagement: *Modify* 

Table 43: DELETE Alerts Denied {id} Input Parameters

Name	In	Description
id	Path	<b>Required</b> . An integer indicating the Keyfactor Command reference ID for the denied certificate request alert to be deleted.  Use the <i>GET /Alerts/Denied</i> method (see <u>GET Alerts Denied on page 45</u> ) to retrieve a list of all the issued request alerts to determine the alert ID.

### **GET Alerts Denied ID**

The GET /Alerts/Denied/{id} method is used to retrieve details for the denied certificate request alerts with the specified ID. This method returns HTTP 200 OK on a success with details about the specified denied certificate request alert.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: WorkflowManagement: *Read* 

Table 44: GET Alerts Denied {id} Input Parameters

Name	In	Description
id	Path	<b>Required</b> . An integer indicating the Keyfactor Command reference ID for the denied certificate request alert.  Use the <i>GET /Alerts/Denied</i> method (see <u>GET Alerts Denied on page 45</u> ) to retrieve a list of all the issued request alerts to determine the alert ID.

Table 45: GET Alerts Denied {id} Response Data

Name	Description			
Id	An integer indicating the Keyfactor Command reference ID of the denied request alert.			
DisplayName	A string indicating the display name for the denied request alert. This name appears in the denied request alerts grid in the Management Portal.			
Subject	A string indicating the subject for the email message that will be delivered when the alert is triggered.			
	Tip: Substitutable special text may be used in the subject line. Substitutable special text uses a variable in the alert definition that is replaced by data from the certificate or certificate metadata at processing time. For example, you can enter {rcn} in the alert definition and each alert generated at processing time will contain the specific requested common name of the given certificate request instead of the variable {rcn}.			
Message	A string indicating the email message that will be delivered when the alert is triggered. The email message is made up of regular text and substitutable special text. If desired, you can format the message body using HTML.  For example:  "Hello {requester:givenname},\n\nWe are sorry to report that the certificate you requested on {subdate} in the name {rcn} has not been issued for the following reason:\n\n{cmnt}\n\nCertificate information includes:\n\n\n\n\rtr>\CertificateDetails\th>Metadata\tr>\n\tr>\n\to <ta>\tr&gt;\n\to<ta>\to<ta>\to<ta>\to&lt;\ta&gt;\to</ta></ta></ta></ta>			
Recipients				

Name	Description				
Template	An object containing information about the certificate template for which the denied request alerts will be generated. A separate alert should be configured for each template. An alert may be configured with no template, if desired. Alerts configured in this way generate alerts for all denied certificate requests. Possible values are:				
	Value		Description		
	Id	Id		An integer indicating the Keyfactor Command reference ID for the template, or <i>null</i> for all templates.	
	DisplayName		created using	ining the name of the template. For a template a Microsoft management tool, this will be the plate display name.	
	ForestRoot		A string indica	ting the forest root of the template.	
				This field is retained for legacy purposes and e replaced by ConfigurationTenant field.	
	ConfigurationTenan	nt	A string indica	ting the configuration tenant of the template.	
RegisteredEventHandl- er	An object containing the event handler configuration for the alert, if applicable. Possible values are:				
	Value	Desc	cription		
	Id		teger indicating thandler.	the Keyfactor Command reference ID for the	
		ID		Event Handler Type	
		6		DeniedLogger	
		7		DeniedPowershell	
	DisplayName	A string containing the name of the event handler.		e name of the event handler.	
	UseHandler	A Boolean indicating whether event handler use is enabled for the alert (true) or not (false).			
	For more information about event handlers, see <i>Using Event Handlers</i> in the <i>Keyfactor Command Reference Guide</i> .		see Using Event Handlers in the Keyfactor		
EventHand- lerParameters	An array containing the parameters configured for use by the event handler. The type of data will vary depending on the configured handler. Possible values are:				

Name	Description	
	Value	Description
	Id	An integer indicating the Keyfactor Command reference ID of the configured parameter.
	Key	A string indicating the reference name of the configured parameter.
	DefaultValue	A string indicating the value for the parameter. This value is related to the type of parameter (see <i>ParameterType</i> ).
	ParameterType	<ul> <li>A string containing the parameter type. Supported types are:         <ul> <li>LogTarget</li> <li>This type is used for the event logging handler and is used to reference the fully qualified domain name of the target machine to which event should be logged.</li> </ul> </li> <li>Script         <ul> <li>This type is used for the PowerShell handler and is used to reference the PowerShell script that should be run when the alert is triggered. It is referenced using the filename and optional relative path to the PowerShell script, located in the extensions directory on the Keyfactor Command server.</li> </ul> </li> <li>Token         <ul> <li>This type is used for the PowerShell handler and is used to reference a substitutable special text value that should be passed to the PowerShell script. See Table: Substitutable Special Text for Denied Certificate Request Alerts in the Keyfactor Command Reference Guide for a complete list of available substitutable special text strings.</li> <li>Value</li></ul></li></ul>

### **GET Alerts Denied**

The GET /Alerts/Denied method is used to retrieve details of all denied certificate request alerts configured in Keyfactor Command. Results can be limited to selected alerts using filtering, and URL parameters can be used to specify paging and sorting. This method returns HTTP 200 OK on a success with details about the specified denied certificate request alerts.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: WorkflowManagement: *Read* 

Table 46: GET Alerts Denied Input Parameters

Name	In	Description	
queryString	Query	A string containing a query to limit the results (e.g. field1 -eq value1 AND field2 -gt value2). The default is to return all records. Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns for the same feature. For querying guidelines, refer to the Keyfactor Command Reference Guide: Certificate Search Page. The query fields supported for this endpoint are:  • DisplayName  • Message  • RegisteredEventHandlerId  • Subject  • Template_Id  • UseHandler	
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.	
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.	
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>DisplayName</i> .	
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.	

Table 47: GET Alerts Denied Response Data

Name	Description			
Id	An integer indicating the Keyfactor Command reference ID of the denied request alert.			
DisplayName	A string indicating the display name for the denied request alert. This name appears in the denied request alerts grid in the Management Portal.			
Subject	A string indicating the subject for the email message that will be delivered when the alert is triggered.			
	Tip: Substitutable special text may be used in the subject line. Substitutable special text uses a variable in the alert definition that is replaced by data from the certificate or certificate metadata at processing time. For example, you can enter {rcn} in the alert definition and each alert generated at processing time will contain the specific requested common name of the given certificate request instead of the variable {rcn}.			
Message	A string indicating the email message that will be delivered when the alert is triggered. The email message is made up of regular text and substitutable special text. If desired, you can format the message body using HTML.  For example:  "Hello {requester:givenname},\n\nWe are sorry to report that the certificate you requested on {subdate} in the name {rcn} has not been issued for the following reason:\n\n{cmnt}\n\nCertificate information includes:\n\n\n\n\n\n\n\n\n\table>\n\table>\n\table>\n\table>\n\table>\r <ta>\table&gt;\r<ta>\table&gt;\r<ta>\table&gt;\r<ta>\table&gt;\r<ta>\table&gt;\r<ta>\table&gt;\r<ta>\table&gt;\r&lt;\tabl</ta></ta></ta></ta></ta></ta></ta>			
Recipients	An array of strings containing the recipients for the alert. Each alert can have multiple recipients. You can use specific email addresses and/or use substitutable special text to replace an email address variable with actual email addresses at processing time. Available email substitutable special text strings include:  • {requester:mail}  The certificate requester, based on a lookup in Active Directory of the email address associated with the requester on the certificate.  • Your custom email-based metadata field, which would be specified similarly to {metadata:AppOwnerEmailAddress}.			

Name	Description				
Template	An object containing information about the certificate template for which the denied request alerts will be generated. A separate alert should be configured for each template. An alert may be configured with no template, if desired. Alerts configured in this way generate alerts for all denied certificate requests. Possible values are:				
	Value		Description		
	Id	Id		An integer indicating the Keyfactor Command reference ID for the template, or <i>null</i> for all templates.	
	DisplayName		created using	ining the name of the template. For a template a Microsoft management tool, this will be the plate display name.	
	ForestRoot		A string indica	ting the forest root of the template.	
				This field is retained for legacy purposes and e replaced by ConfigurationTenant field.	
	ConfigurationTenan	nt	A string indica	ting the configuration tenant of the template.	
RegisteredEventHandl- er	An object containing the event handler configuration for the alert, if applicable. Possible values are:				
	Value	Desc	cription		
	Id		teger indicating thandler.	the Keyfactor Command reference ID for the	
		ID		Event Handler Type	
		6		DeniedLogger	
		7		DeniedPowershell	
	DisplayName	A string containing the name of the event handler.		e name of the event handler.	
	UseHandler	A Boolean indicating whether event handler use is enabled for the alert (true) or not (false).			
	For more information about event handlers, see <i>Using Event Handlers</i> in the <i>Keyfactor Command Reference Guide</i> .		see Using Event Handlers in the Keyfactor		
EventHand- lerParameters	An array containing the parameters configured for use by the event handler. The type of data will vary depending on the configured handler. Possible values are:				

Name	Description		
	Value	Description	
	Id	An integer indicating the Keyfactor Command reference ID of the configured parameter.	
	Key	A string indicating the reference name of the configured parameter.	
	DefaultValue	A string indicating the value for the parameter. This value is related to the type of parameter (see <i>ParameterType</i> ).	
	ParameterType	<ul> <li>A string containing the parameter type. Supported types are:         <ul> <li>LogTarget</li> <li>This type is used for the event logging handler and is used to reference the fully qualified domain name of the target machine to which event should be logged.</li> </ul> </li> <li>Script         <ul> <li>This type is used for the PowerShell handler and is used to reference the PowerShell script that should be run when the alert is triggered. It is referenced using the filename and optional relative path to the PowerShell script, located in the extensions directory on the Keyfactor Command server.</li> </ul> </li> <li>Token         <ul> <li>This type is used for the PowerShell handler and is used to reference a substitutable special text value that should be passed to the PowerShell script. See Table: Substitutable Special Text for Denied Certificate Request Alerts in the Keyfactor Command Reference Guide for a complete list of available substitutable special text strings.</li> <li>Value</li> <li>This type is used for the PowerShell handler and is used to reference a static text string that should be passed to the PowerShell script.</li> </ul> </li> </ul>	

### **POST Alerts Denied**

The POST /Alerts/Denied method is used to create a new denied certificate request alert. This method returns HTTP 200 OK on a success with details about the denied certificate request alert.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: WorkflowManagement: *Modify* 

Table 48: POST Alerts Denied Input Parameters

Name	In	Description
DisplayName	Body	<b>Required</b> . A string indicating the display name for the denied request alert. This name appears in the denied request alerts grid in the Management Portal.
Subject	Body	<b>Required</b> . A string indicating the subject for the email message that will be delivered when the alert is triggered.
		Tip: Substitutable special text may be used in the subject line. Substitutable special text uses a variable in the alert definition that is replaced by data from the certificate or certificate metadata at processing time. For example, you can enter {rcn} in the alert definition and each alert generated at processing time will contain the specific requested common name of the given certificate request instead of the variable {rcn}.
Message	Body	<b>Required</b> . A string indicating the email message that will be delivered when the alert is triggered. The email message is made up of regular text and substitutable special text. If desired, you can format the message body using HTML.
		"Hello {requester:givenname},\n\nWe are sorry to report that the certificate you requested on {subdate} in the name {rcn} has not been issued for the following reason:\n\n{cmnt}\n\nCertificate information includes:\n\n\n
		See Table: Substitutable Special Text for Denied Certificate Request Alerts in the Keyfactor Command Reference Guide for a complete list of available substitutable special text strings.
Recipients	Body	An array of strings containing the recipients for the alert. Each alert can have multiple recipients. You can use specific email addresses and/or use substitutable special text to replace an email address variable with actual email addresses at processing time. Available email substitutable special text strings include:  • {requester:mail}  The certificate requester, based on a lookup in Active Directory of the email address associated with the requester on the certificate.  • Your custom email-based metadata field, which would be specified similarly to {metadata:AppOwnerEmailAddress}.
TemplateId	Body	An integer indicating the certificate template for which the denied request alerts will be

Name	In	Description													
		generated. A separate alert should be configured for each template. An alert may be configured with no template, if desired. Alerts configured in this way generate alerts for all denied certificate requests.  Use the GET /Templates method (see GET Templates on page 1185) to retrieve a list of all the templates to determine the template ID.													
Registered Event Handler	Body	An object containing the event handler configuration for the alert, if applicable. Possible values are:													
		Value Description													
		Id	An integer indicati the event handler.	ng the Keyfactor Command reference ID for											
			ID	Event Handler Type											
			6	DeniedLogger											
			7	DeniedPowershell											
		UseHandler	A Boolean indicating whether event handler use is enabled for the alert (true) or not (false).												
		For more information about event handlers, see <i>Using Event Handlers</i> in the <i>Ke Command Reference Guide</i> .		ers, see Using Event Handlers in the Keyfactor											
EventHand- lerParameters	Body			igured for use by the event handler. The type of ed handler. Possible values are:											
		Value	Description												
													Id	_	cating the Keyfactor Command reference gured parameter.
		Key	A string indicating the reference name of the configured parameter.												
		DefaultValue			ring the value for the parameter. This value is type of parameter (see <i>ParameterType</i> ).										
			are:												

Name	In	Description		
		Value	Description	
			This type is used for the event logging handler and is used to reference the fully qualified domain name of the target machine to which event should be logged.  Script This type is used for the PowerShell handler and is used to reference the PowerShell script that should be run when the alert is triggered. It is referenced using the filename and optional relative path to the PowerShell script, located in the extensions directory on the Keyfactor Command server.  Token This type is used for the PowerShell handler and is used to reference a substitutable special text value that should be passed to the PowerShell script. See Table: Substitutable Special Text for Denied Certificate Request Alerts in the Keyfactor Command Reference Guide for a complete list of available substitutable special text strings.  Value This type is used for the PowerShell handler and is used to reference a static text string that should be passed to the PowerShell script.	
		For example, for a Powe	erShell handler:	
		}, { "Id": 29, "Key": "App "DefaultVal		
		{ "Id": 30, "Key": "Tex	t", ue": "Denied Alert: Enterprise Web Server",	

"ParameterType": "Value"

Name	In	Description
		<pre>}, {     "Id": 31,     "Key": "DenialComment",     "DefaultValue": "cmnt",     "ParameterType": "Token" }, {     "Id": 32,     "Key": "ScriptName",     "DefaultValue": "MyScript.ps1",     "ParameterType": "Script" } </pre>

Table 49: POST Alerts Denied Response Data

Name	Description			
Id	An integer indicating the Keyfactor Command reference ID of the denied request alert.			
DisplayName	A string indicating the display name for the denied request alert. This name appears in the denied request alerts grid in the Management Portal.			
Subject	A string indicating the subject for the email message that will be delivered when the alert is triggered.			
	Tip: Substitutable special text may be used in the subject line. Substitutable special text uses a variable in the alert definition that is replaced by data from the certificate or certificate metadata at processing time. For example, you can enter {rcn} in the alert definition and each alert generated at processing time will contain the specific requested common name of the given certificate request instead of the variable {rcn}.			
Message	A string indicating the email message that will be delivered when the alert is triggered. The email message is made up of regular text and substitutable special text. If desired, you can format the message body using HTML.  For example:  "Hello {requester:givenname},\n\nWe are sorry to report that the certificate you requested on {subdate} in the name {rcn} has not been issued for the following reason:\n\n{cmnt}\n\nCertificate information includes:\n\n\n\n\stringth{\text{care} information includes:\n\n <tar>\n\n\n\rtr&gt;\text{care} information includes:\n\n\n\rtr&gt;\text{care} information includes:\n\n\n\rtr&gt;\text{care} information includes:\n\n\n\rtr&gt;\text{care} information includes:\n\n\n\rtr&gt;\text{care} information includes:\n\n\n\rtr&gt;&lt;\td&gt;\text{care} information includes:\n\n\n\rtr&gt;&lt;\td&gt;\text{care} information includes:\n\n\n\rtr&gt;&lt;\td&gt;\text{care} information includes:\n\n\n\rtr&gt;&lt;\td&gt;\text{care} information includes:\n\n\n\rtr&gt;&lt;\td&gt;\text{care} information includes:\n\n\n\rtr&gt;&lt;\td&gt;\text{care} information includes:\n\n\n\rtr&gt;&lt;\td&gt;\n\rtr&gt;&lt;\td&gt;\text{care} information includes:\n\n\n\rtr&gt;&lt;\td&gt;\text{care} information includes:\n\n\n\rtr&gt;&lt;\td&gt;\text{care} information includes:\n\n\n\rtr&gt;&lt;\td&gt;\text{care} information includes:\n\n\n\n\rtr&gt;&lt;\td&gt;\text{care} information includes:\n\n\n\n\rtr&gt;&lt;\td&gt;\text{care} information includes:\n\n\n\n\rtr&gt;&lt;\td&gt;\text{care} information includes:\n\n\n\n\rtr&gt;&lt;\td&gt;\text{care} information includes:\n\n\n\n\rtr&gt;&lt;\text{care} information includes:\n\n\n<tr>\n\rtr&gt;&lt;\text{care} in</tr></tr></tr></tr></tr></tr></tr></tar>			
Recipients	An array of strings containing the recipients for the alert. Each alert can have multiple recipients. You can use specific email addresses and/or use substitutable special text to replace an email address variable with actual email addresses at processing time. Available email substitutable special text strings include:  • {requester:mail}  The certificate requester, based on a lookup in Active Directory of the email address associated with the requester on the certificate.  • Your custom email-based metadata field, which would be specified similarly to {metadata:AppOwnerEmailAddress}.			

Name	Description				
Template	An object containing information about the certificate template for which the denied request alerts will be generated. A separate alert should be configured for each template. An alert may be configured with no template, if desired. Alerts configured in this way generate alerts for all denied certificate requests. Possible values are:				
	Value		Description		
	Id		An integer indicating the Keyfactor Command reference ID for the template, or <i>null</i> for all templates.		
	DisplayName		created using	ining the name of the template. For a template a Microsoft management tool, this will be the plate display name.	
	ForestRoot		A string indica	ting the forest root of the template.	
			Note: This field is retained for legacy purposes and will be replaced by ConfigurationTenant field.		
	ConfigurationTenan	nt	A string indicating the configuration tenant of the template.		
RegisteredEventHandl- er	An object containing tare:	the eve	nt handler config	guration for the alert, if applicable. Possible values	
	Value	Desc	Description		
	Id	An integer indicating the Keyfactor Comevent handler.		the Keyfactor Command reference ID for the	
		ID		Event Handler Type	
		6		DeniedLogger	
		7		DeniedPowershell	
	DisplayName	A stri	ng containing the name of the event handler.		
	UseHandler		lean indicating whether event handler use is enabled for the true) or not (false).		
	For more information about event handlers, see <i>Using Event Handlers</i> in the <i>Keyfacto Command Reference Guide</i> .				
EventHand- lerParameters	An array containing the parameters configured for use by the event handler. The type of data will vary depending on the configured handler. Possible values are:				

Name	Description			
	Value	Description		
	Id	An integer indicating the Keyfactor Command reference ID of the configured parameter.		
	Кеу	A string indicating the reference name of the configured parameter.		
	DefaultValue	A string indicating the value for the parameter. This value is related to the type of parameter (see <i>ParameterType</i> ).		
	ParameterType	<ul> <li>A string containing the parameter type. Supported types are:         <ul> <li>LogTarget</li> <li>This type is used for the event logging handler and is used to reference the fully qualified domain name of the target machine to which event should be logged.</li> </ul> </li> <li>Script         <ul> <li>This type is used for the PowerShell handler and is used to reference the PowerShell script that should be run when the alert is triggered. It is referenced using the filename and optional relative path to the PowerShell script, located in the extensions directory on the Keyfactor Command server.</li> </ul> </li> <li>Token         <ul> <li>This type is used for the PowerShell handler and is used to reference a substitutable special text value that should be passed to the PowerShell script. See Table: Substitutable Special Text for Denied Certificate Request Alerts in the Keyfactor Command Reference Guide for a complete list of available substitutable special text strings.</li> <li>Value</li> <li>This type is used for the PowerShell handler and is used to reference a static text string that should be passed to the PowerShell script.</li> </ul> </li> </ul>		

#### **PUT Alerts Denied**

The PUT /Alerts/Denied method is used to update a denied certificate request alert. This method returns HTTP 200 OK on a success with details about the denied certificate request alert.





Warning: Any previously populated fields that are not submitted with their full existing data using this method will be cleared of their existing data. When using this method, you should first do a GET to retrieve all the values for the record you want to update, enter corrected data into the field(s) you want to update, and then submit all the fields using PUT, including the fields that contain values but which you are not changing.

Table 50: PUT Alerts Denied Input Parameters

Name	In	Description		
id	Path	An integer indicating the Keyfactor Command reference ID of the denied request alert.		
DisplayName	Body	<b>Required</b> . A string indicating the display name for the denied request alert. This name appears in the denied request alerts grid in the Management Portal.		
Subject	Body	<b>Required</b> . A string indicating the subject for the email message that will be delivered when the alert is triggered.		
		Tip: Substitutable special text may be used in the subject line. Substitutable special text uses a variable in the alert definition that is replaced by data from the certificate or certificate metadata at processing time. For example, you can enter {rcn} in the alert definition and each alert generated at processing time will contain the specific requested common name of the given certificate request instead of the variable {rcn}.		
Message	Body	Required. A string indicating the email message that will be delivered when the alert is triggered. The email message is made up of regular text and substitutable special text. If desired, you can format the message body using HTML.  For example:  "Hello {requester:givenname},\n\nWe are sorry to report that the certificate you requested on {subdate} in the name {rcn} has not been issued for the following reason:\n\n{cmnt}\n\nCertificate information includes:\n\n\n     con:\n\n{cmnt}\n\nCertificate information includes:\n\n\n     con:\n\n{cmnt}\n\nCertificate Details           Metadata         {tr><\td>Template: {template}         {td>App          Owner First Name: {metadata:AppOwnerFirstName}         {td>         Careqid}         {td>App Owner Last Name: {metadata:AppOwner Email Address: {metadata:AppOwnerEmailAddress}         {td>App Owner Email Address: {metadata:BusinessCritical}         {td>N(t)         N(n)         N(n		
Recipients	Body	An array of strings containing the recipients for the alert. Each alert can have multiple recipients. You can use specific email addresses and/or use substitutable special text to replace an email address variable with actual email addresses at processing time. Available email substitutable special text strings include:  • {requester:mail}  The certificate requester, based on a lookup in Active Directory of the email address associated with the requester on the certificate.  • Your custom email-based metadata field, which would be specified similarly to {metadata:AppOwnerEmailAddress}.		

Name	In	Description																								
TemplateId	Body	An integer indicating the certificate template for which the denied request alerts will be generated. A separate alert should be configured for each template. An alert may be configured with no template, if desired. Alerts configured in this way generate alerts for all denied certificate requests.  Use the GET /Templates method (see GET Templates on page 1185) to retrieve a list of all the templates to determine the template ID.																								
RegisteredEventHan- dler	Body	An object containing ible values are:	the event handler c	onfiguration for the alert, if applicable. Poss-																						
		Value	Description																							
		Id	An integer indication the event handler.	ng the Keyfactor Command reference ID for																						
			ID	Event Handler Type																						
			6	DeniedLogger																						
			7	DeniedPowershell																						
		UseHandler	A Boolean indicating the alert (true) or r	ng whether event handler use is enabled for not (false).																						
		For more information about event handlers, see <i>Using Event Handlers</i> in the <i>Command Reference Guide</i> .																								
EventHand- lerParameters	Body	An array containing the parameters configured for use by the event handler. The type of data will vary depending on the configured handler. Possible values are:																								
		Value	Description																							
																								Id		cating the Keyfactor Command reference gured parameter.
												Кеу	A string indicat parameter.	ing the reference name of the configured												
		DefaultValue		ring the value for the parameter. This value is type of parameter (see <i>ParameterType</i> ).																						
			A string contain are:	ning the parameter type. Supported types																						

Name	In	Description		
		Value	Description	
			<ul> <li>LogTarget         This type is used for the event logging handler and is used to reference the fully qualified domain name of the target machine to which event should be logged.     </li> <li>Script         This type is used for the PowerShell handler and is used to reference the PowerShell script that should be run when the alert is triggered. It is referenced using the filename and optional relative path to the PowerShell script, located in the extensions directory on the Keyfactor Command server.     </li> <li>Token         This type is used for the PowerShell handler and is used to reference a substitutable special text value that should be passed to the PowerShell script. See Table: Substitutable Special Text for Denied Certificate Request Alerts in the Keyfactor Command Reference Guide for a complete list of available substitutable special text strings.     </li> <li>Value         This type is used for the PowerShell handler and is used to reference a static text string that should be passed to the PowerShell script.     </li> </ul>	
		For example, for a Powe	erShell handler:	
		}, { "Id": 29, "Key": "App "DefaultVal		

Name	In	Description
		<pre>"DefaultValue": "Denied Alert: Enterprise Web Server",     "ParameterType": "Value" }, {     "Id": 31,     "Key": "DenialComment",     "DefaultValue": "cmnt",     "ParameterType": "Token" }, {     "Id": 32,     "Key": "ScriptName",     "DefaultValue": "MyScript.ps1",     "ParameterType": "Script" }</pre>

Table 51: PUT Alerts Denied Response Data

Name	Description			
Id	An integer indicating the Keyfactor Command reference ID of the denied request alert.			
DisplayName	A string indicating the display name for the denied request alert. This name appears in the denied request alerts grid in the Management Portal.			
Subject	A string indicating the subject for the email message that will be delivered when the alert is triggered.			
	Tip: Substitutable special text may be used in the subject line. Substitutable special text uses a variable in the alert definition that is replaced by data from the certificate or certificate metadata at processing time. For example, you can enter {rcn} in the alert definition and each alert generated at processing time will contain the specific requested common name of the given certificate request instead of the variable {rcn}.			
Message	A string indicating the email message that will be delivered when the alert is triggered. The email message is made up of regular text and substitutable special text. If desired, you can format the message body using HTML.  For example:  "Hello {requester:givenname},\n\nWe are sorry to report that the certificate you requested on {subdate} in the name {rcn} has not been issued for the following reason:\n\n{cmnt}\n\nCertificate information includes:\n\n\n\n\stringth{\text{care} information includes:\n\n <tar>\n\n\n\rtr&gt;\text{care} information includes:\n\n\n\rtr&gt;\text{care} information includes:\n\n\n\rtr&gt;\text{care} information includes:\n\n\n\rtr&gt;\text{care} information includes:\n\n\n\rtr&gt;\text{care} information includes:\n\n\n\rtr&gt;&lt;\td&gt;\text{care} information includes:\n\n\n\rtr&gt;&lt;\td&gt;\text{care} information includes:\n\n\n\rtr&gt;&lt;\td&gt;\text{care} information includes:\n\n\n\rtr&gt;&lt;\td&gt;\text{care} information includes:\n\n\n\rtr&gt;&lt;\td&gt;\text{care} information includes:\n\n\n\rtr&gt;&lt;\td&gt;\text{care} information includes:\n\n\n\rtr&gt;&lt;\td&gt;\n\rtr&gt;&lt;\td&gt;\text{care} information includes:\n\n\n\rtr&gt;&lt;\td&gt;\text{care} information includes:\n\n\n\rtr&gt;&lt;\td&gt;\text{care} information includes:\n\n\n\rtr&gt;&lt;\td&gt;\text{care} information includes:\n\n\n\n\rtr&gt;&lt;\td&gt;\text{care} information includes:\n\n\n\n\rtr&gt;&lt;\td&gt;\text{care} information includes:\n\n\n\n\rtr&gt;&lt;\td&gt;\text{care} information includes:\n\n\n\n\rtr&gt;&lt;\td&gt;\text{care} information includes:\n\n\n\n\rtr&gt;&lt;\text{care} information includes:\n\n\n<tr>\n\rtr&gt;&lt;\text{care} in</tr></tr></tr></tr></tr></tr></tr></tar>			
Recipients	An array of strings containing the recipients for the alert. Each alert can have multiple recipients. You can use specific email addresses and/or use substitutable special text to replace an email address variable with actual email addresses at processing time. Available email substitutable special text strings include:  • {requester:mail}  The certificate requester, based on a lookup in Active Directory of the email address associated with the requester on the certificate.  • Your custom email-based metadata field, which would be specified similarly to {metadata:AppOwnerEmailAddress}.			

Name	Description				
Template	An object containing information about the certificate template for which the denied request alerts will be generated. A separate alert should be configured for each template. An alert may be configured with no template, if desired. Alerts configured in this way generate alerts for all denied certificate requests. Possible values are:				
	Value		Description		
	Id		An integer indicating the Keyfactor Command reference ID for the template, or <i>null</i> for all templates.		
	DisplayName		created using	ining the name of the template. For a template a Microsoft management tool, this will be the plate display name.	
	ForestRoot		A string indica	ting the forest root of the template.	
			Note: This field is retained for legacy purposes and will be replaced by ConfigurationTenant field.		
	ConfigurationTenan	nt	A string indicating the configuration tenant of the template.		
RegisteredEventHandl- er	An object containing tare:	the eve	nt handler config	guration for the alert, if applicable. Possible values	
	Value	Desc	Description		
	Id	An integer indicating the Keyfactor Comevent handler.		the Keyfactor Command reference ID for the	
		ID		Event Handler Type	
		6		DeniedLogger	
		7		DeniedPowershell	
	DisplayName	A stri	ng containing the name of the event handler.		
	UseHandler		lean indicating whether event handler use is enabled for the true) or not (false).		
	For more information about event handlers, see <i>Using Event Handlers</i> in the <i>Keyfacto Command Reference Guide</i> .				
EventHand- lerParameters	An array containing the parameters configured for use by the event handler. The type of data will vary depending on the configured handler. Possible values are:				

Name	Description		
	Value	Description	
	Id	An integer indicating the Keyfactor Command reference ID of the configured parameter.	
	Кеу	A string indicating the reference name of the configured parameter.	
	DefaultValue	A string indicating the value for the parameter. This value is related to the type of parameter (see <i>ParameterType</i> ).	
	ParameterType	<ul> <li>A string containing the parameter type. Supported types are:         <ul> <li>LogTarget</li> <li>This type is used for the event logging handler and is used to reference the fully qualified domain name of the target machine to which event should be logged.</li> </ul> </li> <li>Script         <ul> <li>This type is used for the PowerShell handler and is used to reference the PowerShell script that should be run when the alert is triggered. It is referenced using the filename and optional relative path to the PowerShell script, located in the extensions directory on the Keyfactor Command server.</li> </ul> </li> <li>Token         <ul> <li>This type is used for the PowerShell handler and is used to reference a substitutable special text value that should be passed to the PowerShell script. See Table: Substitutable Special Text for Denied Certificate Request Alerts in the Keyfactor Command Reference Guide for a complete list of available substitutable special text strings.</li> <li>Value</li> <li>This type is used for the PowerShell handler and is used to reference a static text string that should be passed to the PowerShell script.</li> </ul> </li> </ul>	

# 2.2.4.2 Alerts Expiration

The Alerts Expiration component of the Keyfactor API includes methods necessary to create, update, retrieve, schedule, and delete alerts for expired certificates.

Table 52: Alerts Expiration

Endpoint	Method	Description	Link
/Alerts/Expiration/{id}	DELETE	Deletes an expired certificate for the	DELETE Alerts Expiration

Endpoint	Method	Description	Link
		specified ID.	ID on the next page
/Alerts/Expiration/{id}	GET	Retrieves details for an expired certificate for the specified ID.	GET Alerts Expiration ID on the next page
/Alerts/Expiration/Schedule	GET	Retrieves details of the schedule for delivery of expired certificate alerts.	GET Alerts Expiration Schedule on page 69
/Alerts/Expiration/Schedule	PUT	Updates the schedule for delivery of expired certificate alerts.	PUT Alerts Expiration Schedule on page 70
/Alerts/Expiration	GET	Retrieves details for all configured expired certificate.	GET Alerts Expiration on page 72
/Alerts/Expiration	POST	Creates a new expired certificate alert.	POST Alerts Expiration on page 76
/Alerts/Expiration	PUT	Updates an expired certificate for the specified ID.	PUT Alerts Expiration on page 83
/Alerts/Expiration/Test	POST	Test an Expiration Alert	POST Alerts Expiration Test on page 90
/Alerts/Expiration/TestAll	POST	Test All Expiration Alerts	POST Alerts Expiration Test All on page 92

### **DELETE Alerts Expiration ID**

The DELETE /Alerts/Expiration/{id} method is used to delete the expiration alert with the specified ID. This endpoint returns 204 with no content upon success.



Table 53: DELETE Alerts Expiration {id} Input Parameters

Name	In	Description
id	Path	Required. An integer indicating the Keyfactor Command reference ID for the expiration alert to be deleted.  Use the GET /Alerts/Expiration method (see GET Alerts Expiration on page 72) to retrieve a list of all the expiration alerts to determine the alert ID.

## **GET Alerts Expiration ID**

The GET /Alerts/Expiration/{id} method is used to retrieve details for the expiration alert with the specified ID. This method returns HTTP 200 OK on a success with details about the specified alert.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: WorkflowManagement: *Read* 

Table 54: GET Alerts Expiration {id} Input Parameters

Name	In	Description
id	Path	<b>Required</b> . An integer indicating the Keyfactor Command reference ID for the expiration alert. Use the <i>GET /Alerts/Expiration</i> method (see <u>GET Alerts Expiration on page 72</u> ) to retrieve a list of all the expiration alerts to determine the alert ID.

Table 55: GET Alerts Expiration {id} Response Data

Name	Description		
Id	An integer indicating the Keyfactor Command reference ID of the expiration alert.		
DisplayName	A string indicating the display name for the expiration alert. This name appears in the Expiration Certificate Request Alerts grid in the Management Portal.		
Subject	A string indicating the subject for the email message that will be delivered when the alert is triggered.		
Message	A string indicating the email message that will be delivered when the alert is triggered.  The email message is made up of regular text and substitutable special text. If desired, you can format the message body using HTML.  See <i>Table: Substitutable Special Text for Expiration Alerts</i> in the <i>Keyfactor Command Reference Guide</i> for a complete list of available substitutable special text strings.		
ExpirationWarningDays	An integer indicating the number of days prior to expiration to send the warning.		
Recipients	An object containing the recipients for the alert. Each alert can have multiple recipients.  You can use specific email addresses and/or use substitutable special text to replace an email address variable with actual email addresses at processing time. Available email substitutable special text strings include:  • {requester:mail}  The certificate requester, based on a lookup in Active Directory of the email address associated with the requester on the certificate.  • Your custom email-based metadata field, which would be specified similarly to {metadata:AppOwnerEmailAddress}.		
CertificateQuery	An array indicating the certificate collection on which the alert is based. Possible values are:		
	Value Description		
	Id An integer indicating the Keyfactor Command reference ID for the certificate collection.		
	Name A string containing the name of the certificate collection.		
	For more information about certificate collections, see Saving Search Criteria as a Collection in the Keyfactor Command Reference Guide.		

Name	Description			
RegisteredEventHandler	An array containing the event handler configuration for the alert, if applicable. Possible values are:			
	Value	Description		
	Id	An integer indicathe event handle	ating the Keyfactor Command reference ID for er.	
		ID	Event Handler Type	
		1	ExpirationLogger	
		2	ExpirationPowershell	
		3	ExpirationRenewal	
	DisplayName	A string containing the name of the event handler.		
	UseHandler	A Boolean indicating whether event handler use is enabled for the alert (true) or not (false).		
	For more information  Command Reference (		lers, see Using Event Handlers in the Keyfactor	
EventHandlerParameters			nfigured for use by the event handler. The type of red handler. Possible values are:	
	Value	Description		
	Id	An integer ind	icating the Keyfactor Command reference ID of parameter.	
	Key	A string indica meter.	ting the reference name of the configured para-	
	DefaultValue	_	ting the value for the parameter. This value is type of parameter (see <i>ParameterType</i> ).	
	ParameterType	<ul> <li>LogTarge</li> <li>This type</li> <li>used to</li> </ul>	et ining the parameter type. Supported types are: et e is used for the event logging handler and is reference the fully qualified domain name of et machine to which event should be logged.	

Name	Description	
	Value	Description
		<ul> <li>Script         This type is used for the PowerShell handler and is used to reference the PowerShell script that should be run when the alert is triggered. It is referenced using the filename and optional relative path to the PowerShell script, located in the extensions directory on the Keyfactor Command server.     </li> <li>Token         This type is used for the PowerShell handler and is used to reference a substitutable special text value that should be passed to the PowerShell script. See Table: Substitutable Special Text for Expiration Alerts in the Keyfactor Command Reference Guide for a complete list of available substitutable special text strings.     </li> <li>Value         This type is used for the PowerShell handler and is used to reference a static text string that should be passed to the PowerShell script.     </li> </ul>

#### **GET Alerts Expiration Schedule**

The GET /Alerts/Expiration/Schedule method is used to retrieve the schedule for delivery of expiration alerts configured in Keyfactor Command. This method returns HTTP 200 OK on a success with details of the schedule for expiration alerts. This method has no input parameters other than the standard headers (see <a href="Web API Common Features">Web API Common Features</a> on page 3).



Table 56: GET Alerts Expiration Schedule Response Data

Name	Description				
Schedule	An array indic	ating the schedule	ting the schedule for delivery of the expiration alerts. Possible values are:		
	Name	Description			
	Daily	A dictionary that indicates a job scheduled to run every day at the same time with the parameter:			
		Name	Description		
	Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:m-m:ss.000Z (e.g. 2021-05-19T16:23:01Z).			
		For example, da	nily at 11:30 pm:		
		"Daily": {     "Time": }	"2022-02-25T23:30:00Z"		

## **PUT Alerts Expiration Schedule**

The PUT /Alerts/Expiration/Schedule method is used to create or update the schedule for delivery of expiration alerts configured in Keyfactor Command. This method returns HTTP 200 OK on a success with details of the schedule for the alerts.



Table 57: PUT Alerts Expiration Schedule Input Parameters

Name	In	Description			
Schedule	Body	An array indic	cating the schedule for delivery of the expiration alerts. Possible values are:		
		Name	Description		
	Daily		A dictionary that indicates a job scheduled to run every day at the same time with the parameter:		
			Name	Description	
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
			For example, da	aily at 11:30 pm:	
			"Daily": {     "Time": }	"2022-02-25T23:30:00Z"	

Table 58: PUT Alerts Expiration Schedule Response Data

Name	Description				
Schedule	An array indic	ating the schedule	ting the schedule for delivery of the expiration alerts. Possible values are:		
	Name	Description			
	Daily	A dictionary that indicates a job scheduled to run every day at the same time with the parameter:			
		Name	Description		
	Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:m-m:ss.000Z (e.g. 2021-05-19T16:23:01Z).			
		For example, da	nily at 11:30 pm:		
		"Daily": {     "Time": }	"2022-02-25T23:30:00Z"		

## **GET Alerts Expiration**

The GET /Alerts/Expiration method is used to retrieve details of all expiration alerts configured in Keyfactor Command. Results can be limited to selected alerts using filtering, and URL parameters can be used to specify paging and sorting. This method returns HTTP 200 OK on a success with details about the specified alert.



Table 59: GET Alerts Expiration Input Parameters

Name	In	Description
queryString	Query	A string containing a query to limit the results (e.g. field1 -eq value1 AND field2 -gt value2). The default is to return all records. Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns for the same feature. For querying guidelines, refer to the Keyfactor Command Reference Guide: Certificate Search Page. The query fields supported for this endpoint are:  • CertificateQueryId  • Days  • DisplayName  • Message  • RegisteredEventHandlerId  • ScheduledTaskId  • Subject  • UseHandler
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>DisplayName</i> .
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.

Table 60: GET Alerts Expiration Response Data

Name	Description			
Id	An integer indicating the Keyfactor Command reference ID of the expiration alert.			
DisplayName	A string indicating the display name for the expiration alert. This name appears in the Expiration Certificate Request Alerts grid in the Management Portal.			
Subject	A string indicati is triggered.	ng the subject for the email message that will be delivered when the alert		
Message	The email mess you can format See <i>Table: Subs</i>	ng the email message that will be delivered when the alert is triggered. age is made up of regular text and substitutable special text. If desired, the message body using HTML. titutable Special Text for Expiration Alerts in the Keyfactor Command Reference complete list of available substitutable special text strings.		
ExpirationWarningDays	An integer indic	ating the number of days prior to expiration to send the warning.		
Recipients	An object containing the recipients for the alert. Each alert can have multiple recipients.  You can use specific email addresses and/or use substitutable special text to replace an email address variable with actual email addresses at processing time. Available email substitutable special text strings include:  • {requester:mail}  The certificate requester, based on a lookup in Active Directory of the email address associated with the requester on the certificate.  • Your custom email-based metadata field, which would be specified similarly to {metadata:AppOwnerEmailAddress}.			
CertificateQuery	An array indicating the certificate collection on which the alert is based. Possible values are:			
	Value Description			
	Id	An integer indicating the Keyfactor Command reference ID for the certificate collection.		
	Name A string containing the name of the certificate collection.  For more information about certificate collections, see Saving Search Criteria as a C tion in the Keyfactor Command Reference Guide.			

Name	Description			
Registered Event Handler	An array containing the event handler configuration for the alert, if applicable. Possible values are:			
	Value	Description		
	Id	An integer indicating the Keyfactor Command reference ID for the event handler.		
		ID	Event Handler Type	
		1	ExpirationLogger	
		2	ExpirationPowershell	
		3	ExpirationRenewal	
	DisplayName	A string containing the name of the event handler.		
	UseHandler A Boolean indicating whether event handler use is enabled for the alert (true) or not (false).			
	For more information about event handlers, see <i>Using Event Handlers</i> in the <i>Keyfactor Command Reference Guide</i> .			
EventHandlerParameters			configured for use by the event handler. The type of gured handler. Possible values are:	
	Value	Description	on	
	Id An integer indicating the Keyfactor Command reference the configured parameter.			
	Key	A string indicating the reference name of the configured parameter.		
	DefaultValue	A string indicating the value for the parameter. This value is related to the type of parameter (see <i>ParameterType</i> ).		
	ParameterType	• LogTo This t used	ntaining the parameter type. Supported types are: arget type is used for the event logging handler and is to reference the fully qualified domain name of arget machine to which event should be logged.	

Name	Description			
	Value	Description		
		<ul> <li>Script         This type is used for the PowerShell handler and is used to reference the PowerShell script that should be run when the alert is triggered. It is referenced using the filename and optional relative path to the Power-Shell script, located in the extensions directory on the Keyfactor Command server.     </li> <li>Token         This type is used for the PowerShell handler and is used to reference a substitutable special text value that should be passed to the PowerShell script. See Table: Substitutable Special Text for Expiration Alerts in the Keyfactor Command Reference Guide for a complete list of available substitutable special text strings.     </li> <li>Value         This type is used for the PowerShell handler and is used to reference a static text string that should be passed to the PowerShell script.     </li> </ul>		

#### **POST Alerts Expiration**

The POST /Alerts/Expiration method is used to create a new expiration alert. This method returns HTTP 200 OK on a success with details about the expiration alert.



Table 61: POST Alerts Expiration Input Parameters

Name	In	Description
DisplayName	Body	<b>Required</b> . A string indicating the display name for the expiration alert. This name appears in the Expiration Certificate Request Alerts grid in the Management Portal.
Subject	Body	<b>Required</b> . A string indicating the subject for the email message that will be delivered when the alert is triggered.
		Tip: Substitutable special text may be used in the subject line. Substitutable special text uses a variable in the alert definition that is replaced by data from the certificate or certificate metadata at processing time. For example, you can enter {cn} in the alert definition and each alert generated at processing time will contain the specific common name of the given certificate instead of the variable {cn}.
Message	Body	Required. A string indicating the email message that will be delivered when the alert is triggered. The email message is made up of regular text and substitutable special text. If desired, you can format the message body using HTML.  For example:  "Hello {requester:givenname},\n\nThe certificate in the name {cn} issued on {certnotbefore} from {CAreqID} using the {template} template will expire on {certnotafter}. If this certificate is still in use, please consider getting a new one.\n\nCertificate information includes:\n\n\n
ExpirationWarningDays	Body	<b>Required</b> . An integer indicating the number of days prior to expiration to send the warning.
Recipients	Body	An object containing the recipients for the alert. Each alert can have multiple recipients. You can use specific email addresses and/or use substitutable special text to replace an email address variable with actual email addresses

Name	In	Description		
		<ul> <li>at processing time. Available email substitutable special text strings include:</li> <li>{requester:mail}         The certificate requester, based on a lookup in Active Directory of the email address associated with the requester on the certificate.     </li> <li>Your custom email-based metadata field, which would be specified similarly to {metadata:AppOwnerEmailAddress}.</li> </ul>		
CertificateQueryId	Body	Required. An integer indicating the certificate collection on which to base the alert.  Use the GET /CertificateCollections method (see GET Certificate Collections on page 355) to retrieve a list of all the certificate collections to determine the collection ID.		
RegisteredEventHandler	Body	An array containing able. Possible value		er configuration for the alert, if applic-
		Value	Description	
		ld	An integer indicating the Keyfactor Command reference ID for the event handler.	
			ID	Event Handler Type
			1	ExpirationLogger
			2	ExpirationPowershell
			3	ExpirationRenewal
		UseHandler		icating whether event handler use is e alert (true) or not (false).
		For more information		andlers, see <i>Using Event Handlers</i> in the e.
Event Handler Parameters	Body			s configured for use by the event epending on the configured handler.
		Value	Descripti	on
		Id		indicating the Keyfactor Command  ID of the configured parameter.

Name	In	Description	
		Value	Description
		Key	A string indicating the reference name of the configured parameter.
		DefaultValue	A string indicating the value for the parameter. This value is related to the type of parameter (see <i>ParameterType</i> ).
		ParameterType	A string containing the parameter type.  Supported types are:  • LogTarget  This type is used for the event logging handler and is used to reference the fully qualified domain name of the target machine to which event should be logged.  • Script  This type is used for the PowerShell handler and is used to reference the PowerShell script that should be run when the alert is triggered. It is referenced using the filename and optional relative path to the PowerShell script, located in the extensions directory on the Keyfactor Command server.  • Token  This type is used for the PowerShell handler and is used to reference a substitutable special text value that should be passed to the PowerShell script. See  Table: Substitutable Special Text for Expiration Alerts in the Keyfactor Command Reference Guide for a complete list of available substitutable special text strings.  • Value  This type is used for the PowerShell handler and is used to reference a static text string that should be passed to the PowerShell script.
		For example, for a Pow	verShell handler:

Name	In	Description
		<pre>"EventHandlerParameters": [</pre>

Table 62: POST Alerts Expiration Response Data

Name	Description			
Id	An integer indicating the Keyfactor Command reference ID of the expiration alert.			
DisplayName	A string indicating the display name for the expiration alert. This name appears in the Expiration Certificate Request Alerts grid in the Management Portal.			
Subject	A string indicati is triggered.	ng the subject for the email message that will be delivered when the alert		
Message	The email mess you can format See <i>Table: Subs</i>	ng the email message that will be delivered when the alert is triggered. age is made up of regular text and substitutable special text. If desired, the message body using HTML. titutable Special Text for Expiration Alerts in the Keyfactor Command Reference complete list of available substitutable special text strings.		
ExpirationWarningDays	An integer indic	ating the number of days prior to expiration to send the warning.		
Recipients	An object containing the recipients for the alert. Each alert can have multiple recipients.  You can use specific email addresses and/or use substitutable special text to replace an email address variable with actual email addresses at processing time. Available email substitutable special text strings include:  • {requester:mail}  The certificate requester, based on a lookup in Active Directory of the email address associated with the requester on the certificate.  • Your custom email-based metadata field, which would be specified similarly to {metadata:AppOwnerEmailAddress}.			
CertificateQuery	An array indicating the certificate collection on which the alert is based. Possible values are:			
	Value Description			
	Id	An integer indicating the Keyfactor Command reference ID for the certificate collection.		
	Name A string containing the name of the certificate collection.  For more information about certificate collections, see Saving Search Criteria as a C tion in the Keyfactor Command Reference Guide.			

Name	Description				
Registered Event Handler	An array containing the event handler configuration for the alert, if applicable. Possible values are:				
	Value	Value Description			
	Id	An integer indicating the Keyfactor Command reference ID for the event handler.			
		ID	Event Handler Type		
		1	ExpirationLogger		
		2	ExpirationPowershell		
		3	ExpirationRenewal		
	DisplayName	A string containing the name of the event handler.			
	UseHandler A Boolean indicating whether event handler use is enabled for the alert (true) or not (false).				
	For more information about event handlers, see <i>Using Event Handlers</i> in the <i>Keyfactor Command Reference Guide</i> .				
EventHandlerParameters			configured for use by the event handler. The type of gured handler. Possible values are:		
	Value	Descriptio	n		
	Id An integer indicating the Keyfactor Command reference ID the configured parameter.				
	Key A string indicating the reference name of the conf meter.		cating the reference name of the configured para-		
	DefaultValue	A string indicating the value for the parameter. This value is related to the type of parameter (see <i>ParameterType</i> ).			
	ParameterType	<ul> <li>LogTa         This ty         used t     </li> </ul>	taining the parameter type. Supported types are: rget ype is used for the event logging handler and is to reference the fully qualified domain name of rget machine to which event should be logged.		

Name	Description				
	Value	Description			
		<ul> <li>Script         This type is used for the PowerShell handler and is used to reference the PowerShell script that should be run when the alert is triggered. It is referenced using the filename and optional relative path to the Power-Shell script, located in the extensions directory on the Keyfactor Command server.     </li> <li>Token         This type is used for the PowerShell handler and is used to reference a substitutable special text value that should be passed to the PowerShell script. See Table: Substitutable Special Text for Expiration Alerts in the Keyfactor Command Reference Guide for a complete list of available substitutable special text strings.     </li> <li>Value         This type is used for the PowerShell handler and is used to reference a static text string that should be passed to the PowerShell script.     </li> </ul>			

#### **PUT Alerts Expiration**

The PUT /Alerts/Expiration method is used to update an expiration alert. This method returns HTTP 200 OK on a success with details about the alert.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: WorkflowManagement: *Modify* 



**Warning:** Any previously populated fields that are not submitted with their full existing data using this method will be cleared of their existing data. When using this method, you should first do a GET to retrieve all the values for the record you want to update, enter corrected data into the field(s) you want to update, and then submit all the fields using PUT, including the fields that contain values but which you are not changing.

Table 63: PUT Alerts Expiration Input Parameters

Name	In	Description
id	Path	<b>Required</b> . An integer indicating the Keyfactor Command reference ID of the expiration alert.
DisplayName	Body	<b>Required</b> . A string indicating the display name for the expiration alert. This name appears in the Expiration Certificate Request Alerts grid in the Management Portal.
Subject	Body	<b>Required</b> . A string indicating the subject for the email message that will be delivered when the alert is triggered.
		Tip: Substitutable special text may be used in the subject line. Substitutable special text uses a variable in the alert definition that is replaced by data from the certificate or certificate metadata at processing time. For example, you can enter {cn} in the alert definition and each alert generated at processing time will contain the specific common name of the given certificate instead of the variable {cn}.
Message	Body	Required. A string indicating the email message that will be delivered when the alert is triggered. The email message is made up of regular text and substitutable special text. If desired, you can format the message body using HTML.  For example:  "Hello {requester:givenname},\n\nThe certificate in the name {cn} issued on {certnotbefore} from {CAreqID} using the {template} template will expire on {certnotafter}. If this certificate is still in use, please consider getting a new one.\n\nCertificate information includes:\n\n\n
ExpirationWarningDays	Body	<b>Required</b> . An integer indicating the number of days prior to expiration to send the warning.

Name	In	Description		
Recipients	Body	An object containing the recipients for the alert. Each alert can have multiple recipients. You can use specific email addresses and/or use substitutable special text to replace an email address variable with actual email addresses at processing time. Available email substitutable special text strings include:  • {requester:mail}  The certificate requester, based on a lookup in Active Directory of the email address associated with the requester on the certificate.  • Your custom email-based metadata field, which would be specified similarly to {metadata:AppOwnerEmailAddress}.		
CertificateQueryId	Body	Required. An integer indicating the certificate collection on which to base the alert.  Use the GET / Certificate Collections method (see GET Certificate Collections on page 355) to retrieve a list of all the certificate collections to determine the collection ID.		
RegisteredEventHandler	Body	An array containing the event handler configuration for the alert, if applicable. Possible values are:		
		Value Description		
		Id		icating the Keyfactor Command refer- e event handler.
			ID	Event Handler Type
			1	ExpirationLogger
			2	ExpirationPowershell
			3	ExpirationRenewal
		UseHandler		icating whether event handler use is e alert (true) or not (false).
		For more information about event handlers, see <i>Using Event Handlers Keyfactor Command Reference Guide</i> .		
EventHandlerParameters	Body	An object containing the parameters configured for use by the event handler. The type of data will vary depending on the configured handler. Possible values are:		

Name	In	Description	
		Value	Description
		Id	An integer indicating the Keyfactor Command reference ID of the configured parameter.
		Key	A string indicating the reference name of the configured parameter.
		DefaultValue	A string indicating the value for the parameter. This value is related to the type of parameter (see <i>ParameterType</i> ).
		ParameterType	<ul> <li>A string containing the parameter type.</li> <li>Supported types are: <ul> <li>LogTarget</li> <li>This type is used for the event logging handler and is used to reference the fully qualified domain name of the target machine to which event should be logged.</li> <li>Script</li> <li>This type is used for the PowerShell handler and is used to reference the PowerShell script that should be run when the alert is triggered. It is referenced using the filename and optional relative path to the PowerShell script, located in the extensions directory on the Keyfactor Command server.</li> </ul> </li> <li>Token  This type is used for the PowerShell handler and is used to reference a substitutable special text value that should be passed to the PowerShell script. See  Table: Substitutable Special Text for Expiration Alerts in the Keyfactor  Command Reference Guide for a complete list of available substitutable special text strings.</li> <li>Value  This type is used for the PowerShell handler and is used to reference a static text string that should be passed to the PowerShell script.</li> </ul>

In Description Name For example, for a PowerShell handler: "EventHandlerParameters": [ { "Id": 28, "Key": "cn", "DefaultValue": "cn",
"ParameterType": "Token" }, "Id": 29, "Key": "AppOwnerFirstName", "DefaultValue": "metadata:AppOwnerFirstName",
"ParameterType": "Token" }, "Id": 30, "Key": "Text",
"DefaultValue": "Expiration Alert: Enterprise Web Server", "ParameterType": "Value" }, "Id": 32, "Key": "ScriptName", "DefaultValue": "MyScript.ps1",
"ParameterType": "Script" ]

Table 64: PUT Alerts Expiration Response Data

Name	Description		
Id	An integer indicating the Keyfactor Command reference ID of the expiration alert.		
DisplayName	A string indicating the display name for the expiration alert. This name appears in the Expiration Certificate Request Alerts grid in the Management Portal.		
Subject	A string indicating the subject for the email message that will be delivered when the alert is triggered.		
Message	A string indicating the email message that will be delivered when the alert is triggered. The email message is made up of regular text and substitutable special text. If desired, you can format the message body using HTML.  See <i>Table: Substitutable Special Text for Expiration Alerts</i> in the <i>Keyfactor Command Reference Guide</i> for a complete list of available substitutable special text strings.		
ExpirationWarningDays	An integer indicating the number of days prior to expiration to send the warning.		
Recipients	An object containing the recipients for the alert. Each alert can have multiple recipients.  You can use specific email addresses and/or use substitutable special text to replace an email address variable with actual email addresses at processing time. Available email substitutable special text strings include:  • {requester:mail}  The certificate requester, based on a lookup in Active Directory of the email address associated with the requester on the certificate.  • Your custom email-based metadata field, which would be specified similarly to {metadata:AppOwnerEmailAddress}.		
CertificateQuery	An array indicating the certificate collection on which the alert is based. Possible values are:		
	Value Description		
	Id An integer indicating the Keyfactor Command reference ID for the certificate collection.		
	Name A string containing the name of the certificate collection.		
	For more information about certificate collections, see Saving Search Criteria as a Collection in the Keyfactor Command Reference Guide.		

Name	Description			
Registered Event Handler	An array containing the event handler configuration for the alert, if applicable. Possible values are:			
	Value	Description		
	Id	An integer ind the event hand	icating the Keyfactor Command reference ID for dler.	
		ID	Event Handler Type	
		1	ExpirationLogger	
		2	ExpirationPowershell	
		3	ExpirationRenewal	
	DisplayName	A string containing the name of the event handler.		
	UseHandler	A Boolean indicating whether event handler use is enabled for the alert (true) or not (false).		
	For more information about event handlers, see <i>Using Event Handlers</i> in the <i>Keyfactor Command Reference Guide</i> .			
EventHandlerParameters			configured for use by the event handler. The type of gured handler. Possible values are:	
	Value	Descriptio	n	
	Id		ndicating the Keyfactor Command reference ID of ed parameter.	
	Key	A string indi meter.	cating the reference name of the configured para-	
	DefaultValue	_	cating the value for the parameter. This value is ne type of parameter (see <i>ParameterType</i> ).	
	ParameterType	<ul> <li>LogTa         This ty         used t     </li> </ul>	taining the parameter type. Supported types are: rget ype is used for the event logging handler and is to reference the fully qualified domain name of rget machine to which event should be logged.	

Name	Description		
	Value	Description	
		<ul> <li>Script         This type is used for the PowerShell handler and is used to reference the PowerShell script that should be run when the alert is triggered. It is referenced using the filename and optional relative path to the PowerShell script, located in the extensions directory on the Keyfactor Command server.     </li> <li>Token         This type is used for the PowerShell handler and is used to reference a substitutable special text value that should be passed to the PowerShell script. See Table: Substitutable Special Text for Expiration Alerts in the Keyfactor Command Reference Guide for a complete list of available substitutable special text strings.     </li> <li>Value         This type is used for the PowerShell handler and is used to reference a static text string that should be passed to the PowerShell script.     </li> </ul>	

## **POST Alerts Expiration Test**

The POST /Alerts/Expiration/Test method is used to test individual certificate expiration alerts. This method returns HTTP 200 OK on a success with details about the resulting alerts generated or a response of "NoActionTaken" if no certificates match the test criteria entered.



**Tip:** Alerts are generated when a certificate has expired or is approaching expiration as defined by the timeframe configured in the alert.

By default, a maximum of 100 alerts will be generated during a test. The maximum value is configurable with the *Expiration Alert Test Result Limit* setting in Keyfactor Command application settings (see <u>Application Settings</u>: Console <u>Tab</u> in the *Keyfactor Command Reference Guide*). If more than 100 alerts are generated, no email messages will be sent and you'll have the opportunity to view the first 100 alerts generated.

If you're using an event handler, the event handler is run and the handler actions taken (PowerShell script run, event log message written, certificates renewed) when the test is run. This is true regardless of the setting of the *SendAlerts* flag.



**Tip:** The following permissions (see Security Overview) are required to use this feature:

WorkflowManagement: Read WorkflowManagement: Test

Table 65: POST Alerts Expiration Test Input Parameters

Name	In	Description		
expirationAlertTestRequest	Body	<b>Required</b> . An array containing information for the alert test. Alert test detail values are:		
		Name	Description	
		AlertId	Required. An integer indicating the reference ID of expiration alert to test.  Use the GET /Alerts/Expiration method (see GET Alerts Expiration on page 72) to retrieve a list of all your expiration alerts to determine the alert Id.	
			EvaluationDate	Required. A string indicating the start date/time for the test, in UTC.  You can use the date range to simulate running the alerts a month from now instead of today, for example, or put in a broad date range to be sure you pick up some expiring certificates for testing purposes.
		PreviousEvaluationDate	<b>Required</b> . A string indicating the end date/time for the test, in UTC.	
		SendAlerts	A Boolean indicating whether to send alert emails with the test (true) or not (false). The default is <i>false</i> .	
		For example:		
			22-08-31T20:51:33.528Z", te": "2022-08-31T20:51:33.528Z",	

Table 66: POST Alerts Expiration Test Response Data

Parameter	Description		
ExpirationAlerts	An object containing alert details resulting from the test. Expiration alert details are:		
	Name	Description	
	CAName	A string indicating the certificate authority that issued the certificate in hostname\logical name format.	
	CARow	An integer containing the CA's reference ID for certificate.	
	IssuedCN	A string indicating the common name of the certificate.	
	Expiry	A string indicating the date and time when the certificate expires.	
	Subject	A string indicating the subject for the email message, including any replaced substitutable special text.	
	Message	A string indicating the email message, including any replaced substitutable special text.  See <i>Table: Substitutable Special Text for Expiration Alerts</i> in the <i>Keyfactor Command Reference Guide</i> for a complete list of available substitutable special text strings.	
	Recipients	An object containing the recipients for the alert.	
	SendDate	A string indicating the date on which the alert will be sent, based on configuration of the <i>ExpirationWarningDays</i> in the alert (e.g. if the alert is configured for one month before expiration and the certificate expires on July 20, the alert will have a send date of June 20).	
AlertBuildResult	A string indicating	the outcome of the test (e.g. Success).	

# **POST Alerts Expiration Test All**

The POST /Alerts/Expiration/TestAll method is used to test all certificate expiration alerts. This method returns HTTP 200 OK on a success with details about the resulting alerts generated or a response of "NoActionTaken" if no certificates match the test criteria entered.



**Tip:** Alerts are generated when a certificate has expired or is approaching expiration as defined by the timeframe configured in the alert.



By default, a maximum of 100 alerts will be generated during a test. The maximum value is configurable with the *Expiration Alert Test Result Limit* setting in Keyfactor Command application settings (see <u>Application Settings</u>: Console Tab in the *Keyfactor Command Reference Guide*). If more than 100 alerts are generated, no email messages will be sent and you'll have the opportunity to view the first 100 alerts generated.

If you're using an event handler, the event handler is run and the handler actions taken (PowerShell script run, event log message written, certificates renewed) when the test is run. This is true regardless of the setting of the *SendAlerts* flag.



**Tip:** The following permissions (see Security Overview) are required to use this feature:

WorkflowManagement: *Read* WorkflowManagement: *Test* 

Table 67: POST Alerts Expiration Test All Input Parameters

Name	In	Description		
expirationAlertTestRequest	Body	<b>Required</b> . An array containing information for the alert test. Alert test detail values are:		
		Name	Description	
		EvaluationDate	Required. A string indicating the start date/time for the test, in UTC.  You can use the date range to simulate running the alerts a month from now instead of today, for example, or put in a broad date range to be sure you pick up some expiring certificates for testing purposes.	
		PreviousEvaluationDate	<b>Required</b> . A string indicating the end date/time for the test, in UTC.	
		SendAlerts	A Boolean indicating whether to send alert emails with the test (true) or not (false). The default is <i>false</i> .	
		For example:		
			22-08-31T20:51:33.528Z", te": "2022-08-31T20:51:33.528Z",	

Table 68: POST Alerts Expiration Test All Response Data

Parameter	Description			
ExpirationAlerts	An object contain	An object containing alert details resulting from the test. Expiration alert details are:		
	Name	Description		
	CAName	A string indicating the certificate authority that issued the certificate in hostname\logical name format.		
	CARow	An integer containing the CA's reference ID for certificate.		
	IssuedCN	A string indicating the common name of the certificate.		
	Expiry	A string indicating the date and time when the certificate expires.		
	Subject	A string indicating the subject for the email message, including any replaced substitutable special text.		
	Message	A string indicating the email message, including any replaced substitutable special text.  See <i>Table: Substitutable Special Text for Expiration Alerts</i> in the <i>Keyfactor Command Reference Guide</i> for a complete list of available substitutable special text strings.		
	Recipients	An object containing the recipients for the alert.		
	SendDate	A string indicating the date on which the alert will be sent, based on configuration of the <i>ExpirationWarningDays</i> in the alert (e.g. if the alert is configured for one month before expiration and the certificate expires on July 20, the alert will have a send date of June 20).		
AlertBuildResult	A string indicating	the outcome of the test (e.g. Success).		

## 2.2.4.3 Alerts Issued

The Alerts Issued component of the Keyfactor API includes methods necessary to create, update, retrieve, schedule, and delete alerts for issued certificate requests.

Table 69: Alerts Issued

Endpoint	Method	Description	Link
/Alerts/Issued/{id}	DELETE	Deletes an issued certificate request alert for the specified ID.	DELETE Alerts Issued  ID on the next page

Endpoint	Method	Description	Link
/Alerts/Issued/{id}	GET	Retrieves details for an issued certificate request alert for the specified ID.	GET Alerts Issued ID below
/Alerts/Issued/Schedule	GET	Retrieves details of the schedule for delivery of issued certificate request alerts.	GET Alerts Issued Schedule on page 100
/Alerts/Issued/Schedule	PUT	Updates the schedule for delivery of issued certificate request alerts.	PUT Alerts Issued Schedule on page 101
/Alerts/Issued	GET	Retrieves details for all configured issued certificate request alerts.	GET Alerts Issued on page 103
/Alerts/Issued	POST	Creates a new issued certificate request alert.	POST Alerts Issued on page 108
/Alerts/Issued	PUT	Updates an issued certificate request alert for the specified ID.	PUT Alerts Issued on page 116

#### **DELETE Alerts Issued ID**

The DELETE /Alerts/Issued/{id} method is used to delete the issued certificate request alert with the specified ID. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: WorkflowManagement: *Modify* 

Table 70: DELETE Alerts Issued {id} Input Parameters

Name	In	Description
id	Path	Required. An integer indicating the Keyfactor Command reference ID for the issued certificate request alert to be deleted.  Use the GET /Alerts/Issued method (see GET Alerts Issued on page 103) to retrieve a list of all the issued request alerts to determine the alert ID.

#### **GET Alerts Issued ID**

The GET /Alerts/Issued/{id} method is used to retrieve details for the issued certificate request alerts with the specified ID. This method returns HTTP 200 OK on a success with details about the specified issued certificate request alert.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: WorkflowManagement: *Read* 

Table 71: GET Alerts Issued {id} Input Parameters

Name	In	Description
id	Path	Required. An integer indicating the Keyfactor Command reference ID for the issued certificate request alert.  Use the GET /Alerts/Issued method (see GET Alerts Issued on page 103) to retrieve a list of all the issued request alerts to determine the alert ID.

Table 72: GET Alerts Issued {id} Response Data

Name	Description		
Id	An integer indicating the Keyfactor Command reference ID of the issued request alert.		
DisplayName	A string indicating the display name for the issued request alert. This name appears in the issued request alerts grid in the Management Portal.		
Subject	A string indicating the subject for the email message that will be delivered when the alert is triggered.  Tip: Substitutable special text may be used in the subject line. Substitutable special text uses a variable in the alert definition that is replaced by data from the certificate or certificate metadata at processing time. For example, you can enter {rcn} in the alert definition and each alert generated at processing time will contain the specific requested common name of the given certificate request instead of the variable {rcn}.		
Message	A string indicating the email message that will be delivered when the alert is triggered. The email message is made up of regular text and substitutable special text. If desired, you can format the message body using HTML.  For example:  "Hello {requester:givenname},\n\nThe certificate you requested in the name {cn} was successfully issued on {certnotbefore}. You can download it from here:\n\n{dnld-link}\n\nCertificate information includes:\n\n\n		
Recipients	An array of strings containing the recipients for the alert. Each alert can have multiple recipients. You can use specific email addresses and/or use substitutable special text to replace an email address variable with actual email addresses at processing time. Available email substitutable special text strings include:  • {requester:mail}  The certificate requester, based on a lookup in Active Directory of the email address associated with the requester on the certificate.		

Name	Description				
	<ul> <li>Your custom email-based metadata field, which would be specified similarly to {metadata:AppOwnerEmailAddress}.</li> </ul>				
Template	request alerts will be generat		ted. A separate vith no templa	e certificate template for which the issued e alert should be configured for each template. te, if desired. Alerts configured in this way uests. Possible values are:	
	Value	Value		n	
	Id			ndicating the Keyfactor Command reference emplate, or <i>null</i> for All Templates.	
	DisplayName		template cr	taining the name of the template. For a eated using a Microsoft management tool, the Microsoft template display name.	
	ForestRoot  ConfigurationTenant		A string indicating the forest root of the template.		
			Note: This field is retained for legacy purposes and will be replaced by ConfigurationTenant field.		
			A string indicating the configuration tenant of the template.		
RegisteredEventHandler	An object containing to values are:	the eve	nt handler con	ofiguration for the alert, if applicable. Possible	
	Value	Desc	cription		
	Id		teger indicatin vent handler.	ng the Keyfactor Command reference ID for	
		ID		Event Handler Type	
		4		IssuedLogger	
		5		IssuedPowershell	
	DisplayName	A stri	A string containing the name of the event handler.		
			olean indicatin lert (true) or n	g whether event handler use is enabled for ot (false).	

Name	Description			
	For more information about event handlers, see <i>Using Event Handlers</i> in the <i>Keyfactor Command Reference Guide</i> .			
EventHandlerParameters		ing the parameters configured for use by the event handler. The type of pending on the configured handler. Possible values are:		
	Value	Description		
	Id	An integer indicating the Keyfactor Command reference ID of the configured parameter.		
	Кеу	A string indicating the reference name of the configured parameter.		
	DefaultValue	A string indicating the value for the parameter. This value is related to the type of parameter (see <i>ParameterType</i> ).		
	ParameterType	<ul> <li>A string containing the parameter type. Supported types are:</li> <li>LogTarget         This type is used for the event logging handler and is used to reference the fully qualified domain name of the target machine to which event should be logged.     </li> <li>Script         This type is used for the PowerShell handler and is used to reference the PowerShell script that should be run when the alert is triggered. It is referenced using the filename and optional relative path to the PowerShell script, located in the extensions directory on the Keyfactor Command server.     </li> <li>Token         This type is used for the PowerShell handler and is used to reference a substitutable special text value that should be passed to the PowerShell script. See Table: Substitutable Special Text for Issued Certificate Alerts in the Keyfactor Command Reference Guide for a complete list of available substitutable special text strings.     </li> <li>Value         This type is used for the PowerShell handler and is used to reference a static text string that should be passed to the PowerShell script.     </li> </ul>		

### **GET Alerts Issued Schedule**

The GET /Alerts/Issued/Schedule method is used to retrieve the schedule for delivery of issued certificate request alerts configured in Keyfactor Command. This method returns HTTP 200 OK on a success with details of the schedule for issued certificate request alerts. This method has no input parameters other than the standard headers (see Web API Common Features on page 3).



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: WorkflowManagement: *Read* 

Table 73: GET Alerts Issued Schedule Response Data

Name	Description				
Schedule	An array indic	licating the schedule for delivery of the issued request alerts. Possible values are:			
	Name	Description			
	Interval	A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database.			
		Name Description			
		Minutes An integer indicating interval.	ting the number of minutes between each		
		For example, every hour:			
		"Interval": {     "Minutes": 60 }			
	Daily	A dictionary that indicates a job scheduled to run every day at the same time with the parameter:			
		Name Description			
		given using the IS	e to next run the job. The date and time should be O 8601 UTC time format YYYY-MM-DDTHH:m-021-05-19T16:23:01Z).		
		For example, daily at 11:30 pm:			
		"Daily": {     "Time": "2022-02-25T23:3 }	0:00Z"		

### **PUT Alerts Issued Schedule**

The PUT /Alerts/Issued/Schedule method is used to create or update the schedule for delivery of issued certificate request alerts configured in Keyfactor Command. This method returns HTTP 200 OK on a success with details of the schedule for issued certificate request alerts.



 $\textbf{Tip: } The following permissions (see \underline{Security\ Overview}) are required to use this feature: \\ WorkflowManagement: \underline{\textit{Modify}}$ 

Table 74: PUT Alerts Issued Schedule Input Parameters

Name	In	Description			
Schedule	Body	An array indic	ating the schedule	for delivery of the issued request alerts. Possible values are:	
		Name	Description		
		Interval	A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted minutes when stored in the database.		
			Name	Description	
			Minutes	An integer indicating the number of minutes between each interval.	
			For example, ev	ery hour:	
			"Interval":     "Minutes }	·	
		Daily	A dictionary that with the parame	t indicates a job scheduled to run every day at the same time eter:	
			Name	Description	
	should be given using the		The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).		
			For example, daily at 11:30 pm:		
			"Daily": {     "Time": }	"2022-02-25T23:30:00Z"	

Table 75: PUT Alerts Issued Schedule Response Data

Name	Description				
Schedule	An array indic	licating the schedule for delivery of the issued request alerts. Possible values are:			
	Name	Description			
	Interval	A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database.			
		Name Description			
		Minutes An integer indicating interval.	ting the number of minutes between each		
		For example, every hour:			
		"Interval": {     "Minutes": 60 }			
	Daily	A dictionary that indicates a job scheduled to run every day at the same time with the parameter:			
		Name Description			
		given using the IS	e to next run the job. The date and time should be O 8601 UTC time format YYYY-MM-DDTHH:m-021-05-19T16:23:01Z).		
		For example, daily at 11:30 pm:			
		"Daily": {     "Time": "2022-02-25T23:3 }	0:00Z"		

#### **GET Alerts Issued**

The GET /Alerts/Issued method is used to retrieve details of all issued certificate request alerts configured in Keyfactor Command. Results can be limited to selected alerts using filtering, and URL parameters can be used to specify paging and sorting. This method returns HTTP 200 OK on a success with details about the specified issued certificate request alerts.



 $\textbf{Tip: } The following permissions (see \underline{Security\ Overview}) are required to use this feature: \\ WorkflowManagement: \\ \textit{Read}$ 

Table 76: GET Alerts Issued Input Parameters

Name	In	Description
queryString	Query	A string containing a query to limit the results (e.g. field1 -eq value1 AND field2 -gt value2). The default is to return all records. Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns for the same feature. For querying guidelines, refer to the Keyfactor Command Reference Guide: Certificate Search Page. The query fields supported for this endpoint are:  • DisplayName  • Message  • RegisteredEventHandlerId  • Subject  • Template_Id  • UseHandler
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>DisplayName</i> .
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.

Table 77: GET Alerts Issued Response Data

Name	Description
ld	An integer indicating the Keyfactor Command reference ID of the issued request alert.
DisplayName	A string indicating the display name for the issued request alert. This name appears in the issued request alerts grid in the Management Portal.
Subject	A string indicating the subject for the email message that will be delivered when the alert is triggered.
	Tip: Substitutable special text may be used in the subject line. Substitutable special text uses a variable in the alert definition that is replaced by data from the certificate or certificate metadata at processing time. For example, you can enter {rcn} in the alert definition and each alert generated at processing time will contain the specific requested common name of the given certificate request instead of the variable {rcn}.
Message	A string indicating the email message that will be delivered when the alert is triggered. The email message is made up of regular text and substitutable special text. If desired, you can format the message body using HTML.  For example:  "Hello {requester:givenname},\n\nThe certificate you requested in the name {cn} was successfully issued on {certnotbefore}. You can download it from here:\n\n{dnld-link}\n\nCertificate information includes:\n\n\n
Recipients	An array of strings containing the recipients for the alert. Each alert can have multiple recipients. You can use specific email addresses and/or use substitutable special text to replace an email address variable with actual email addresses at processing time. Available email substitutable special text strings include:  • {requester:mail}  The certificate requester, based on a lookup in Active Directory of the email address associated with the requester on the certificate.

Name	Description				
	<ul> <li>Your custom email-based metadata field, which would be specified similarly to {metadata:AppOwnerEmailAddress}.</li> </ul>				
Template	request alerts will be generat		ted. A separate vith no templa	e certificate template for which the issued e alert should be configured for each template. te, if desired. Alerts configured in this way uests. Possible values are:	
	Value	Value		n	
	Id			ndicating the Keyfactor Command reference emplate, or <i>null</i> for All Templates.	
	DisplayName		template cr	taining the name of the template. For a eated using a Microsoft management tool, the Microsoft template display name.	
	ForestRoot  ConfigurationTenant		A string indicating the forest root of the template.		
			Note: This field is retained for legacy purposes and will be replaced by ConfigurationTenant field.		
			A string indicating the configuration tenant of the template.		
RegisteredEventHandler	An object containing t values are:	he eve	nt handler con	ifiguration for the alert, if applicable. Possible	
	Value	Desc	cription		
	Id		teger indicatin vent handler.	g the Keyfactor Command reference ID for	
		ID		Event Handler Type	
		4		IssuedLogger	
		5		IssuedPowershell	
	DisplayName	A stri	ng containing	the name of the event handler.	
			olean indicating whether event handler use is enabled for lert (true) or not (false).		

Name	Description			
	For more information about event handlers, see <i>Using Event Handlers</i> in the <i>Keyfactor Command Reference Guide</i> .			
EventHandlerParameters		the parameters configured for use by the event handler. The type of nding on the configured handler. Possible values are:		
	Value	Description		
	Id	An integer indicating the Keyfactor Command reference ID of the configured parameter.		
	Key	A string indicating the reference name of the configured parameter.		
	DefaultValue	A string indicating the value for the parameter. This value is related to the type of parameter (see <i>ParameterType</i> ).		
	ParameterType	<ul> <li>A string containing the parameter type. Supported types are:         <ul> <li>LogTarget</li> <li>This type is used for the event logging handler and is used to reference the fully qualified domain name of the target machine to which event should be logged.</li> </ul> </li> <li>Script         <ul> <li>This type is used for the PowerShell handler and is used to reference the PowerShell script that should be run when the alert is triggered. It is referenced using the filename and optional relative path to the PowerShell script, located in the extensions directory on the Keyfactor Command server.</li> </ul> </li> <li>Token         <ul> <li>This type is used for the PowerShell handler and is used to reference a substitutable special text value that should be passed to the PowerShell script. See Table: Substitutable Special Text for Issued Certificate Alerts in the Keyfactor Command Reference Guide for a complete list of available substitutable special text strings.</li> <li>Value             <ul> <li>This type is used for the PowerShell handler and is used to reference a static text string that should be passed to the PowerShell script.</li> </ul> </li> </ul></li></ul>		

### **POST Alerts Issued**

The POST /Alerts/Issued method is used to create a new issued certificate request alert. This method returns HTTP 200 OK on a success with details about the issued certificate request alert.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: WorkflowManagement: *Modify* 

Table 78: POST Alerts Issued Input Parameters

Name	In	Description
DisplayName	Body	<b>Required</b> . A string indicating the display name for the issued request alert. This name appears in the issued request alerts grid in the Management Portal.
Subject	Body	<b>Required</b> . A string indicating the subject for the email message that will be delivered when the alert is triggered.
		Tip: Substitutable special text may be used in the subject line. Substitutable special text uses a variable in the alert definition that is replaced by data from the certificate or certificate metadata at processing time. For example, you can enter {rcn} in the alert definition and each alert generated at processing time will contain the specific requested common name of the given certificate request instead of the variable {rcn}.
Message	Body	Required. A string indicating the email message that will be delivered when the alert is triggered. The email message is made up of regular text and substitutable special text. If desired, you can format the message body using HTML.  For example:  "Hello {requester:givenname},\n\nThe certificate you requested in the name {cn} was successfully issued on {certnotbefore}. You can download it from here:\n\n{dnldlink}\n\nCertificate information includes:\n\n <t-able>\n</t-able>
Recipients	Body	An array of strings containing the recipients for the alert. Each alert can have multiple recipients. You can use specific email addresses and/or use substitutable special text to replace an email address variable with actual email addresses at processing time. Available email substitutable special text strings include:  • {requester:mail}

Name	In	Description		
		The certificate requester, based on a lookup in Active Directory of the email address associated with the requester on the certificate.  • Your custom email-based metadata field, which would be specified similarly to {metadata:AppOwnerEmailAddress}.		
TemplateId	Body	An integer indicating the certificate template for which the issued request alerts will be generated. A separate alert should be configured for each template. An alert may be configured with no template, if desired. Alerts configured in this way generate alerts for all issued certificate requests.  Use the GET /Templates method (see GET Templates on page 1185) to retrieve a list of all the templates to determine the template ID.		
RegisteredEventHandler	Body	An object containing able. Possible value		er configuration for the alert, if applic-
		Value	Description	
		Id	An integer indicence ID for the	cating the Keyfactor Command referevent handler.
			ID	Event Handler Type
			4	IssuedLogger
			5	IssuedPowershell
		UseHandler		cating whether event handler use is alert (true) or not (false).
		For more information  Keyfactor Command		andlers, see <i>Using Event Handlers</i> in the
Event Handler Parameters	Body	An array containing the parameters configured The type of data will vary depending on the covalues are:		
		Value	Descriptio	on
		Id	_	indicating the Keyfactor Command  D of the configured parameter.
		Key	A string ind configured	icating the reference name of the parameter.

<b>Value</b> DefaultValue	Description
DefaultValue	A shall a limit a shall a shall a family a same and
	A string indicating the value for the parameter. This value is related to the type of parameter (see <i>ParameterType</i> ).
ParameterType	A string containing the parameter type.  Supported types are:  LogTarget This type is used for the event logging handler and is used to reference the fully qualified domain name of the target machine to which event should be logged.  Script This type is used for the PowerShell handler and is used to reference the PowerShell script that should be run when the alert is triggered. It is referenced using the filename and optional relative path to the PowerShell script, located in the extensions directory on the Keyfactor Command server.  Token This type is used for the PowerShell handler and is used to reference a substitutable special text value that should be passed to the PowerShell script. See Table: Substitutable Special Text for Issued Certificate Alerts in the Keyfactor Command Reference Guide for a complete list of available substitutable special text strings.  Value This type is used for the PowerShell handler and is used to reference a static text string that should be passed to the PowerShell script.
For example, for a Pow	verShell handler:

In Description Name "EventHandlerParameters": [ "Id": 28, "Key": "cn", "DefaultValue": "cn", "ParameterType": "Token" }, "Id": 29, "Key": "AppOwnerFirstName", "DefaultValue": "metadata:AppOwnerFirstName", "ParameterType": "Token" "Id": 30, "Key": "Text", "DefaultValue": "Issued Alert: Enterprise Web Server", "ParameterType": "Value" }, "Id": 31, "Key": "DownloadLink", "DefaultValue": "dnldlink",
"ParameterType": "Token" }, "Id": 32, "Key": "ScriptName", "DefaultValue": "MyScript.ps1", "ParameterType": "Script" } ]

Table 79: POST Alerts Issued Response Data

Name	Description				
Id	An integer indicating the Keyfactor Command reference ID of the issued request alert.				
DisplayName	A string indicating the display name for the issued request alert. This name appears in the issued request alerts grid in the Management Portal.				
Subject	A string indicating the subject for the email message that will be delivered when the alert is triggered.				
	Tip: Substitutable special text may be used in the subject line. Substitutable special text uses a variable in the alert definition that is replaced by data from the certificate or certificate metadata at processing time. For example, you can enter {rcn} in the alert definition and each alert generated at processing time will contain the specific requested common name of the given certificate request instead of the variable {rcn}.				
Message	A string indicating the email message that will be delivered when the alert is triggered. The email message is made up of regular text and substitutable special text. If desired, you can format the message body using HTML.  For example:  "Hello {requester:givenname},\n\nThe certificate you requested in the name {cn} was successfully issued on {certnotbefore}. You can download it from here:\n\n{dnld-link}\n\nCertificate information includes:\n\n\n				
Recipients	An array of strings containing the recipients for the alert. Each alert can have multiple recipients. You can use specific email addresses and/or use substitutable special text to replace an email address variable with actual email addresses at processing time. Available email substitutable special text strings include:  • {requester:mail}  The certificate requester, based on a lookup in Active Directory of the email address associated with the requester on the certificate.				

Name	Description				
	<ul> <li>Your custom email-based metadata field, which would be specified similarly to {metadata:AppOwnerEmailAddress}.</li> </ul>				
Template	An object containing information about the certificate template for which the issued request alerts will be generated. A separate alert should be configured for each template. An alert may be configured with no template, if desired. Alerts configured in this way generate alerts for all issued certificate requests. Possible values are:				
	Value		Description		
	Id	Id		ndicating the Keyfactor Command reference emplate, or <i>null</i> for All Templates.	
	DisplayName		A string containing the name of the template. For a template created using a Microsoft management tool, this will be the Microsoft template display name.		
	ForestRoot		A string indicating the forest root of the template.		
			Note: This field is retained for legacy purposes and will be replaced by ConfigurationTenant field.		
	ConfigurationTenant		A string indicating the configuration tenant of the template.		
RegisteredEventHandler	An object containing the event handler configuration for the alert, if applicable. Possible values are:				
	Value	Desc	cription		
	Id	An integer indicating the Keyfactor Command reference ID for the event handler.			
		ID		Event Handler Type	
		4		IssuedLogger	
		5		IssuedPowershell	
	DisplayName	A string containing the name of the event handler.			
			olean indicatin lert (true) or n	g whether event handler use is enabled for ot (false).	

Name	Description			
	For more information about event handlers, see <i>Using Event Handlers</i> in the <i>Keyfactor Command Reference Guide</i> .			
EventHandlerParameters	An array containing the parameters configured for use by the event handler. The type of data will vary depending on the configured handler. Possible values are:			
	Value	Description		
	Id	An integer indicating the Keyfactor Command reference ID of the configured parameter.		
	Key	A string indicating the reference name of the configured parameter.		
	DefaultValue	A string indicating the value for the parameter. This value is related to the type of parameter (see <i>ParameterType</i> ).		
	ParameterType	<ul> <li>A string containing the parameter type. Supported types are:         <ul> <li>LogTarget</li> <li>This type is used for the event logging handler and is used to reference the fully qualified domain name of the target machine to which event should be logged.</li> </ul> </li> <li>Script         <ul> <li>This type is used for the PowerShell handler and is used to reference the PowerShell script that should be run when the alert is triggered. It is referenced using the filename and optional relative path to the PowerShell script, located in the extensions directory on the Keyfactor Command server.</li> </ul> </li> <li>Token         <ul> <li>This type is used for the PowerShell handler and is used to reference a substitutable special text value that should be passed to the PowerShell script. See Table: Substitutable Special Text for Issued Certificate Alerts in the Keyfactor Command Reference Guide for a complete list of available substitutable special text strings.</li> <li>Value             <ul> <li>This type is used for the PowerShell handler and is used to reference a static text string that should be passed to the PowerShell script.</li> </ul> </li> </ul></li></ul>		

#### **PUT Alerts Issued**

The PUT /Alerts/Issued method is used to update an issued certificate request alert. This method returns HTTP 200 OK on a success with details about the issued certificate request alert.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: WorkflowManagement: Modify



Warning: Any previously populated fields that are not submitted with their full existing data using this method will be cleared of their existing data. When using this method, you should first do a GET to retrieve all the values for the record you want to update, enter corrected data into the field(s) you want to update, and then submit all the fields using PUT, including the fields that contain values but which you are not changing.

Table 80: PUT Alerts Issued Input Parameters

Name	In	Description		
id	Path	An integer indicating the Keyfactor Command reference ID of the issued request alert.		
DisplayName	Body	<b>Required</b> . A string indicating the display name for the issued request alert. This name appears in the issued request alerts grid in the Management Portal.		
Subject	Body	<b>Required</b> . A string indicating the subject for the email message that will be delivered when the alert is triggered.		
		Tip: Substitutable special text may be used in the subject line. Substitutable special text uses a variable in the alert definition that is replaced by data from the certificate or certificate metadata at processing time. For example, you can enter {rcn} in the alert definition and each alert generated at processing time will contain the specific requested common name of the given certificate request instead of the variable {rcn}.		
Message	Body	Required. A string indicating the email message that will be delivered when the alert is triggered. The email message is made up of regular text and substitutable special text. If desired, you can format the message body using HTML.  For example:  "Hello {requester:givenname},\n\nThe certificate you requested in the name {cn} was successfully issued on {certnotbefore}. You can download it from here:\n\n{dnldlink}\n\nCertificate information includes:\n\n <t-able>\n\n\n\n\serial \n\nterest\n\n\serial \n\nterest\n\n\r\n\n\r\n\n\r\r\r&lt;\n\r&lt;\r&lt;\r&lt;\r&lt;\r&lt;\r&lt;\r&lt;\r&lt;\r&lt;\r&lt;\r&lt;\r&lt;\r&lt;\</t-able>		
Recipients	Body	An array of strings containing the recipients for the alert. Each alert can have multiple recipients. You can use specific email addresses and/or use substitutable special text to replace an email address variable with actual email addresses at processing time. Available email substitutable special text		

Name	In	Description			
		strings include:  • {requester:mail}  The certificate requester, based on a lookup in Active Directory of the email address associated with the requester on the certificate.  • Your custom email-based metadata field, which would be specified similarly to {metadata:AppOwnerEmailAddress}.			
TemplateId	Body	An integer indicating the certificate template for which the issued request alerts will be generated. A separate alert should be configured for each template. An alert may be configured with no template, if desired. Alerts configured in this way generate alerts for all issued certificate requests.  Use the GET /Templates method (see GET Templates on page 1185) to retrieve a list of all the templates to determine the template ID.			
RegisteredEventHandler	Body	An object containing the event handler configuration for the alert, if applicable. Possible values are:			
		Value Description			
		ld	An integer indicating the Keyfactor Command reference ID for the event handler.		
			ID	Event Handler Type	
			4	IssuedLogger	
			5	IssuedPowershell	
		UseHandler		rating whether event handler use is alert (true) or not (false).	
		For more information  Keyfactor Command		ndlers, see <i>Using Event Handlers</i> in the	
Event Handler Parameters	Body	An array containing the parameters configured for use by the event handler. The type of data will vary depending on the configured handler. Possible values are:			
		Value	Descriptio	n	
		Id		ndicating the Keyfactor Command O of the configured parameter.	

Name	In	Description		
		Value	Description	
		Key	A string indicating the reference name of the configured parameter.	
		DefaultValue	A string indicating the value for the parameter. This value is related to the type of parameter (see <i>ParameterType</i> ).	
		ParameterType	A string containing the parameter type.  Supported types are:  • LogTarget  This type is used for the event logging handler and is used to reference the fully qualified domain name of the target machine to which event should be logged.  • Script  This type is used for the PowerShell handler and is used to reference the PowerShell script that should be run when the alert is triggered. It is referenced using the filename and optional relative path to the PowerShell script, located in the extensions directory on the Keyfactor Command server.  • Token  This type is used for the PowerShell handler and is used to reference a substitutable special text value that should be passed to the PowerShell script. See  Table: Substitutable Special Text for Issued Certificate Alerts in the Keyfactor Command Reference Guide for a complete list of available substitutable special text strings.  • Value  This type is used for the PowerShell handler and is used to reference a static text string that should be passed to the PowerShell script.	
		For example, for a Pow	verShell handler:	

Name	In	Description
		<pre>"EventHandlerParameters": [</pre>

Table 81: PUT Alerts Issued Response Data

Name	Description			
Id	An integer indicating the Keyfactor Command reference ID of the issued request alert.			
DisplayName	A string indicating the display name for the issued request alert. This name appears in the issued request alerts grid in the Management Portal.			
Subject	A string indicating the subject for the email message that will be delivered when the alert is triggered.			
	Tip: Substitutable special text may be used in the subject line. Substitutable special text uses a variable in the alert definition that is replaced by data from the certificate or certificate metadata at processing time. For example, you can enter {rcn} in the alert definition and each alert generated at processing time will contain the specific requested common name of the given certificate request instead of the variable {rcn}.			
Message	A string indicating the email message that will be delivered when the alert is triggered. The email message is made up of regular text and substitutable special text. If desired, you can format the message body using HTML.  For example:  "Hello {requester:givenname},\n\nThe certificate you requested in the name {cn} was successfully issued on {certnotbefore}. You can download it from here:\n\n{dnld-link}\n\nCertificate information includes:\n\n\n			
Recipients	An array of strings containing the recipients for the alert. Each alert can have multiple recipients. You can use specific email addresses and/or use substitutable special text to replace an email address variable with actual email addresses at processing time. Available email substitutable special text strings include:  • {requester:mail}  The certificate requester, based on a lookup in Active Directory of the email address associated with the requester on the certificate.			

Name	Description				
	<ul> <li>Your custom email-based metadata field, which would be specified similarly to {metadata:AppOwnerEmailAddress}.</li> </ul>				
Template	An object containing information about the certificate template for which the issued request alerts will be generated. A separate alert should be configured for each template. An alert may be configured with no template, if desired. Alerts configured in this way generate alerts for all issued certificate requests. Possible values are:				
	Value		Description		
	Id	Id		ndicating the Keyfactor Command reference emplate, or <i>null</i> for All Templates.	
	DisplayName		A string containing the name of the template. For a template created using a Microsoft management tool, this will be the Microsoft template display name.		
	ForestRoot		A string indicating the forest root of the template.		
			Note: This field is retained for legacy purposes and will be replaced by ConfigurationTenant field.		
	ConfigurationTenant		A string indicating the configuration tenant of the template.		
RegisteredEventHandler	An object containing the event handler configuration for the alert, if applicable. Possible values are:				
	Value	Desc	cription		
	Id	An integer indicating the Keyfactor Command reference ID for the event handler.			
		ID		Event Handler Type	
		4		IssuedLogger	
		5		IssuedPowershell	
	DisplayName	A string containing the name of the event handler.			
			olean indicatin lert (true) or n	g whether event handler use is enabled for ot (false).	

Name	Description			
	For more information a Command Reference Gu	bout event handlers, see <i>Using Event Handlers</i> in the <i>Keyfactor uide</i> .		
EventHandlerParameters		An array containing the parameters configured for use by the event handler. The type of data will vary depending on the configured handler. Possible values are:		
	Value	Description		
	Id	An integer indicating the Keyfactor Command reference ID of the configured parameter.		
	Кеу	A string indicating the reference name of the configured parameter.		
	DefaultValue	A string indicating the value for the parameter. This value is related to the type of parameter (see <i>ParameterType</i> ).		
	ParameterType	<ul> <li>A string containing the parameter type. Supported types are:</li> <li>LogTarget         This type is used for the event logging handler and is used to reference the fully qualified domain name of the target machine to which event should be logged.     </li> <li>Script         This type is used for the PowerShell handler and is used to reference the PowerShell script that should be run when the alert is triggered. It is referenced using the filename and optional relative path to the PowerShell script, located in the extensions directory on the Keyfactor Command server.     </li> <li>Token         This type is used for the PowerShell handler and is used to reference a substitutable special text value that should be passed to the PowerShell script. See Table: Substitutable Special Text for Issued Certificate Alerts in the Keyfactor Command Reference Guide for a complete list of available substitutable special text strings.     </li> <li>Value         This type is used for the PowerShell handler and is used to reference a static text string that should be passed to the PowerShell script.     </li> </ul>		

### 2.2.4.4 Alerts Key Rotation

The Alerts Key Rotation component of the Keyfactor API includes methods necessary to create, update, retrieve, schedule, and delete alerts for SSH keys approaching the end of the key lifetime. The default key lifetime is 365 days, but this setting is configurable (see <u>Application Settings: SSH Tab</u> in the *Keyfactor Command Reference Guide*). Key rotation alerts apply to both user keys (see <u>My SSH Key</u> in the *Keyfactor Command Reference Guide*) and service account keys (see <u>Service Account Keys</u> in the *Keyfactor Command Reference Guide*) generated within Keyfactor Command.

Table 82: Alerts Key Rotation

Endpoint	Method	Description	Link
/Alerts/KeyRotation/{id}	DELETE	Deletes an SSH key rotation alert for the specified ID.	DELETE Alerts Key Rotation ID below
/Alerts/KeyRotation/{id}	GET	Retrieves details for the SSH key rotation alert for the specified ID.	GET Alerts Key Rotation  ID on the next page
/Alerts/KeyRotation/Schedule	GET	Retrieves details of the schedule for delivery of SSH key rotation alerts.	GET Alerts Key Rotation Schedule on page 128
/Alerts/KeyRotation/Schedule	PUT	Updates the schedule for delivery of SSH key rotation alerts.	PUT Alerts Key Rotation Schedule on page 129
/Alerts/KeyRotation	GET	Retrieves details for all configured SSH key rotation alerts.	GET Alerts Key Rotation on page 131
/Alerts/KeyRotation	POST	Creates a new SSH key rotation alert.	POST Alerts Key Rotation on page 135
/Alerts/KeyRotation	PUT	Updates the SSH key rotation alert for a specified ID.	PUT Alerts Key Rotation on page 142
/Alerts/KeyRotation/Test	POST	Used to test specific SSH key rotation alerts.	POST Alerts Key Rotation Test on page 149
/Alerts/KeyRotation/TestAll	POST	Used to test all SSH key rotation alerts.	POST Alerts Key Rota- tion Test All on page 151

### **DELETE Alerts Key Rotation ID**

The DELTE /Alerts/KeyRotation/{id} method is used to delete the SSH key rotation alert with the specified ID. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: WorkflowManagement: *Modify* 

Table 83: DELETE Alerts Key Rotation {id} Input Parameters

Name	In	Description
id	Path	Required. An integer indicating the Keyfactor Command reference ID for the SSH key rotation alert to be deleted.  Use the GET /Alerts/KeyRotation method (see GET Alerts Key Rotation on page 131) to retrieve a list of all the SSH key rotation alerts to determine the alert ID.

## **GET Alerts Key Rotation ID**

The GET /Alerts/KeyRotation/{id} method is used to retrieve details for the SSH key rotation alerts with the specified ID. This method returns HTTP 200 OK on a success with details about the specified SSH key rotation alert.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: WorkflowManagement: *Read* 

Table 84: GET Alerts Key Rotation {id} Input Parameters

Name	In	Description
id	Path	Required. An integer indicating the Keyfactor Command reference ID for the SSH key rotation alert.  Use the GET /Alerts/KeyRotation method (see GET Alerts Key Rotation on page 131) to retrieve a list of all the SSH key rotation alerts to determine the alert ID.

Table 85: GET Alerts Key Rotation {id} Response Data

Name	Description		
Id	An integer indicating the Keyfactor Command reference ID of the SSH key rotation alert.		
DisplayName	A string indicating the display name for the SSH key rotation alert. This name appears in the SSH key rotation alerts grid in the Management Portal.		
Subject	A string indicating the subject for the email message that will be delivered when the alert is triggered.		
	Tip: Substitutable special text may be used in the subject line. Substitutable special text uses a variable in the alert definition that is replaced by data from the key record at processing time. For example, you can enter {comment} in the alert definition and each alert generated at processing time will contain the specific key comment of the given SSH key instead of the variable {comment}.		
Message	A string indicating the email message that will be delivered when the alert is triggered. The email message is made up of regular text and substitutable special text. If desired, you can format the message body using HTML.  For example:  "Hello,\n\nYou requested an SSH key pair almost a year ago with the following information:\n\n\n "Hello,\n\nYou requested an SSH key pair almost a year ago with the following information:\n\n\n \to\to \to \to\t		
RotationWarningDays	An integer indicating the number of days prior to the end of an SSH key's lifetime the alert should be triggered.		

Name	Description			
RegisteredEventHandler	An object containing the event handler configuration for the alert, if applicable. Possible values are:			
	Value	Description		
	Id	An integer indicating the Keyfactor Command reference ID for the event handler.		
		ID Event Handler Type		
		10 SSHKeyRotationLogger		
		11 SSHKeyRotationPowershell		
	DisplayName	A string containing the name of the event handler.		
	UseHandler	A Boolean indicating whether event handler use is enabled for the alert (true) or not (false).		
	For more information a	bout event handlers, see <i>Using Event Handlers</i> in the <i>Keyfactor</i> uide.		
EventHandlerParameters	An array containing the parameters configured for use by the event handler. The type of data will vary depending on the configured handler. Possible values are:			
	Value	Description		
	Id	An integer indicating the Keyfactor Command reference ID of the configured parameter.		
	Key	A string indicating the reference name of the configured parameter.		
	DefaultValue	A string indicating the value for the parameter. This value is related to the type of parameter (see <i>ParameterType</i> ).		
	ParameterType	<ul> <li>A string containing the parameter type. Supported types are:</li> <li>LogTarget         This type is used for the event logging handler and is used to reference the fully qualified domain name of the target machine to which event should be logged.     </li> <li>Script         This type is used for the PowerShell handler and is used     </li> </ul>		

Name	Description	
	Value	Description
		to reference the PowerShell script that should be run when the alert is triggered. It is referenced using the filename and optional relative path to the PowerShell script, located in the extensions directory on the Keyfactor Command server.  • Token  This type is used for the PowerShell handler and is used to reference a substitutable special text value that should be passed to the PowerShell script. See Table:  Substitutable Special Text for Key Rotation Alerts in the Keyfactor Command Reference Guide for a complete list of available substitutable special text strings.  • Value  This type is used for the PowerShell handler and is used to reference a static text string that should be passed to the PowerShell script.

## **GET Alerts Key Rotation Schedule**

The GET /Alerts/KeyRotation/Schedule method is used to retrieve the schedule for delivery of SSH key rotation alerts configured in Keyfactor Command. This method returns HTTP 200 OK on a success with details of the schedule for SSH key rotation alerts. This method has no input parameters other than the standard headers (see Web API Common Features on page 3).



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: WorkflowManagement: *Read* 

Table 86: GET Alerts Key Rotation Schedule Response Data

Name	Description		
Schedule	An array indic	An array indicating the schedule for delivery of the SSH key rotation alerts. Possible values are:	
	Name	Description	
	Interval		icates a job scheduled to run every x minutes with the specified val that is selected in the UI will be converted to minutes when se.
		Name D	escription
			n integer indicating the number of minutes between each terval.
		For example, every h	our:
		"Interval": {     "Minutes": 6 }	0
	Daily	A dictionary that indiparameter:	icates a job scheduled to run every day at the same time with the
		Name De	escription
		giv	e date and time to next run the job. The date and time should be en using the ISO 8601 UTC time format YYYY-MM-DDTHH:m-ss.000Z (e.g. 2021-05-19T16:23:01Z).
		For example, daily at	11:30 pm:
		"Daily": { "Time": "202 }	2-02-25T23:30:00Z"

# **PUT Alerts Key Rotation Schedule**

The PUT /Alerts/KeyRotation/Schedule method is used to create or update the schedule for delivery of SSH key rotation alerts configured in Keyfactor Command. This method returns HTTP 200 OK on a success with details of the schedule for SSH key rotation alerts.



 $\textbf{Tip: } The following permissions (see \underline{Security\ Overview}) are required to use this feature: \\ WorkflowManagement: \underline{\textit{Modify}}$ 

Table 87: PUT Alerts Key Rotation Schedule Input Parameters

Name	In	Description		
Schedule	Body	An array indic	cating the schedule	for delivery of the SSH key rotation alerts. Possible values are:
		Name	Description	
		Interval	specified parame	e indicates a job scheduled to run every x minutes with the eter. Any interval that is selected in the UI will be converted to cored in the database.
			Name	Description
			Minutes	An integer indicating the number of minutes between each interval.
			For example, eve	ery hour:
			"Interval":     "Minutes' }	·
		Daily	A dictionary that with the parame	indicates a job scheduled to run every day at the same time tter:
			Name	Description
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
			For example, dai	ily at 11:30 pm:
			"Daily": {     "Time": '	"2022-02-25T23:30:00Z"

Table 88: PUT Alerts Key Rotation Schedule Response Data

Name	Description		
Schedule	An array indic	An array indicating the schedule for delivery of the SSH key rotation alerts. Possible values are:	
	Name	Description	
	Interval		icates a job scheduled to run every x minutes with the specified val that is selected in the UI will be converted to minutes when se.
		Name D	escription
			n integer indicating the number of minutes between each terval.
		For example, every h	our:
		"Interval": {     "Minutes": 6 }	0
	Daily	A dictionary that indiparameter:	icates a job scheduled to run every day at the same time with the
		Name De	escription
		giv	e date and time to next run the job. The date and time should be en using the ISO 8601 UTC time format YYYY-MM-DDTHH:m-ss.000Z (e.g. 2021-05-19T16:23:01Z).
		For example, daily at	11:30 pm:
		"Daily": { "Time": "202 }	2-02-25T23:30:00Z"

## **GET Alerts Key Rotation**

The GET /Alerts/KeyRotation method is used to retrieve details of all SSH key rotation alerts configured in Keyfactor Command. Results can be limited to selected alerts using filtering, and URL parameters can be used to specify paging and sorting. This method returns HTTP 200 OK on a success with details about the specified SSH key rotation alerts.



 $\textbf{Tip: } The following permissions (see \underline{Security\ Overview}) are required to use this feature: \\ WorkflowManagement: \\ \textit{Read}$ 

Table 89: GET Alerts Key Rotation Input Parameters

Name	In	Description
queryString	Query	A string containing a query to limit the results (e.g. field1 -eq value1 AND field2 -gt value2). The default is to return all records. Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns for the same feature. For querying guidelines, refer to the Keyfactor Command Reference Guide: Certificate Search Page. The query fields supported for this endpoint are:  • Days  • DisplayName  • Message  • RegisteredEventHandlerId  • ScheduledTaskId  • Subject  • UseHandler
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>DisplayName</i> .
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.

Table 90: GET Alerts Key Rotation Response Data

Name	Description
Id	An integer indicating the Keyfactor Command reference ID of the SSH key rotation alert.
DisplayName	A string indicating the display name for the SSH key rotation alert. This name appears in the SSH key rotation alerts grid in the Management Portal.
Subject	A string indicating the subject for the email message that will be delivered when the alert is triggered.
	Tip: Substitutable special text may be used in the subject line. Substitutable special text uses a variable in the alert definition that is replaced by data from the key record at processing time. For example, you can enter {comment} in the alert definition and each alert generated at processing time will contain the specific key comment of the given SSH key instead of the variable {comment}.
Message	A string indicating the email message that will be delivered when the alert is triggered. The email message is made up of regular text and substitutable special text. If desired, you can format the message body using HTML.  For example:  "Hello,\n\nYou requested an SSH key pair almost a year ago with the following information:\n\n\n "Hello,\n\nYou requested an SSH key pair almost a year ago with the following information:\n\n\n \to <th< td=""></th<>
RotationWarningDays	An integer indicating the number of days prior to the end of an SSH key's lifetime the alert should be triggered.

Name	Description			
RegisteredEventHandler	An object containing the event handler configuration for the alert, if applicable. Possible values are:			
	Value	Description		
	Id	An integer indicating the Keyfactor Command reference ID for the event handler.		
		ID Event Handler Type		
		10 SSHKeyRotationLogger		
		11 SSHKeyRotationPowershell		
	DisplayName	A string containing the name of the event handler.		
	UseHandler	A Boolean indicating whether event handler use is enabled for the alert (true) or not (false).		
	For more information about event handlers, see <i>Using Event Handlers</i> in the <i>Keyfactor Command Reference Guide</i> .			
EventHandlerParameters	An array containing the parameters configured for use by the event handler. The type of data will vary depending on the configured handler. Possible values are:			
	Value	Description		
	Id	An integer indicating the Keyfactor Command reference ID of the configured parameter.		
	Key	A string indicating the reference name of the configured parameter.		
	DefaultValue	A string indicating the value for the parameter. This value is related to the type of parameter (see <i>ParameterType</i> ).		
	ParameterType	<ul> <li>A string containing the parameter type. Supported types are:</li> <li>LogTarget         This type is used for the event logging handler and is used to reference the fully qualified domain name of the target machine to which event should be logged.     </li> <li>Script         This type is used for the PowerShell handler and is used     </li> </ul>		

Name	Description		
	Value	Description	
		to reference the PowerShell script that should be run when the alert is triggered. It is referenced using the filename and optional relative path to the PowerShell script, located in the extensions directory on the Keyfactor Command server.  • Token  This type is used for the PowerShell handler and is used to reference a substitutable special text value that should be passed to the PowerShell script. See Table:  Substitutable Special Text for Key Rotation Alerts in the Keyfactor Command Reference Guide for a complete list of available substitutable special text strings.  • Value  This type is used for the PowerShell handler and is used to reference a static text string that should be passed to the PowerShell script.	

## **POST Alerts Key Rotation**

The POST /Alerts/KeyRotation method is used to create a new SSH key rotation alert. This method returns HTTP 200 OK on a success with details about the SSH key rotation alert.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: WorkflowManagement: *Modify* 

Table 91: POST Alerts Key Rotation Input Parameters

Name	In	Description	
DisplayName	Body	<b>Required</b> . A string indicating the display name for the SSH key rotation alert. This name appears in the SSH key rotation alerts grid in the Management Portal.	
Subject	Body	<b>Required</b> . A string indicating the subject for the email message that will be delivered when the alert is triggered.	
		Tip: Substitutable special text may be used in the subject line. Substitutable special text uses a variable in the alert definition that is replaced by data from the key record at processing time. For example, you can enter {comment} in the alert definition and each alert generated at processing time will contain the specific key comment of the given SSH key instead of the variable {comment}.	
Message	Body	Required. A string indicating the email message that will be delivered when the alert is triggered. The email message is made up of regular text and substitutable special text. If desired, you can format the message body using HTML.  For example:  "Hello,\n\nYou requested an SSH key pair almost a year ago with the following information:\n\n <t- able="">\n ation:\n\n<t- able="">\n ith&gt;Field th&gt;Value th&gt;tr&gt;\n td&gt;Value th&gt;td&gt;\td&gt; td&gt; td&gt; td&gt; td&gt; td&gt; td&gt; td&gt; td&gt; td&gt;</t-></t->	
RotationWarningDays	Body	An integer indicating the number of days prior to the end of an SSH key's lifetime the alert should be triggered.	

Name	In	Description		
RegisteredEventHandle-	Body	An object containing the event handler configuration for the alert, if applicable.  Possible values are:		
		Value	Description	
		Id	An integer indicating the Keyfactor Command reference ID for the event handler.	
			ID Event Handler Type	
			10 SSHKeyRotationLogger	
			11 SSHKeyRotationPowershell	
		UseHandler	A Boolean indicating whether event handler use is enabled for the alert (true) or not (false).	
		For more information al Keyfactor Command Rej	bout event handlers, see <i>Using Event Handlers</i> in the ference Guide.	
EventHand- lerParameters	Body	An array containing the parameters configured for use by the event handler. The type of data will vary depending on the configured handler. Possible values are:		
		Value	Description	
		Id	An integer indicating the Keyfactor Command reference ID of the configured parameter.	
		Key	A string indicating the reference name of the configured parameter.	
		DefaultValue	A string indicating the value for the parameter. This value is related to the type of parameter (see <i>ParameterType</i> ).	
		ParameterType	A string containing the parameter type. Supported types are:  • LogTarget  This type is used for the event logging handler and is used to reference the fully qualified domain name of the target machine to which event should be logged.  • Script	

Name	In	Description	
		Value	Description
			This type is used for the PowerShell handler and is used to reference the PowerShell script that should be run when the alert is triggered. It is referenced using the filename and optional relative path to the PowerShell script, located in the extensions directory on the Keyfactor Command server.  • Token  This type is used for the PowerShell handler and is used to reference a substitutable special text value that should be passed to the PowerShell script. See Table: Substitutable Special Text for Key Rotation Alerts in the Keyfactor Command Reference Guide for a complete list of available substitutable special text strings.  • Value  This type is used for the PowerShell handler and is used to reference a static text string that should be passed to the PowerShell script.
		"ParameterT },  {     "Id": 29,     "Key": "com     "DefaultVal     "ParameterT },  {     "Id": 30,     "Key": "Tex     "DefaultVal	meters": [  r",  ue": "username",  ype": "Token"  ment",  ue": "comment",  ype": "Token"  t",  ue": "Key Rotation Alert: 3 Days",  ype": "Value"

Name	In	Description	
		"DefaultValue": "MyScript.ps1",     "ParameterType": "Script" }	

Table 92: POST Alerts Key Rotation Response Data

Name	Description
Id	An integer indicating the Keyfactor Command reference ID of the SSH key rotation alert.
DisplayName	A string indicating the display name for the SSH key rotation alert. This name appears in the SSH key rotation alerts grid in the Management Portal.
Subject	A string indicating the subject for the email message that will be delivered when the alert is triggered.
	Tip: Substitutable special text may be used in the subject line. Substitutable special text uses a variable in the alert definition that is replaced by data from the key record at processing time. For example, you can enter {comment} in the alert definition and each alert generated at processing time will contain the specific key comment of the given SSH key instead of the variable {comment}.
Message	A string indicating the email message that will be delivered when the alert is triggered. The email message is made up of regular text and substitutable special text. If desired, you can format the message body using HTML.  For example:  "Hello,\n\nYou requested an SSH key pair almost a year ago with the following information:\n\n\n"Hello,\n\nYou requested an SSH key pair almost a year ago with the following information:\n\n\n\toFieldValue\to\toUsername\toUsername\to\
RotationWarningDays	An integer indicating the number of days prior to the end of an SSH key's lifetime the alert should be triggered.

Name	Description			
RegisteredEventHandler	An object containing the event handler configuration for the alert, if applicable. Possible values are:			
	Value	Description		
	Id	An integer indicating the Keyfactor Command reference ID for the event handler.		
		ID Event Handler Type		
		10 SSHKeyRotationLogger		
		11 SSHKeyRotationPowershell		
	DisplayName	A string containing the name of the event handler.		
	UseHandler	A Boolean indicating whether event handler use is enabled for the alert (true) or not (false).		
	For more information about event handlers, see <i>Using Event Handlers</i> in the <i>Keyfactor Command Reference Guide</i> .			
EventHandlerParameters	An array containing the parameters configured for use by the event handler. The type of data will vary depending on the configured handler. Possible values are:			
	Value	ue Description		
	Id	An integer indicating the Keyfactor Command reference ID of the configured parameter.		
	Кеу	A string indicating the reference name of the configured parameter.		
	DefaultValue	A string indicating the value for the parameter. This value is related to the type of parameter (see <i>ParameterType</i> ).		
	ParameterType	A string containing the parameter type. Supported types are:              LogTarget             This type is used for the event logging handler and is used to reference the fully qualified domain name of the target machine to which event should be logged.              Script             This type is used for the PowerShell handler and is used		

Name	Description		
	Value	Description	
		to reference the PowerShell script that should be run when the alert is triggered. It is referenced using the filename and optional relative path to the PowerShell script, located in the extensions directory on the Keyfactor Command server.  • Token  This type is used for the PowerShell handler and is used to reference a substitutable special text value that should be passed to the PowerShell script. See Table:  Substitutable Special Text for Key Rotation Alerts in the Keyfactor Command Reference Guide for a complete list of available substitutable special text strings.  • Value  This type is used for the PowerShell handler and is used to reference a static text string that should be passed to the PowerShell script.	

### **PUT Alerts Key Rotation**

The PUT /Alerts/KeyRotation method is used to update a SSH key rotation alert. This method returns HTTP 200 OK on a success with details about the SSH key rotation alert.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: WorkflowManagement: Modify



Warning: Any previously populated fields that are not submitted with their full existing data using this method will be cleared of their existing data. When using this method, you should first do a GET to retrieve all the values for the record you want to update, enter corrected data into the field(s) you want to update, and then submit all the fields using PUT, including the fields that contain values but which you are not changing.

Table 93: PUT Alerts Key Rotation Input Parameters

Name	In	Description	
id	Path	An integer indicating the Keyfactor Command reference ID of the SSH key rotation alert.	
DisplayName	Body	<b>Required</b> . A string indicating the display name for the SSH key rotation alert. This name appears in the SSH key rotation alerts grid in the Management Portal.	
Subject	Body	Required. A string indicating the subject for the email message that will be delivered when the alert is triggered.  Tip: Substitutable special text may be used in the subject line. Substitutable special text uses a variable in the alert definition that is replaced by data from the key record at processing time. For example, you can enter {comment} in the alert definition and each alert generated at processing time will contain the specific key comment of the given SSH key instead of the variable {comment}.	
Message	Body	Required. A string indicating the email message that will be delivered when the alert is triggered. The email message is made up of regular text and substitutable special text. If desired, you can format the message body using HTML.  For example:  "Hello,\n\nYou requested an SSH key pair almost a year ago with the following information:\n\n <t- able="">\n able&gt;\n td&gt;fingerprint\ //r&gt;\n td&gt;fingerprint\ //r&gt;\n td&gt;cd&gt;Fingerprint\ //r&gt;\n td&gt;Comment\ //to\ \n td&gt;cd&gt;Key Length //td&gt; //to\ \n td&gt;keylength\ //td&gt; //tr&gt;\n td&gt;Key Type //td&gt; //tr&gt;\n td&gt;key Length<!--/--> //to&gt;\n\nCorporate policy requires key rotation every year. Please visit the <a href='\"https://[your_server_name]/Key-factorPortal/SshMyKey\"'>My SSH Key Portal</a> for user keys or the <a href='\"https://[your_server_name]/Key-factorPortal/SshServiceAccountKeys\"'>Service Account Key Portal</a> for service account keys and request a new key pair.\n\nThanks!"  See Table: Substitutable Special Text for Key Rotation Alerts in the Keyfactor Command Reference Guide for a complete list of available substitutable special text strings.</t->	
RotationWarningDays	Body	An integer indicating the number of days prior to the end of an SSH key's lifetime the alert should be triggered.	

Name	In	Description		
RegisteredEventHandle- B	Body	An object containing the event handler configuration for the alert, if applicable.  Possible values are:		
		Value	Description	
		Id	An integer indicating the Keyfactor Command reference ID for the event handler.	
			ID Event Handler Type	
			10 SSHKeyRotationLogger	
			11 SSHKeyRotationPowershell	
		DisplayName	A string containing the name of the event handler.	
		UseHandler	A Boolean indicating whether event handler use is enabled for the alert (true) or not (false).	
		For more information al Keyfactor Command Rej	bout event handlers, see <i>Using Event Handlers</i> in the ference Guide.	
EventHand- lerParameters	Body	An array containing the parameters configured for use by the event handler. The type of data will vary depending on the configured handler. Possible values are:		
		Value	Description	
		Id	An integer indicating the Keyfactor Command reference ID of the configured parameter.	
		Key	A string indicating the reference name of the configured parameter.	
		DefaultValue	A string indicating the value for the parameter. This value is related to the type of parameter (see <i>ParameterType</i> ).	
		ParameterType	A string containing the parameter type. Supported types are:  • LogTarget  This type is used for the event logging handler and is used to reference the fully qualified domain name of the target machine to which	

Name	In	Description	
		Value	Description
			<ul> <li>event should be logged.</li> <li>Script  This type is used for the PowerShell handler and is used to reference the PowerShell script that should be run when the alert is triggered. It is referenced using the filename and optional relative path to the PowerShell script, located in the extensions directory on the Keyfactor Command server.</li> <li>Token  This type is used for the PowerShell handler and is used to reference a substitutable special text value that should be passed to the PowerShell script. See Table: Substitutable Special Text for Key Rotation Alerts in the Keyfactor Command Reference Guide for a complete list of available substitutable special text strings.</li> <li>Value  This type is used for the PowerShell handler and is used to reference a static text string that should be passed to the PowerShell script.</li> </ul>
		For example, for a Powe	erShell handler:
		"ParameterTy },  {  "Id": 29,  "Key": "comm  "DefaultValu  "ParameterTy },  {  "Id": 30,  "Key": "Text  "DefaultValu  "DefaultValu  "DefaultValu	r", ue": "username", ype": "Token"  ment", ue": "comment", ype": "Token"

Name	In	Description
		"Id": 32,  "Key": "ScriptName",  "DefaultValue": "MyScript.ps1",  "ParameterType": "Script"  } ]

Table 94: PUT Alerts Key Rotation Response Data

Name	Description
Id	An integer indicating the Keyfactor Command reference ID of the SSH key rotation alert.
DisplayName	A string indicating the display name for the SSH key rotation alert. This name appears in the SSH key rotation alerts grid in the Management Portal.
Subject	A string indicating the subject for the email message that will be delivered when the alert is triggered.
	Tip: Substitutable special text may be used in the subject line. Substitutable special text uses a variable in the alert definition that is replaced by data from the key record at processing time. For example, you can enter {comment} in the alert definition and each alert generated at processing time will contain the specific key comment of the given SSH key instead of the variable {comment}.
Message	A string indicating the email message that will be delivered when the alert is triggered. The email message is made up of regular text and substitutable special text. If desired, you can format the message body using HTML.  For example:  "Hello,\n\nYou requested an SSH key pair almost a year ago with the following information:\n\n\n Field Value \text{tr>\n Username} \td>\text{tr>\n Fingerprint \text{tr>\n Key length \text{tr>\n Key length \text{tr>\n Key Type \text{keytype} \to-tr>\n NnCorporate policy requires key rotation every year. Please visit the <a href='\"https://[your_server_name]/KeyfactorPortal/SshMyKey\"'>My SSH Key Portal</a> for user keys or the <a href='\"https://[your_server_name]/KeyfactorPortal&lt;/a'> for service account keys and request a new key pair.\n\nThanks!"</a>
	See Table: Substitutable Special Text for Key Rotation Alerts in the Keyfactor Command Reference Guide for a complete list of available substitutable special text strings.
RotationWarningDays	An integer indicating the number of days prior to the end of an SSH key's lifetime the alert should be triggered.

Name	Description			
RegisteredEventHandler	An object containing the event handler configuration for the alert, if applicable. Possible values are:			
	Value	Description		
	Id	An integer ind	icating the Keyfactor Command reference nt handler.	
		ID	Event Handler Type	
		10	SSHKeyRotationLogger	
		11	SSHKeyRotationPowershell	
	DisplayName	A string conta	ining the name of the event handler.	
	UseHandler		icating whether event handler use is enabled rue) or not (false).	
	For more information al		see Using Event Handlers in the Keyfactor	
EventHandlerParameters			ed for use by the event handler. The type of andler. Possible values are:	
	Value	Description		
	Id	An integer indicatir configured parame	ng the Keyfactor Command reference ID of the ter.	
	Key	A string indicating t meter.	the reference name of the configured para-	
	DefaultValue		the value for the parameter. This value is of parameter (see <i>ParameterType</i> ).	
	ParameterType	<ul> <li>LogTarget         This type is u         used to refer         target machine     </li> <li>Script</li> </ul>	the parameter type. Supported types are:  sed for the event logging handler and is ence the fully qualified domain name of the ne to which event should be logged.  sed for the PowerShell handler and is used	

Name	Description		
	Value	Description	
		to reference the PowerShell script that should be run when the alert is triggered. It is referenced using the filename and optional relative path to the PowerShell script, located in the extensions directory on the Keyfactor Command server.  • Token  This type is used for the PowerShell handler and is used to reference a substitutable special text value that should be passed to the PowerShell script. See Table:  Substitutable Special Text for Key Rotation Alerts in the Keyfactor Command Reference Guide for a complete list of available substitutable special text strings.  • Value  This type is used for the PowerShell handler and is used to reference a static text string that should be passed to the PowerShell script.	

#### **POST Alerts Key Rotation Test**

The POST /Alerts/KeyRotation/Test method is used to test a specific SSH key rotation alert. This method returns HTTP 200 OK on a success with details about the SSH key rotation alert or a response of "NoActionTaken" if no keys match the test criteria entered.



**Tip:** Alerts are generated when an SSH key is approaching or has reached its stale date as defined by the timeframe configured in the alert and the SSH key lifetime (the *Key Lifetime (days)* application setting). By default, a maximum of 100 alerts will be generated during a test. The maximum value is configurable with the *Key Rotation Alert Test Result Limit* setting in Keyfactor Command application settings (see <u>Application Settings: Console Tab</u> in the *Keyfactor Command Reference Guide*). If more than 100 alerts are generated, no email messages will be sent and you'll have the opportunity to view the first 100 alerts generated.

If you're using an event handler, the event handler is run and the handler actions taken (PowerShell script run, event log message written) when the test is run. This is true regardless of the setting of the *SendAlerts* flag.



**Tip:** The following permissions (see Security Overview) are required to use this feature:

WorkflowManagement: *Read* WorkflowManagement: *Test* 

Table 95: POST Alerts Key Rotation Test Input Parameters

Name	In	Description																											
keyRotationAlertTestRequest	Body	<b>Required</b> . An array containing information for the alert test. Alert test detail values are:																											
		Parameter	Description																										
		AlertId	Required. An integer of the reference ID of the SSH key rotation alert to test.  Use the GET /Alerts/KeyRotation method (see GET Alerts Key Rotation on page 131) to retrieve a list of all your key rotation alerts to determine the alert Id.																										
		EvaluationDate	Required. A string indicating the start date/time for the test, in UTC. You can use the date range to simulate running the alerts a month from now instead of today, for example, or put in a broad date range to be sure you pick up some expiring keys for testing purposes.																										
		Previous Evaluation Date	<b>Required</b> . A string indicating the end date/time for the test, in UTC.																										
		SendAlerts	A Boolean indicating whether to send alert emails with the test (true) or not (false). The default is false.																										
		For example:																											
																												{     "EvaluationDate": "20     "PreviousEvaluationDa 31T20:51:33.528Z",     "SendAlerts": true }	22-08-31T20:51:33.528Z", te": "2022-08-

Table 96: POST Alerts Key Rotation Test Response Data

Parameter	Description		
KeyRotationAlerts	An object containing alert details resulting from the test. Expiration alert details are:		
	Name	Description	
	Subject	A string indicating the subject for the email message, including any replaced substitutable special text.	
	Message	A string indicating the email message, including any replaced substitutable special text	
		See Table: Substitutable Special Text for Key Rotation Alerts in the Keyfactor Command Reference Guide for a complete list of available substitutable special text strings.	
	Recipient	A string indicating the recipient for the alert.	
AlertBuildResult	A string indicating	g the outcome of the test (e.g. Success).	

#### **POST Alerts Key Rotation Test All**

The POST /Alerts/KeyRotation/TestAll method is used to test all SSH key rotation alerts. This method returns HTTP 200 OK on a success with details about the SSH key rotation alert or a response of "NoActionTaken" if no keys match the test criteria entered.



**Tip:** Alerts are generated when an SSH key is approaching or has reached its stale date as defined by the timeframe configured in the alert and the SSH key lifetime (the *Key Lifetime (days)* application setting). By default, a maximum of 100 alerts will be generated during a test. The maximum value is configurable with the *Key Rotation Alert Test Result Limit* setting in Keyfactor Command application settings (see <u>Application Settings: Console Tab</u> in the *Keyfactor Command Reference Guide*). If more than 100 alerts are generated, no email messages will be sent and you'll have the opportunity to view the first 100 alerts generated.

If you're using an event handler, the event handler is run and the handler actions taken (PowerShell script run, event log message written) when the test is run. This is true regardless of the setting of the *SendAlerts* flag.



**Tip:** The following permissions (see Security Overview) are required to use this feature:

WorkflowManagement: Read WorkflowManagement: Test

Table 97: POST Alerts Key Rotation Test All Input Parameters

Name	In	Description											
keyRotationAlertTestRequest	Body	<b>Required</b> . An array containing information for the alert test. Alert test detail values are:											
		Parameter	Description										
		EvaluationDate	Required. A string indicating the start date/time for the test, in UTC.  You can use the date range to simulate running the alerts a month from now instead of today, for example, or put in a broad date range to be sure you pick up some expiring keys for testing purposes.										
				PreviousEvaluationDate	<b>Required</b> . A string indicating the end date/time for the test, in UTC.								
					SendAlerts	A Boolean indicating whether to send alert emails with the test (true) or not (false). The default is false.							
												For example:	
													{     "EvaluationDate": "20.     "PreviousEvaluationDar 31T20:51:33.528Z",     "SendAlerts": true }

Table 98: POST Alerts Key Rotation Test All Response Data

Parameter	Description		
KeyRotationAlerts	An object containing alert details resulting from the test. Expiration alert details are:		
	Name	Description	
	Subject	A string indicating the subject for the email message, including any replaced substitutable special text.	
	Message	A string indicating the email message, including any replaced substitutable special text	
		See Table: Substitutable Special Text for Key Rotation Alerts in the Keyfactor Command Reference Guide for a complete list of available substitutable special text strings.	
	Recipient	A string indicating the recipient for the alert.	
AlertBuildResult	A string indicating	g the outcome of the test (e.g. Success).	

### 2.2.4.5 Alerts Pending

The Alerts Pending component of the Keyfactor API includes methods necessary to create, update, retrieve, schedule, and delete alerts for certificate requests that require approval based on policy on the CA.



**Important:** Pending alerts are **not** used to provide email alerts for certificate requests that require approval based on policies configured in Keyfactor Command workflows. These alerts are configured as steps within the workflow (see Workflow Definitions on page 1234).

For more information about the difference between alerting for certificate requests that require manager approval at the CA level and alerting for certificate requests that require manager approval at the Keyfactor Command workflow level, see <a href="Pending Certificate Request Alerts">Pending Certificate Request Alerts</a> in the Keyfactor Command Reference Guide.

Table 99: Alerts Pending

Endpoint	Method	Description	Link
/Alerts/Pending/{id}	DELETE	Deletes a pending certificate request alert for the specified ID.	DELETE Alerts Pending  ID on the next page
/Alerts/Pending/{id}	GET	Retrieves details for a pending certificate request alert for the specified ID.	GET Alerts Pending ID on the next page
/Alerts/Pending	PUT	Updates a pending certificate request alert for a specified ID.	PUT Alerts Pending on page 175

Endpoint	Method	Description	Link
/Alerts/Pending/Schedule	GET	Retrieves details of the schedule for delivery of pending certificate request alerts.	GET Alerts Pending Schedule on page 159
/Alerts/Pending/Schedule	PUT	Updates the schedule for delivery of pending certificate request alerts.	PUT Alerts Pending Schedule on page 160
/Alerts/Pending	GET	Retrieves details for all configured pending certificate request alerts.	GET Alerts Pending on page 162
/Alerts/Pending	POST	Creates a new pending certificate request alert.	POST Alerts Pending on page 167
/Alerts/Pending/Test	POST	Tests all alerts	POST Alerts Pending TestAll on page 186
/Alerts/Pending/Test/{id}	POST	Tests specific alerts	POST Alerts Pending Test on page 183

## **DELETE Alerts Pending ID**

The DELTE /Alerts/Pending/{id} method is used to delete the pending certificate request alert with the specified ID. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: WorkflowManagement: *Modify* 

Table 100: DELETE Alerts Pending {id} Input Parameters

Name	In	Description
id	Path	Required. An integer indicating the Keyfactor Command reference ID for the pending certificate request alert to be deleted.  Use the GET /Alerts/Pending method (see GET Alerts Pending on page 162) to retrieve a list of all the pending request alerts to determine the alert ID.

## **GET Alerts Pending ID**

The GET /Alerts/Pending/{id} method is used to retrieve details for the pending certificate request alerts with the specified ID. This method returns HTTP 200 OK on a success with details about the specified pending certificate request alert.



Table 101: GET Alerts Pending {id} Input Parameters

Name	In	Description
id	Path	Required. An integer indicating the Keyfactor Command reference ID for the pending certificate request alert.  Use the GET /Alerts/Pending method (see GET Alerts Pending on page 162) to retrieve a list of all the pending request alerts to determine the alert ID.

Table 102: GET Alerts Pending {id} Response Data

Name	Description		
Id	An integer indicating the Keyfactor Command reference ID of the pending request alert.  Run GET /Alerts/Pending to find the pending request alert ID.		
DisplayName	A string indicating the display name for the pending request alert. This name appears in the pending request alerts grid in the Management Portal.		
Subject	A string indicating the subject for the email message that will be delivered when the alert is triggered.		
	Tip: Substitutable special text may be used in the subject line. Substitutable special text uses a variable in the alert definition that is replaced by data from the certificate request or certificate metadata at processing time. For example, you can enter {rcn} in the alert definition and each alert generated at processing time will contain the specific requested common name of the given certificate request instead of the variable {rcn}.		
Message	A string indicating the email message that will be delivered when the alert is triggered. The email message is made up of regular text and substitutable special text. If desired, you can format the message body using HTML.  For example:  "Hello,\n\nA certificate using the {template} template was requested by {requester:displayname} from {careqid} on {subdate}. The certificate details include:\n\n <t-able>\n \text{cro}Certificate Details \text{h&gt;Metadata \text{h&gt; \text{h&gt;Cro}} \text{cd&gt;App Owner First Name: {metadata:Ap-pOwnerFirstName} \text{dd&gt; \text{ho} \text{cd}Email Address: {metadata:Ap-pOwnerLastName} \text{dd&gt; \text{ho} \text{cd}SANs: {san} \text{dd&gt;<app address}<="" email="" owner="" th=""> \text{dd&gt;<app address}<="" email="" owner="" tr=""> \text{dd&gt;<app address}<="" email="" owner="" td=""> \text{dd}&lt;\text{Nn}&lt;\t</app></app></app></app></app></app></app></app></app></app></app></app></app></app></app></app></app></app></app></t-able>		
Recipients	An array of strings containing the recipients for the alert. Each alert can have multiple recipients. You can use specific email addresses and/or use substitutable special text to replace an email address variable with actual email addresses at processing time. Available email substitutable special text strings include:  • {requester:mail}		

Name	Description			
	The certificate requester, based on a lookup in Active Directory of the email address associated with the requester on the certificate.  • Your custom email-based metadata field, which would be specified similarly to {metadata:AppOwnerEmailAddress}.			
Template	An object containing information about the certificate template for which the pending request alerts will be generated. A separate alert should be configured for each template. An alert may be configured with no template, if desired. Alerts configured in this way generate alerts for all pending certificate requests. Possible values are:			
	Value	Description		
	Id	An integer indicating the Keyfactor Command reference ID for the template, or <i>null</i> for all templates.		
	DisplayName	A string containing the name of the template. For a template created using a Microsoft management tool, this will be the Microsoft template display name.		
	ForestRoot	A string indicating the forest root of the template.		
		Note: This field is retained for legacy purposes and will be replaced by ConfigurationTenant field.		
	ConfigurationTenant	A string indicating the configuration tenant of the template.		

Name	Description			
RegisteredEventHandler	An object containing the event handler configuration for the alert, if applicable. Possible values are:			
	Value	Description		
		An integer indicating the Keyfactor Command reference ID for the event handler.		
		ID	Event Handler Type	
		8	PendingLogger	
		9	PendingPowershell	
	DisplayName	A string containing the name of the event handler.		
	UseHandler	A Boolean indicating whether event handler use is enabled for the alert (true) or not (false).		
	For more information about event handlers, see <i>Using Event Handlers</i> in the <i>Keyfactor Command Reference Guide</i> .			
EventHandlerParameters	An array containing the parameters configured for use by the event handler. The type of data will vary depending on the configured handler. Possible values are:			
	Value	Description		
	Id	An integer indicating the Keyfactor Command reference ID of the configured parameter.		
	Key	A string indicating the reference name of the configured parameter.		
	DefaultValue	A string indicating the value for the parameter. This value is related to the type of parameter (see <i>ParameterType</i> ).		
	ParameterType	<ul> <li>A string containing the parameter type. Supported types are:</li> <li>LogTarget         This type is used for the event logging handler and is used to reference the fully qualified domain name of the target machine to which event should be logged.     </li> <li>Script         This type is used for the PowerShell handler and is     </li> </ul>		

Name	Description				
	Value	Description			
		used to reference the PowerShell script that should be run when the alert is triggered. It is referenced using the filename and optional relative path to the Power-Shell script, located in the extensions directory on the Keyfactor Command server.  • Token  This type is used for the PowerShell handler and is used to reference a substitutable special text value that should be passed to the PowerShell script. See Table: Substitutable Special Text for Pending Request Alerts in the Keyfactor Command Reference Guide for a complete list of available substitutable special text strings.  • Value  This type is used for the PowerShell handler and is used to reference a static text string that should be passed to the PowerShell script.			

## **GET Alerts Pending Schedule**

The GET /Alerts/Pending/Schedule method is used to retrieve the schedule for delivery of pending certificate request alerts configured in Keyfactor Command. This method returns HTTP 200 OK on a success with details of the schedule for pending certificate request alerts. This method has no input parameters other than the standard headers (see Web API Common Features on page 3).



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: WorkflowManagement: *Read* 

Table 103: GET Alerts Pending Schedule Response Data

Name	Description					
Schedule	An array indica	ting the schedule f	ing the schedule for delivery of the pending request alerts. Possible values are:			
	Name	Description	Description			
	Interval		t indicates a job scheduled to run every x minutes with the specified interval that is selected in the UI will be converted to minutes when tabase.			
		Name	Description			
		Minutes	An integer indicating the number of minutes between each interval.			
		For example, ev	For example, every hour:			
			"Interval": {     "Minutes": 60 }			
	Daily	A dictionary that parameter:	t indicates a job scheduled to run every day at the same time with the			
		Name	Description			
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:m-m:ss.000Z (e.g. 2021-05-19T16:23:01Z).			
		For example, daily at 11:30 pm:				
		"Daily": {     "Time": }	"2022-02-25T23:30:00Z"			

## **PUT Alerts Pending Schedule**

The PUT /Alerts/Pending/Schedule method is used to create or update the schedule for delivery of pending certificate request alerts configured in Keyfactor Command. This method returns HTTP 200 OK on a success with details of the schedule for pending certificate request alerts. This method has no input parameters other than the standard headers (see Web API Common Features on page 3).



 $\textbf{Tip: } The following permissions (see \underline{Security\ Overview}) are required to use this feature: \\ WorkflowManagement: \underline{\textit{Modify}}$ 

Table 104: PUT Alerts Pending Schedule Input Parameters

Name	In	Description			
Schedule	Body	An array indi	icating the schedule for delivery of the pending request alerts. Possible values are:		
	Name Interval		Description		
			•	i job scheduled to run every x minutes with the terval that is selected in the UI will be converted to database.	
			Name Descrip	tion	
			Minutes An integral.	er indicating the number of minutes between each	
			For example, every hour:		
			"Interval": {     "Minutes": 60 }		
		Daily	A dictionary that indicates a with the parameter:	job scheduled to run every day at the same time	
			Name Descript	ion	
				should be	and time to next run the job. The date and time given using the ISO 8601 UTC time format YYYY-HH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
			For example, daily at 11:30	pm:	
			"Daily": {     "Time": "2022-02-2	25T23:30:00Z"	

Table 105: PUT Alerts Pending Schedule Response Data

Name	Description			
Schedule	An array indica	ing the schedule for delivery of the pending request alerts. Possible values are:		
	Name	Description		
	Interval	A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database.		
		Name Description		
		Minutes An integer indicating the numb interval.	per of minutes between each	
		For example, every hour:		
		"Interval": {     "Minutes": 60 }		
	Daily	A dictionary that indicates a job scheduled to run parameter:	every day at the same time with the	
		Name Description		
			the job. The date and time should be time format YYYY-MM-DDTHH:m-:23:01Z).	
		For example, daily at 11:30 pm:		
		"Daily": {     "Time": "2022-02-25T23:30:00Z" }		

## **GET Alerts Pending**

The GET /Alerts/Pending method is used to retrieve details of all pending certificate request alerts configured in Keyfactor Command. Results can be limited to selected alerts using filtering, and URL parameters can be used to specify paging and sorting. This method returns HTTP 200 OK on a success with details about the specified pending certificate request alerts.



Table 106: GET Alerts Pending Input Parameters

Name	In	Description
queryString	Query	A string containing a query to limit the results (e.g. field1 -eq value1 AND field2 -gt value2). The default is to return all records. Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns for the same feature. For querying guidelines, refer to the Keyfactor Command Reference Guide: Certificate Search Page. The query fields supported for this endpoint are:  • DisplayName  • Message  • RegisteredEventHandlerId  • ScheduledTaskId  • Subject  • Template_Id  • UseHandler
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>DisplayName</i> .
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.

Table 107: GET Alerts Pending Response Data

Name	Description		
Id	An integer indicating the Keyfactor Command reference ID of the pending request alert.  Run GET /Alerts/Pending to find the pending request alert ID.		
DisplayName	A string indicating the display name for the pending request alert. This name appears in the pending request alerts grid in the Management Portal.		
Subject	A string indicating the subject for the email message that will be delivered when the alert is triggered.		
	Tip: Substitutable special text may be used in the subject line. Substitutable special text uses a variable in the alert definition that is replaced by data from the certificate request or certificate metadata at processing time. For example, you can enter {rcn} in the alert definition and each alert generated at processing time will contain the specific requested common name of the given certificate request instead of the variable {rcn}.		
Message	A string indicating the email message that will be delivered when the alert is triggered. The email message is made up of regular text and substitutable special text. If desired, you can format the message body using HTML.  For example:  "Hello,\n\nA certificate using the {template} template was requested by {requester:displayname} from {careqid} on {subdate}. The certificate details include:\n\n <t-able>\n \table&gt;\n \table&gt;\n\table&gt;\n \table&gt;\n\table&gt;\n\table&gt;\table&gt;\n\table&gt;</t-able>		
Recipients	An array of strings containing the recipients for the alert. Each alert can have multiple recipients. You can use specific email addresses and/or use substitutable special text to replace an email address variable with actual email addresses at processing time. Available email substitutable special text strings include:  • {requester:mail}		

Name	Description			
	The certificate requester, based on a lookup in Active Directory of the email address associated with the requester on the certificate.  • Your custom email-based metadata field, which would be specified similarly to {metadata:AppOwnerEmailAddress}.			
Template	An object containing information about the certificate template for which the pending request alerts will be generated. A separate alert should be configured for each template. An alert may be configured with no template, if desired. Alerts configured in this way generate alerts for all pending certificate requests. Possible values are:			
	Value	Value Description		
	Id	An integer indicating the Keyfactor Command reference ID for the template, or <i>null</i> for all templates.		
	DisplayName	A string containing the name of the template. For a template created using a Microsoft management tool, this will be the Microsoft template display name.		
	ForestRoot	A string indicating the forest root of the template.		
		Note: This field is retained for legacy purposes and will be replaced by ConfigurationTenant field.		
	ConfigurationTenant	A string indicating the configuration tenant of the template.		

Name	Description			
RegisteredEventHandler	An object containing the event handler configuration for the alert, if applicable. Possible values are:			
	Value	Description		
	Id	An integer indicating the Keyfactor Command reference ID for the event handler.		
		ID	Event Handler Type	
		8	PendingLogger	
		9	PendingPowershell	
	DisplayName	A string containing	g the name of the event handler.	
	UseHandler A Boolean indicating whether event handler use is enable the alert (true) or not (false).			
	For more information about event handlers, see <i>Using Event Handlers</i> in the <i>Keyfactor Command Reference Guide</i> .			
EventHandlerParameters			gured for use by the event handler. The type of d handler. Possible values are:	
	Value	Value Description		
	Id	An integer indicating the Keyfactor Command reference ID of the configured parameter.		
	Key	A string indicating the reference name of the configured parameter.		
	DefaultValue	A string indicating the value for the parameter. This value is related to the type of parameter (see <i>ParameterType</i> ).		
	ParameterType	<ul> <li>LogTarget         This type         used to re         the target     </li> <li>Script</li> </ul>	ing the parameter type. Supported types are: is used for the event logging handler and is eference the fully qualified domain name of machine to which event should be logged. is used for the PowerShell handler and is	

Name	Description				
	Value	Description			
		used to reference the PowerShell script that should be run when the alert is triggered. It is referenced using the filename and optional relative path to the Power-Shell script, located in the extensions directory on the Keyfactor Command server.  • Token  This type is used for the PowerShell handler and is used to reference a substitutable special text value that should be passed to the PowerShell script. See Table: Substitutable Special Text for Pending Request Alerts in the Keyfactor Command Reference Guide for a complete list of available substitutable special text strings.  • Value  This type is used for the PowerShell handler and is used to reference a static text string that should be passed to the PowerShell script.			

# **POST Alerts Pending**

The POST /Alerts/Pending method is used to create a new pending certificate request alert. This method returns HTTP 200 OK on a success with details about the pending certificate request alert.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: WorkflowManagement: *Modify* 

Table 108: POST Alerts Pending Input Parameters

Name	In	Description
DisplayName	Body	<b>Required</b> . A string indicating the display name for the pending request alert. This name appears in the pending request alerts grid in the Management Portal.
Subject	Body	<b>Required</b> . A string indicating the subject for the email message that will be delivered when the alert is triggered.
		Tip: Substitutable special text may be used in the subject line. Substitutable special text uses a variable in the alert definition that is replaced by data from the certificate request or certificate metadata at processing time. For example, you can enter {rcn} in the alert definition and each alert generated at processing time will contain the specific requested common name of the given certificate request instead of the variable {rcn}.
Message	Body	Required. A string indicating the email message that will be delivered when the alert is triggered. The email message is made up of regular text and substitutable special text. If desired, you can format the message body using HTML. For example:  "Hello,\n\nA certificate using the {template} template was requested by {requester:displayname} from {careqid} on {subdate}. The certificate details include:\nPlease review this request and issue the certificate as appropriate by going here:\n\n{apprlink}\n\nThanks!\n\nYour Certificate Management Tool\n" See Table: Substitutable Special Text for Pending Request Alerts in the Keyfactor Command Reference Guide for a complete list of available substitutable special text strings.
Recipients	Body	An array of strings containing the recipients for the alert. Each alert can have multiple recipients. You can use specific email addresses and/or use substitutable special text to replace an email address variable with actual email addresses at processing time. Available email substitutable special text strings include:  • {requester:mail}  The certificate requester, based on a lookup in Active Directory of the email address associated with the requester on the certificate.

Name	In	Description			
		<ul> <li>Your custom email-based metadata field, which would be specified similarly to {metadata:AppOwnerEmailAddress}.</li> </ul>			
TemplateId	Body	An integer indicating the certificate template for which the pending request alerts will be generated. A separate alert should be configured for each template. An alert may be configured with no template, if desired. Alerts configured in this way generate alerts for all pending certificate requests.  Use the GET /Templates method (see GET Templates on page 1185) to retrieve a list of all the templates to determine the template ID.			
RegisteredEventHandler	Body	An object containing Possible values are:	the event handle	r configuration for the alert, if applicable.	
		Value	Description		
		Id		An integer indicating the Keyfactor Command reference D for the event handler.	
			ID	Event Handler Type	
			8	PendingLogger	
			9	PendingPowershell	
		UseHandler		ating whether event handler use is alert (true) or not (false).	
		For more information Keyfactor Command		dlers, see <i>Using Event Handlers</i> in the	
EventHandlerParameters	Body	An array containing the parameters configured for use by the event handler. The type of data will vary depending on the configured handler. Possible values are:			
		Value	Description	1	
		Id	-	ndicating the Keyfactor Command refer- ne configured parameter.	
		Кеу	A string indic	cating the reference name of the arameter.	
	DefaultValue		A string indic	cating the value for the parameter. This	

Name	In	Description		
		Value	Description	
			value is related to the type of parameter (see <i>ParameterType</i> ).	
		ParameterType	A string containing the parameter type. Supported types are:  • LogTarget This type is used for the event logging handler and is used to reference the fully qualified domain name of the target machine to which event should be logged.  • Script This type is used for the PowerShell handler and is used to reference the PowerShell script that should be run when the alert is triggered. It is referenced using the filename and optional relative path to the PowerShell script, located in the extensions directory on the Keyfactor Command server.  • Token This type is used for the PowerShell handler and is used to reference a substitutable special text value that should be passed to the PowerShell script. See Table: Substitutable Special Text for Pending Request Alerts in the Keyfactor Command Reference Guide for a complete list of available substitutable special text strings.  • Value This type is used for the PowerShell handler and is used to reference a static text string that should be passed to the PowerShell script.	
		For example, for a PowerShell handler:		
		"EventHandlerPara { "Id": 28, "Key": "cn" "DefaultVal	,	

Name	In	Description
		<pre>"ParameterType": "Token" }, {     "Id": 29,     "Key": "AppOwnerFirstName",     "DefaultValue": "metadata:AppOwnerFirstName",     "ParameterType": "Token" }, {     "Id": 30,     "Key": "Text",     "DefaultValue": "Pending Alert: Enterprise Web Server",     "ParameterType": "Value" }, {     "Id": 31,     "Key": "ApprovalLink",     "DefaultValue": "apprlink",     "ParameterType": "Token" }, {     "Id": 32,     "Key": "ScriptName",     "DefaultValue": "MyScript.ps1",     "ParameterType": "Script" } ]</pre>
CARequestId		A string containing the CA's reference ID for the certificate request.
CommonName		A string indicating the common name of the certificate.
LogicalName		A string indicating the logical name of the certificate authority.

Table 109: POST Alerts Pending Response Data

Name	Description		
Id	An integer indicating the Keyfactor Command reference ID of the pending request alert. Run GET /Alerts/Pending to find the pending request alert ID.		
DisplayName	A string indicating the display name for the pending request alert. This name appears in the pending request alerts grid in the Management Portal.		
Subject	A string indicating the subject for the email message that will be delivered when the alert is triggered.  Tip: Substitutable special text may be used in the subject line. Substitutable special text uses a variable in the alert definition that is replaced by data from the certificate request or certificate metadata at processing time. For example, you can enter {rcn} in the alert definition and each alert generated at processing time will contain the specific requested common name of the given certificate request instead of the variable {rcn}.		
Message	A string indicating the email message that will be delivered when the alert is triggered. The email message is made up of regular text and substitutable special text. If desired, you can format the message body using HTML. For example:  "Hello,\n\nA certificate using the {template} template was requested by {requester:displayname} from {careqid} on {subdate}. The certificate details include:\n\n <t-able>\n \cron\  \cron\  \careqid} on {subdate}. The certificate details include:\n\n<t-able>\n\rt&gt;\cron\ \cron\ \cron\ \cron\ \cron\ \cron\ \cron\ \cron\ \cron\ \cron\ \cron\&lt;\td&gt;\cron\&lt;\td&gt;\cron\&lt;\td&gt;\cron\&lt;\td&gt;\cron\&lt;\td&gt;\cron\&lt;\td&gt;\cron\&lt;\td&gt;\cron\&lt;\td&gt;\cron\&lt;\td&gt;\cron\&lt;\td&gt;\cron\&lt;\cron\&lt;\td&gt;\cron\&lt;\td&gt;\cron\&lt;\td&gt;\cron\&lt;\td&gt;\cron\&lt;\td&gt;\cron\&lt;\td&gt;\cron\&lt;\td&gt;\cron\&lt;\td&gt;\cron\&lt;\td&gt;\cron\&lt;\td&gt;\cron\&lt;\td&gt;\cron\&lt;\cron\&lt;\td&gt;\cron\&lt;\td&gt;\cron\&lt;\td&gt;\cron\&lt;\cron\&lt;\td&gt;\cron\&lt;\cron\&lt;\cron\&lt;\td&gt;\cron\&lt;\cron\&lt;\cron\&lt;\cron\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\</t-able></t-able>		
Recipients	An array of strings containing the recipients for the alert. Each alert can have multiple recipients. You can use specific email addresses and/or use substitutable special text to replace an email address variable with actual email addresses at processing time. Available email substitutable special text strings include:  • {requester:mail}		

Name	Description			
	The certificate requester, based on a lookup in Active Directory of the email address associated with the requester on the certificate.  • Your custom email-based metadata field, which would be specified similarly to {metadata:AppOwnerEmailAddress}.			
Template	An object containing information about the certificate template for which the pending request alerts will be generated. A separate alert should be configured for each template. An alert may be configured with no template, if desired. Alerts configured in this way generate alerts for all pending certificate requests. Possible values are:			
	Value Description			
	Id	An integer indicating the Keyfactor Command reference ID for the template, or <i>null</i> for all templates.		
	DisplayName	A string containing the name of the template. For a template created using a Microsoft management tool, this will be the Microsoft template display name.		
	ForestRoot	A string indicating the forest root of the template.		
		Note: This field is retained for legacy purposes and will be replaced by ConfigurationTenant field.		
	ConfigurationTenant	A string indicating the configuration tenant of the template.		

Name	Description				
RegisteredEventHandler	An object containing the event handler configuration for the alert, if applicable. Possible values are:				
	Value Description				
	Id	An integer indicating the Keyfactor Command reference ID for the event handler.			
		ID	Event Handler Type		
		8	PendingLogger		
		9	PendingPowershell		
	DisplayName	A string containing	the name of the event handler.		
	UseHandler A Boolean indicating whether event handler use is enabled the alert (true) or not (false).				
	For more information about event handlers, see <i>Using Event Handlers</i> in the <i>Keyfactor Command Reference Guide</i> .				
EventHandlerParameters	An array containing the parameters configured for use by the event handler. The type of data will vary depending on the configured handler. Possible values are:				
	Value	Description			
	Id	An integer indicating the Keyfactor Command reference ID of the configured parameter.			
	Key	A string indicating the reference name of the configured parameter.			
	DefaultValue	A string indicating the value for the parameter. This value is related to the type of parameter (see <i>ParameterType</i> ).			
	ParameterType	<ul> <li>LogTarget         This type         used to re         the target     </li> <li>Script</li> </ul>	ing the parameter type. Supported types are: is used for the event logging handler and is eference the fully qualified domain name of machine to which event should be logged. is used for the PowerShell handler and is		

Name	Description			
	Value	Description		
		used to reference the PowerShell script that should be run when the alert is triggered. It is referenced using the filename and optional relative path to the Power-Shell script, located in the extensions directory on the Keyfactor Command server.  • Token  This type is used for the PowerShell handler and is used to reference a substitutable special text value that should be passed to the PowerShell script. See Table: Substitutable Special Text for Pending Request Alerts in the Keyfactor Command Reference Guide for a complete list of available substitutable special text strings.  • Value  This type is used for the PowerShell handler and is used to reference a static text string that should be passed to the PowerShell script.		

### **PUT Alerts Pending**

The PUT /Alerts/Pending method is used to update a pending certificate request alert. This method returns HTTP 200 OK on a success with details about the pending certificate request alert.



**Tip:** The following permissions (see Security Overview) are required to use this feature: WorkflowManagement: Modify



Warning: Any previously populated fields that are not submitted with their full existing data using this method will be cleared of their existing data. When using this method, you should first do a GET to retrieve all the values for the record you want to update, enter corrected data into the field(s) you want to update, and then submit all the fields using PUT, including the fields that contain values but which you are not changing.

Table 110: PUT Alerts Pending Input Parameters

Name	In	Description
id	Path	An integer indicating the Keyfactor Command reference ID of the pending request alert. Run the
DisplayName	Body	<b>Required</b> . A string indicating the display name for the pending request alert. This name appears in the pending request alerts grid in the Management Portal.
Subject	Body	<b>Required</b> . A string indicating the subject for the email message that will be delivered when the alert is triggered.
		Tip: Substitutable special text may be used in the subject line. Substitutable special text uses a variable in the alert definition that is replaced by data from the certificate request or certificate metadata at processing time. For example, you can enter {rcn} in the alert definition and each alert generated at processing time will contain the specific requested common name of the given certificate request instead of the variable {rcn}.
Message	Body	Required. A string indicating the email message that will be delivered when the alert is triggered. The email message is made up of regular text and substitutable special text. If desired, you can format the message body using HTML. For example:  "Hello,\n\nA certificate using the {template} template was requested by {requester:displayname} from {careqid} on {subdate}. The certificate details include:\n\n\n Include:\n\n\n Certificate   Details   Details   Heladata:AppOwnerFirstName}   First Name: {metadata:AppOwnerFirstName}   PownerLast Name: {metadata:AppOwnerFirstName}    PownerLastName}   SANs: {san}    Address: {metadata:AppOwnerEmailAddress}   PownerEmailAddress}   Address: {metadata:AppOwnerEmailAddress}   PownerEmailAddress}   Address: {metadata:AppownerEmailAddress}   PownerEmailAddress   Address: {metadata:AppownerEmailAddress}   Address: {metadata:AppownerEma
Recipients	Body	An array of strings containing the recipients for the alert. Each alert can have multiple recipients. You can use specific email addresses and/or use substitutable special text to replace an email address variable with actual email addresses at processing time. Available email substitutable special text strings include:  • {requester:mail}

Name	In	Description			
		The certificate requester, based on a lookup in Active Directory of the email address associated with the requester on the certificate.  • Your custom email-based metadata field, which would be specified similarly to {metadata:AppOwnerEmailAddress}.			
TemplateId	Body	An integer indicating the certificate template for which the pending request alerts will be generated. A separate alert should be configured for each template. An alert may be configured with no template, if desired. Alerts configured in this way generate alerts for all pending certificate requests.  Use the GET /Templates method (see GET Templates on page 1185) to retrieve a list of all the templates to determine the template ID.			
RegisteredEventHandler	Body	An object containing Possible values are:	the event handle	er configuration for the alert, if applicable.	
		Value	Description		
		Id	An integer indicating the Keyfactor Command reference ID for the event handler.		
			ID	Event Handler Type	
			8	PendingLogger	
			9	PendingPowershell	
		UseHandler		A Boolean indicating whether event handler use is enabled for the alert (true) or not (false).	
		For more information about event handlers, see <i>Using Event Handlers</i> in the <i>Keyfactor Command Reference Guide</i> .			
Event Handler Parameters	Body	An array containing the parameters configured for use by the event handler. The type of data will vary depending on the configured handler. Possible values are:			
		Value Description		n	
		Id	_	ndicating the Keyfactor Command refer- he configured parameter.	
		Key	A string indiconfigured	icating the reference name of the parameter.	

Name	In	Description			
		Value	Description		
		DefaultValue	A string indicating the value for the parameter. This value is related to the type of parameter (see <i>ParameterType</i> ).		
		ParameterType	<ul> <li>A string containing the parameter type. Supported types are: <ul> <li>LogTarget</li> <li>This type is used for the event logging handler and is used to reference the fully qualified domain name of the target machine to which event should be logged.</li> <li>Script</li> <li>This type is used for the PowerShell handler and is used to reference the PowerShell script that should be run when the alert is triggered. It is referenced using the filename and optional relative path to the PowerShell script, located in the extensions directory on the Keyfactor Command server.</li> </ul> </li> <li>Token <ul> <li>This type is used for the PowerShell handler and is used to reference a substitutable special text value that should be passed to the PowerShell script. See Table: Substitutable Special Text for Pending Request Alerts in the Keyfactor Command Reference Guide for a complete list of available substitutable special text strings.</li> <li>Value <ul> <li>This type is used for the PowerShell handler and is used to reference a static text string that should be passed to the PowerShell script.</li> </ul> </li> </ul></li></ul>		
		For example, for a PowerShell handler:			
		"EventHandlerPar { "Id": 28,	rameters": [		

Name	In	Description
		<pre>"Key": "cn",    "DefaultValue": "rcn",    "ParameterType": "Token" }, {    "Id": 29,    "Key": "AppOwnerFirstName",    "DefaultValue": "metadata:AppOwnerFirstName",    "ParameterType": "Token" }, {    "Id": 30,    "Key": "Text",    "DefaultValue": "Pending Alert: Enterprise Web Server",    "ParameterType": "Value" }, {    "Id": 31,    "Key": "ApprovalLink",    "DefaultValue": "apprlink",    "ParameterType": "Token" }, {    "Id": 32,    "Key": "ScriptName",    "DefaultValue": "MyScript.ps1",    "ParameterType": "Script" } </pre>

Table 111: PUT Alerts Pending Response Data

Name	Description		
Id	An integer indicating the Keyfactor Command reference ID of the pending request alert.  Run GET /Alerts/Pending to find the pending request alert ID.		
DisplayName	A string indicating the display name for the pending request alert. This name appears in the pending request alerts grid in the Management Portal.		
Subject	A string indicating the subject for the email message that will be delivered when the alert is triggered.		
	Tip: Substitutable special text may be used in the subject line. Substitutable special text uses a variable in the alert definition that is replaced by data from the certificate request or certificate metadata at processing time. For example, you can enter {rcn} in the alert definition and each alert generated at processing time will contain the specific requested common name of the given certificate request instead of the variable {rcn}.		
Message	A string indicating the email message that will be delivered when the alert is triggered. The email message is made up of regular text and substitutable special text. If desired, you can format the message body using HTML.  For example:  "Hello,\n\nA certificate using the {template} template was requested by {requester:displayname} from {careqid} on {subdate}. The certificate details include:\n\n <t-able>\n \table&gt;\n \table&gt;\n\table&gt;\n \table&gt;\n\table&gt;\n\table&gt;\table&gt;\n\table&gt;</t-able>		
Recipients	An array of strings containing the recipients for the alert. Each alert can have multiple recipients. You can use specific email addresses and/or use substitutable special text to replace an email address variable with actual email addresses at processing time. Available email substitutable special text strings include:  • {requester:mail}		

Name	Description			
	<ul> <li>The certificate requester, based on a lookup in Active Directory of the email address associated with the requester on the certificate.</li> <li>Your custom email-based metadata field, which would be specified similarly to {metadata:AppOwnerEmailAddress}.</li> </ul>			
Template	An object containing information about the certificate template for which the pending request alerts will be generated. A separate alert should be configured for each template. An alert may be configured with no template, if desired. Alerts configured in this way generate alerts for all pending certificate requests. Possible values are:			
	Value Description			
	Id	An integer indicating the Keyfactor Command reference ID for the template, or <i>null</i> for all templates.		
	DisplayName	A string containing the name of the template. For a template created using a Microsoft management tool, this will be the Microsoft template display name.		
	ForestRoot	A string indicating the forest root of the template.		
		Note: This field is retained for legacy purposes and will be replaced by ConfigurationTenant field.		
	ConfigurationTenant	A string indicating the configuration tenant of the template.		

Name	Description				
RegisteredEventHandler	An object containing the event handler configuration for the alert, if applicable. Possible values are:				
	Value Description				
	Id	An integer indicating the Keyfactor Command reference ID for the event handler.			
		ID	Event Handler Type		
		8	PendingLogger		
		9	PendingPowershell		
	DisplayName	A string containing	g the name of the event handler.		
	UseHandler A Boolean indicating whether event handler use is enabled the alert (true) or not (false).				
	For more information about event handlers, see <i>Using Event Handlers</i> in the <i>Keyfactor Command Reference Guide</i> .				
EventHandlerParameters	An array containing the parameters configured for use by the event handler. The type of data will vary depending on the configured handler. Possible values are:				
	Value	Description			
	Id	An integer indicating the Keyfactor Command reference ID of the configured parameter.			
	Key	A string indicating the reference name of the configured parameter.			
	DefaultValue	A string indicating the value for the parameter. This value is related to the type of parameter (see <i>ParameterType</i> ).			
	ParameterType	<ul> <li>LogTarget         This type         used to re         the target     </li> <li>Script</li> </ul>	ing the parameter type. Supported types are: is used for the event logging handler and is eference the fully qualified domain name of e machine to which event should be logged. is used for the PowerShell handler and is		

Name	Description	
	Value	Description
		used to reference the PowerShell script that should be run when the alert is triggered. It is referenced using the filename and optional relative path to the Power-Shell script, located in the extensions directory on the Keyfactor Command server.  • Token  This type is used for the PowerShell handler and is used to reference a substitutable special text value that should be passed to the PowerShell script. See Table: Substitutable Special Text for Pending Request Alerts in the Keyfactor Command Reference Guide for a complete list of available substitutable special text strings.  • Value  This type is used for the PowerShell handler and is used to reference a static text string that should be passed to the PowerShell script.
CARequestId	A string containing the CA's reference ID for the certificate request.	
CommonName	A string indicating the common name of the certificate.	
LogicalName	A string indicating the logical name of the certificate authority.	

#### **POST Alerts Pending Test**

The POST /Alerts/Pending/Test method is used to test individual pending certificate request alerts. This method returns HTTP 200 OK on a success with details about the resulting alerts generated.



Tip: Alerts are generated for all certificate requests that have not previously been alerted on, unless the system has been configured to send multiple alerts per request. By default, one alert is sent to each recipient for any given request. The number of alerts to send for a given request is configurable with the *Pending Alert Max Reminders* setting in Keyfactor Command application settings (see <u>Application Settings: Console Tab</u> in the *Keyfactor Command Reference Guide*). If a certificate remains in a pending state after the configured number of alerts has been sent, no further alerts will be sent. By default, a maximum of 100 alerts will be generated during a test. The maximum value is configurable with the *Pending Alert Test Result Limit* setting in Keyfactor Command application settings (see <u>Application Settings: Console Tab</u> in the *Keyfactor Command Reference Guide*). If more than 100 alerts are generated, no email messages will be sent and you'll have the opportunity to view the first 100 alerts generated.



If you're using an event handler, the event handler is run and the handler actions taken (PowerShell script run, event log message) when the test is run. This is true regardless of the setting of the *sendAlertsEmails* flag.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature:

WorkflowManagement: *Read* WorkflowManagement: *Test* 

Table 112: POST Alerts Pending Test Input Parameters

Parameter	In	Description	
req	Body	Required. An array containing information for the alert test. Alert test detail values are:	
		Value	Description
		AlertId	An integer indicating the Keyfactor Command reference ID for the pending alert.
		SendAlerts	A Boolean indicating whether to send alert emails with the test (true), or not (false).
		For example:	
		{     "AlertId":     "SendAlertI	1, Emails": false

Table 113: POST Alerts Pending Test Response Data

Parameter	Description	
PendingAlerts	An object containing al	ert details resulting from the test. Pending alert details are
	Name Description	
	Subject	A string indicating the subject for the email message that will be delivered when the alert is triggered.
Subject	Tip: Substitutable special text may be used in the subject line. Substitutable special text uses a variable in the alert definition that is replaced by data from the certificate request or certificate metadata at processing time. For example, you can enter {rcn} in the alert definition and each alert generated at processing time will contain the specific requested common name of the given certificate request instead of the variable {rcn}.	

Parameter	Description		
	Name	Description	
	Message	A string indicating the email message that will be delivered when the alert is triggered. The email message is made up of regular text and substitutable special text. If desired, you can format the message body using HTML.	
	Recipients	An object containing a list of strings with the recipients for the alert. Each alert can have multiple recipients. You can use specific email addresses and/or use substitutable special text to replace an email address variable with actual email addresses at processing time.	
	CARequestId	An string containing the CA's reference ID for the certificate request.	
	CommonName	A string indicating the common name of the certificate request.	
	LogicalName	A string indicating the logical name of the certificate authority from which the certificate was requested.	
AlertBuildResult	A string indicating the result of pending alerts test (e.g. Success).		

### **POST Alerts Pending TestAll**

The POST /Alerts/Pending/TestAll method is used to test all pending certificate request alerts. This method returns HTTP 200 OK on a success with details about the resulting number of alerts generated.



Tip: Alerts are generated for all certificate requests that have not previously been alerted on, unless the system has been configured to send multiple alerts per request. By default, one alert is sent to each recipient for any given request. The number of alerts to send for a given request is configurable with the *Pending Alert Max Reminders* setting in Keyfactor Command application settings (see <u>Application Settings: Console Tab</u> in the *Keyfactor Command Reference Guide*). If a certificate remains in a pending state after the configured number of alerts has been sent, no further alerts will be sent. By default, a maximum of 100 alerts will be generated during a test. The maximum value is configurable with the *Pending Alert Test Result Limit* setting in Keyfactor Command application settings (see <u>Application Settings: Console Tab</u> in the *Keyfactor Command Reference Guide*). If more than 100 alerts are generated,

If you're using an event handler, the event handler is run and the handler actions taken (PowerShell script run, event log message) when the test is run. This is true regardless of the setting of the *sendAlertsEmails* flag.

no email messages will be sent and you'll have the opportunity to view the first 100 alerts generated.



WorkflowManagement: Test

Table 114: POST Alerts Pending Test All Input Parameters

Name	In	Description	
req	Body	<b>Required</b> . An array containing information for the alert test. Alert test detail values are:	
		Value	Description
		SendAlerts	A Boolean indicating whether to send alert emails with the test (true), or not (false).
		For example:	
	{     "SendAlertI }	Emails": false	

Table 115: POST Alerts Pending Test All Response Data

Name	Description			
PendingAlerts	An object containing alert details resulting from the test. Pending alert details are:			
	Name	Description		
	Subject	A string indicating the subject for the email message that will be delivered when the alert is triggered.		
		Tip: Substitutable special text may be used in the subject line. Substitutable special text uses a variable in the alert definition that is replaced by data from the certificate request or certificate metadata at processing time. For example, you can enter {rcn} in the alert definition and each alert generated at processing time will contain the specific requested common name of the given certificate request instead of the variable {rcn}.		
	Message	A string indicating the email message that will be delivered when the alert is triggered. The email message is made up of regular text and substitutable special text. If desired, you can format the message body using HTML.		
	Recipients	An object containing a list of strings with the recipients for the alert. Each alert can have multiple recipients. You can use specific email addresses and/or use substitutable special text to replace an email address variable with actual email addresses at processing time.		
	CARequestId	An string containing the CA's reference ID for the certificate request.		
	CommonName	A string indicating the common name of the certificate request.		
	LogicalName	A string indicating the logical name of the certificate authority from which the certificate was requested.		
AlertBuildResult	An integer indicating th	e number of pending alerts run by the test.		

## 2.2.5 Audit

The Audit component of the Keyfactor API is used to track changes to the Keyfactor Command operation and configuration.

Table 116: Audit Endpoints

Endpoint	Method	Description	Links
/{id}	GET	Returns information about the specified audit log entry.	GET Audit ID below
/{id}/Validate	GET	Validates the specified audit log entry.	GET Audit ID Validate on page 194
/	GET	Returns a list of all audit log entries according to the provided filters and input parameters.	GET Audit on page 194
/Download	GET	Returns a comma separated list of audit log entries according to the provided filters and input parameters.	GET Audit Down- load on page 200
/RelatedEntities	GET	Returns a list of all audit log entries and entries related to this entry according to the provided filters and input parameters.	GET Audit Related Entities on page 202

#### 2.2.5.1 GET Audit ID

The GET /Audit/{id} method is used to retrieve details for a specified audit entry. This method returns HTTP 200 OK on a success with audit log details.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: Auditing: *Read* 

Table 117: GET Audit {id} Input Parameters

Name	In	Description
id	Path	Required. The ID of the audit log entry to retrieve.  Use the GET /Audit method (see GET Audit on page 194) to retrieve a list of all the audit log entries to determine the audit log entry ID.

Table 118: GET Audit {id} Response Data

Name	Description			
	The ID of the specified audit log entry.			
Id				
TimeStamp	The timestamp	(UTC) on the audit log entry indicating when the ac	ction performed occurred.	
Message	XML data on the	e audit event.		
Signature	The signature o	n the audit entry.		
Category	An integer iden	tifying the category of the audit entry. Possible val	ues are:	
	Value	Subcategory Name	Description	
	2001	Certificate	Certificate	
	2001	AuditingCertificateScheduledReplacement	Auditing Certificate Scheduled Replacement	
	2001	AuditingCertificateRequest	Certificate Request	
	2002	ApiApplication	API Application	
	2003	Template	Template	
	2004	CertificateQuery	Certificate Collection/Query	
	2005	ExpirationAlert	Expiration Alert	
	2005	ExpirationAlertDefinitionContextModel	Expiration Alert	
	2006	PendingAlert	Pending Alert	
	2006	PendingAlertDefinitionContextModel	Pending Alert	
	2007	ApplicationSetting	Application Setting	
	2008	IssuedAlert	Issued Alert	
	2008	IssuedAlertDefinitionContextModel	Issued Alert	
	2009	DeniedAlert	Denied Alert	

Name	Description		
	Value	Subcategory Name	Description
	2009	DeniedAlertDefinitionContextModel	Denied Alert
	2010	ADIdentityModel	Security Identity
	2011	SecurityRole	Security Role
	2012	AuthorizationFailure	Authorization Failure
	2013	CertificateSigningRequest	CSR
	2014	ServerGroup	SSH Server Group
	2015	Server	SSH Server
	2016	DiscoveredKey	Rogue Key for Logon
	2016	Key	SSH Key
	2017	ServiceAccount	SSH Service Account
	2018	Logon	SSH Logon
	2019	SshUser	SSH User
	2020	KeyRotationAlertDefinitionContextModel	SSH Key Rotation Alert
	2021	CertificateStore	Certificate Store
	2022	JobType	Orchestrator Job Type
	2023	AgentSchedule	Orchestrator Job
	2024	BulkAgentSchedule	Bulk Orchestrator Job
	2025	CertificateStoreContainer	Store Container
	2026	Agent	Orchestrator
	2027	RevocationMonitoring	Monitoring
	2028	License	License
	2029	WorkflowDefinition	Workflow Definition

Name	Description	Description			
	Value	Subcategory	Name	Description	
	2030	WorkflowInst	ance	Workflow Instance	
	2031	WorkflowInstanceSignal		Workflow Instance Signal	
	query v contair	Tip: To do a query by category, use the subcategory string. For example, the following query would return audit records for categories 2023, 2024, and 2026 since they all contain "Agent" in the subcategory:  category -contains "Agent"			
Operations	An integer ider	tifying the opera	tion of the audit entry. Possible va	alues are:	
	Value		Description		
	1		Created		
	2		Updated		
	3		Deleted		
	4		Approved		
	5		Denied		
	6		Revoked		
	7		Downloaded		
	8		Deleted Private Key		
	9		Renewed		
	10		Encountered		
	11		Scheduled Replacement		
	12		Recovered		
	13		Imported		
	14		Removed from Hold		

Name	Description		
	Value	Description	
	15	Scheduled Add	
	16	Scheduled Removal	
	17	Download with Private Key	
	18	Scheduled	
	19	Reset	
	20	Disapproved	
	21	Restarted	
	22	Sent	
	23	Failed	
	24	Completed	
	25	Rejected	
Level	The alert level of the audit log e	ntry. Possible values are:	
	Value	Description	
	0	Information	
	1	Warning	
	2	Failure	
User	The user who performed the audit event in DOMAIN\username format.		
EntityType	The category of the object being audited (e.g. Template, Certificate).		
AuditIdentifier	An identifier of the object being audited (e.g. the template name for a template, the CN for a certificate). It is important to note that this is a value that is typically used for easy identification of an object, but is not necessarily unique, and is subject to change.		
ImmutableIdentifier	The fixed ID of the auditable even	ent in the Keyfactor database.	

### 2.2.5.2 GET Audit ID Validate

The GET /Audit/{id}/Validate method is used to return whether or not (true or false) the audit log entry is valid. An audit log might become invalidated if it is tampered with. This method returns HTTP 200 OK on a success with a value of true or false.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: Auditing: *Read* 

Table 119: GET Audit {id} Validate Input Parameters

Name	In	Description
id	Path	Required. The ID of the audit log entry to validate.  Use the GET /Audit method (see GET Audit below) to retrieve a list of all the audit log entries to determine the audit log entry ID.

Table 120: GET Audit {id} Validate Response Data

Name	Description	
	A Boolean that indicates whether the audit log entry is valid (true) or not (false). This value is returned without a parameter name.	

#### 2.2.5.3 GET Audit

The GET /Audit method returns a list of all audit entries. This method returns HTTP 200 OK on a success with audit log details.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: Auditing: *Read* 

Table 121: GET Audit Input Parameters

Name	In	Description
queryString	Query	A string containing a query to limit the results (e.g. field1 -eq value1 AND field2 -gt value2). The default is to return all records. Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns for the same feature. For querying guidelines, refer to the Keyfactor Command Reference Guide: Using the Audit Log Search Feature. The query fields supported for this endpoint are:  • Name (Entityldentifier)  • Category (EntityType) (see Table 122: GET Audit Response Data for codes)  • ImmutableIdentifier  • Level (see Table 122: GET Audit Response Data for codes)  • Operation (see Table 122: GET Audit Response Data for codes)  • PropertyChanged  • Timestamp  • ActingUser  Tip: To do a query by category, use the subcategory string (see Category in the response data). For example: category -contains "Agent"
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>Id</i> .
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.

Table 122: GET Audit Response Data

Name	Description			
Id	The ID of the specified audit log entry.			
TimeStamp	The timestamp	(UTC) on the audit log entry indicating when the ac	ction performed occurred.	
Message	XML data on th	e audit event.		
Signature	The signature o	n the audit entry.		
Category	An integer iden	tifying the category of the audit entry. Possible val	ues are:	
	Value	Subcategory Name	Description	
	2001	Certificate	Certificate	
	2001	AuditingCertificateScheduledReplacement	Auditing Certificate Scheduled Replacement	
	2001	AuditingCertificateRequest	Certificate Request	
	2002	ApiApplication	API Application	
	2003 Template Template			
	2004	CertificateQuery	Certificate Collection/Query	
	2005	ExpirationAlert	Expiration Alert	
	2005	ExpirationAlertDefinitionContextModel	Expiration Alert	
	2006	PendingAlert	Pending Alert	
	2006	PendingAlertDefinitionContextModel	Pending Alert	
	Application Setting			
	2008	IssuedAlert	Issued Alert	
	2008	IssuedAlertDefinitionContextModel	Issued Alert	
	2009	DeniedAlert	Denied Alert	

Name	Description		
	Value	Subcategory Name	Description
	2009	DeniedAlertDefinitionContextModel	Denied Alert
	2010	ADIdentityModel	Security Identity
	2011	SecurityRole	Security Role
	2012	AuthorizationFailure	Authorization Failure
	2013	CertificateSigningRequest	CSR
	2014	ServerGroup	SSH Server Group
	2015	Server	SSH Server
	2016	DiscoveredKey	Rogue Key for Logon
	2016	Кеу	SSH Key
	2017	ServiceAccount	SSH Service Account
	2018	Logon	SSH Logon
	2019	SshUser	SSH User
	2020	KeyRotationAlertDefinitionContextModel	SSH Key Rotation Alert
	2021	CertificateStore	Certificate Store
	2022	JobType	Orchestrator Job Type
	2023	AgentSchedule	Orchestrator Job
	2024	BulkAgentSchedule	Bulk Orchestrator Job
	2025	CertificateStoreContainer	Store Container
	2026	Agent	Orchestrator
	2027	RevocationMonitoring	Monitoring
	2028	License	License
	2029	WorkflowDefinition	Workflow Definition

Name	Description			
	Value	Subcategory	Name	Description
	2030	WorkflowInst	ance	Workflow Instance
	2031 WorkflowInsta		anceSignal	Workflow Instance Signal
	query v contain	vould return aud "Agent" in the s	ategory, use the subcategory string it records for categories 2023, 202 subcategory: rains "Agent"	
Operations	An integer iden	tifying the opera	ntion of the audit entry. Possible va	alues are:
	Value		Description	
	1		Created	
	2		Updated	
	3		Deleted	
	4		Approved	
	5		Denied	
	6		Revoked	
	7		Downloaded	
	8		Deleted Private Key	
	9		Renewed	
	10		Encountered	
	11		Scheduled Replacement	
	12		Recovered	
	13		Imported	
	14		Removed from Hold	

Name	Description		
	Value	Description	
	15	Scheduled Add	
	16	Scheduled Removal	
	17	Download with Private Key	
	18	Scheduled	
	19	Reset	
	20	Disapproved	
	21	Restarted	
	22	Sent	
	23	Failed	
	24	Completed	
	25	Rejected	
Level	The alert level of the audit log e	ntry. Possible values are:	
	Value	Description	
	0	Information	
	1	Warning	
	2	Failure	
User	The user who performed the audit event in DOMAIN\username format.		
EntityType	The category of the object being audited (e.g. Template, Certificate).		
AuditIdentifier	An identifier of the object being audited (e.g. the template name for a template, the CN for a certificate). It is important to note that this is a value that is typically used for easy identification of an object, but is not necessarily unique, and is subject to change.		
ImmutableIdentifier	The fixed ID of the auditable eve	ent in the Keyfactor database.	

#### 2.2.5.4 GET Audit Download

The GET /Audit/Download method returns a comma-delimited list of all audit entries matching the requested filters appropriate for output to a CSV file. This method returns HTTP 200 OK on a success with the information requested in comma-delimited form with the property names at the start of the list and then the values.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: Auditing: *Read* 

Table 123: GET Audit Download Input Parameters

Name	In	Description
queryString	Query	A string containing a query to limit the results (e.g. field1 -eq value1 AND field2 -gt value2). The default is to return all records. Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns for the same feature. For querying guidelines, refer to the Keyfactor Command Reference Guide: Using the Audit Log Search Feature. The query fields supported for this endpoint are:  • Name (EntityIdentifier)  • Category (EntityType) (see Table 122: GET Audit Response Data for codes)  • ImmutableIdentifier  • Level (see Table 122: GET Audit Response Data for codes)  • Operation (see Table 122: GET Audit Response Data for codes)  • PropertyChanged  • Timestamp  • ActingUser
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>Id</i> .
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.

Table 124: GET Audit Download Response Data

Name	Description		
Id	The ID of the specified audit log entry.		
TimeStamp	The timestamp (UTC) on the audi	t log entry indicating when the action performed occurred.	
Message	The message as displayed in the k	Keyfactor Command Management Portal.	
Message	XML data on the audit event. Also	known as the XMLMessage in some interfaces.	
Operations	An integer identifying the operati	on of the audit entry. Possible values are:	
	Value	Description	
	1	Created	
	2	Updated	
	3	Deleted	
	4	Approved	
	5	Denied	
	6	Revoked	
	7	Downloaded	
	8	Deleted Private Key	
	9	Renewed	
	10	Encountered	
	11	Scheduled Replacement	
	12	Recovered	
	13	Imported	
	14	Removed from Hold	
	15	Scheduled Add	

Name	Description		
	Value	Description	
	16	Scheduled Removal	
	17	Download with Private Key	
	18	Scheduled	
	19	Reset	
	20	Disapproved	
	21	Restarted	
	22	Sent	
	23 Failed		
	24 Completed		
	25	Rejected	
Level	The alert level of the audit log entry. Possible values are:		
	Value	Description	
	0	Information	
	1	Warning	
	2	Failure	
User	The user who performed the audit event in DOMAIN\username format.		
EntityType	The category of the object being audited (e.g. Template, Certificate). Also known as the <i>Category</i> in some interfaces.		
AuditIdentifier	ficate). It is important to note tha	audited (e.g. the template name for a template, the CN for a certist this is a value that is typically used for easy identification of an que, and is subject to change. Also known as the <i>Name</i> in some	

### 2.2.5.5 GET Audit Related Entities

The GET /Audit/RelatedEntities method returns a list of all audit entries and all audit entries related to those audit entries. This method returns HTTP 200 OK on a success with the information requested.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: Auditing: *Read* 

Table 125: GET Audit Related Entities Input Parameters

Name	In	Description
queryString	Query	A string containing a query to limit the results (e.g. field1 -eq value1 AND field2 -gt value2). The default is to return all records. Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns for the same feature. For querying guidelines, refer to the Keyfactor Command Reference Guide: Using the Audit Log Search Feature. The query fields supported for this endpoint are:  • Name (Entityldentifier)  • Category (EntityType) (see Table 122: GET Audit Response Data for codes)  • ImmutableIdentifier  • Level (see Table 122: GET Audit Response Data for codes)  • Operation (see Table 122: GET Audit Response Data for codes)  • PropertyChanged  • Timestamp  • ActingUser  Tip: In order to return related entries, your queryString needs to query for the specific immutable identifier of the audit record for which you wish to see related entries. For example:  ImmutableIdentifier -eq 707662
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>Id</i> .
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.

Table 126: GET Audit Related Entities Response Data

Name	Description			
Id	The ID of the sp	pecified audit log entry.		
TimeStamp	The timestamp	(UTC) on the audit log entry indicating when the ac	ction performed occurred.	
Message	XML data on th	e audit event.		
Signature	The signature o	n the audit entry.		
Category	An integer iden	tifying the category of the audit entry. Possible val	ues are:	
	Value	Subcategory Name	Description	
	2001	Certificate	Certificate	
	2001	AuditingCertificateScheduledReplacement	Auditing Certificate Scheduled Replacement	
	2001	AuditingCertificateRequest	Certificate Request	
	2002	ApiApplication	API Application	
	2003	Template	Template	
	2004	CertificateQuery	Certificate Collection/Query	
	2005	ExpirationAlert	Expiration Alert	
	2005	ExpirationAlertDefinitionContextModel	Expiration Alert	
	2006	PendingAlert	Pending Alert	
	2006	PendingAlertDefinitionContextModel	Pending Alert	
	2007	ApplicationSetting	Application Setting	
	2008	IssuedAlert	Issued Alert	
	2008	IssuedAlertDefinitionContextModel	Issued Alert	
	2009	DeniedAlert	Denied Alert	

Name	Description		
	Value	Subcategory Name	Description
	2009	DeniedAlertDefinitionContextModel	Denied Alert
	2010	ADIdentityModel	Security Identity
	2011	SecurityRole	Security Role
	2012	AuthorizationFailure	Authorization Failure
	2013	CertificateSigningRequest	CSR
	2014	ServerGroup	SSH Server Group
	2015	Server	SSH Server
	2016	DiscoveredKey	Rogue Key for Logon
	2016	Кеу	SSH Key
	2017	ServiceAccount	SSH Service Account
	2018	Logon	SSH Logon
	2019	SshUser	SSH User
	2020	KeyRotationAlertDefinitionContextModel	SSH Key Rotation Alert
	2021	CertificateStore	Certificate Store
	2022	JobType	Orchestrator Job Type
	2023	AgentSchedule	Orchestrator Job
	2024	BulkAgentSchedule	Bulk Orchestrator Job
	2025	CertificateStoreContainer	Store Container
	2026	Agent	Orchestrator
	2027	RevocationMonitoring	Monitoring
	2028	License	License
	2029	WorkflowDefinition	Workflow Definition

Name	Description	Description			
	Value	Subcategory	Name	Description	
	2030	WorkflowInst	ance	Workflow Instance	
	2031	WorkflowInst	anceSignal	Workflow Instance Signal	
	query v contair	vould return aud "Agent" in the s	ategory, use the subcategory string it records for categories 2023, 202 ubcategory: ains "Agent"	-	
Operations	An integer ider	tifying the opera	tion of the audit entry. Possible va	alues are:	
	Value		Description		
	1		Created		
	2		Updated		
	3		Deleted		
	4		Approved		
	5		Denied		
	6		Revoked		
	7		Downloaded		
	8		Deleted Private Key		
	9		Renewed		
	10		Encountered		
	11		Scheduled Replacement		
	12		Recovered		
	13		Imported		
	14		Removed from Hold		

Name	Description		
	Value	Description	
	15	Scheduled Add	
	16 Scheduled Removal		
	17	Download with Private Key	
	18	Scheduled	
	19	Reset	
	20	Disapproved	
	21	Restarted	
	22	Sent	
	23	Failed	
	24	Completed	
	25	Rejected	
Level	The alert level of the audit log e	entry. Possible values are:	
	Value	Description	
	0	Information	
	1	Warning	
	2	Failure	
User	The user who performed the audit event in DOMAIN\username format.		
EntityType	The category of the object being audited (e.g. Template, Certificate).		
AuditIdentifier	An identifier of the object being audited (e.g. the template name for a template, the CN for a certificate). It is important to note that this is a value that is typically used for easy identification of an object, but is not necessarily unique, and is subject to change.		
ImmutableIdentifier	The fixed ID of the auditable event in the Keyfactor database.		

# 2.2.6 Certificates

The Certificates component of the Keyfactor API supports certificate lifecycle and management tasks, apart from enrollment.

Table 127: Certificates Endpoints

Endpoint	Method	Description	Link
/{id}/Security	GET	Returns details of the security identities that have been granted permissions to the specified certificate including what the specific permissions are.	GET Certificates ID Security on the next page
/{id}/Validate	GET	Validates that a certificate chain can be built for the specified certificate.	GET Certificates ID Validate on page 210
/Locations/{id}	GET	Returns details about the certificates stores in which the certificate is located.	GET Certificates Locations ID on page 216
/IdentityAudit/{id}	GET	Returns audit identity permissions for certificate.	GET Certificates Iden- tity Audit ID on page 219
/{id}	DELETE	Deletes a certificate from the Keyfactor Command database by its ID.	DELETE Certificates ID on page 220
/{id}	GET	Returns certificate details for a specified certificate.	GET Certificates ID on page 221
/Metadata/Compare	GET	Compares the metadata value provided with the metadata value associated with the specified certificate.	GET Certificates  Metadata Compare on page 233
/{id}/History	GET	Returns the certificate operations history for a specified certificate.	GET Certificates ID History on page 234
/	DELETE	Deletes multiple certificates from the Keyfactor Command database, as specified by the IDs in the request body.	DELETE Certificates on page 236
/	GET	Returns all certificates with paging (number of pages to return and number of results per page) and verbosity option to specify detail level.	GET Certificates on page 237
/Metadata	PUT	Updates the metadata for a specified certificate.	PUT Certificates  Metadata on page 251
/Metadata/All	PUT	Updates the metadata for an array of certificate	PUT Certificates

Endpoint	Method	Description	Link
		IDs.	Metadata All on page 252
/Import	POST	Imports a certificate into Keyfactor Command.	POST Certificates Import on page 255
/Revoke	POST	Revokes a certificate.	POST Certificates Revoke on page 258
/Analyze	POST	Reads a base-64 encoded PEM certificates and returns it in human-readable form.	POST Certificates Analyze on page 260
/Recover	POST	Returns a recovered certificate as a PFX.	POST Certificates Recover on page 261
/Download	POST	Downloads a certificate.	POST Certificates  Download on page 263
/RevokeAll	POST	Revokes all the certificates in the provided query.	POST Certificates Revoke All on page 265
/Query	DELETE	Deletes multiple certificates from the Keyfactor Command database based on search query.	DELETE Certificates Query on page 266
/PrivateKey	DELETE	Deletes the stored private keys of multiple certificates within the Keyfactor Command database.	DELETE Certificates Private Key on page 267
/PrivateKey/{id}	DELETE	Deletes the stored private key(s) of a certificate within the Keyfactor Command database.	DELETE Certificates Private Key ID on page 268

## 2.2.6.1 GET Certificates ID Security

The GET /Certificates/{id}/Security method is used to return details of permission granted to a specific certificate with the specified ID. This method returns HTTP 200 OK on a success with security details in the message body. Both global and collection-level permissions are included in the response.



**Tip:** The following permissions (see Security Overview) are required to use this feature:

Certificates: *Read* SecuritySettings: *Read* 

Table 128: GET Certificates {id} Security Input Parameters

Name	In	Description
id	Path	<b>Required</b> . The Keyfactor Command reference ID of the certificate for which to check security permissions.
CollectionId	Query	An integer specifying an optional certificate collection identifier to validate that the user executing the request has sufficient permissions to do so. If a certificate collection ID is not supplied, the user must have global permissions to complete the action. Supplying a certificate collection ID allows for a check of the user's certificate collection-level permissions to determine whether the user has sufficient permissions at a collection level to complete the action. See <i>Certificate Permissions</i> in the <i>Keyfactor Command Reference Guide</i> for more information.

Table 129: GET Certificates {id} Security Response Data

Name	Description	
Roles	An array containing the certificate-specific permissions granted to the named security identity broken down by permission and defined by role. All roles are returned, including those that have no permissions. Role information includes:	
	Name	Description
	Name	A string containing the short reference name for the security role.
	Permissions	An array of strings containing the permissions assigned to the role.
	For example, the follow	ing return snippet shows the response for the "Power Users" security role:
	<pre>{    "Name": "Power Users",    "Permissions": [         "Read",         "EditMetadata",         "Recover"    ] }</pre>	

### 2.2.6.2 GET Certificates ID Validate

The GET /Certificates/{id}/Validate method is used to return details for the validity of the X509 certificate chain for the certificate with the specified ID. This method returns HTTP 200 OK on a success with certificate chain validity details in the message body.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: Certificates: *Read* 

Table 130: GET Certificates {id} Validate Input Parameters

Name	In	Description
id	Path	Required. The Keyfactor Command reference ID of the certificate to be validated.
CollectionId	Query	An integer specifying an optional certificate collection identifier to validate that the user executing the request has sufficient permissions to do so. If a certificate collection ID is not supplied, the user must have global permissions to complete the action. Supplying a certificate collection ID allows for a check of the user's certificate collection-level permissions to determine whether the user has sufficient permissions at a collection level to complete the action. See <i>Certificate Permissions</i> in the <i>Keyfactor Command Reference Guide</i> for more information.

Table 131: GET Certificates {id} Validate Response Data

Name	Description		
Valid	A Boolean that indicates whether all the validity tests are in a passing state (true) or not (false).		
Results	An array containing the X509 certificate ch	ain validity fields. The in	cluded validity fields are:
	Name	Keyfactor Command Management Portal Equivalent	Description
	NotTimeValid	Time Valid	A value of <i>Pass</i> indicates that the certificate time value is valid. A time can appear invalid ( <i>Fail</i> ) for a certificate that has expired.
	NotTimeNested	n/a	A value of <i>Pass</i> indicates that the CA certificate and issued certificate have nested validity periods. A value of <i>Fail</i> can occur if the CA certificate expires before the issued certificate.  This is considered deprecated and may be removed in a future release.
	Revoked	Active	A value of <i>Pass</i> indicates that the X509 certificate chain is valid for the certificate and contains no revoked certificates or errors.
	NotSignatureValid	Signature	A value of <i>Fail</i> indicates that the X509 certi-

Name	Description		
	Name	Keyfactor Command Management Portal Equivalent	Description
			ficate chain is invalid as a result of an invalid certificate signature.
	NotValidForUsage	Usage	A value of <i>Fail</i> indicates that the X509 certificate chain is invalid as a result of an invalid key usage.
	UntrustedRoot	Trusted Root	A value of <i>Fail</i> indicates that the X509 certificate chain is invalid as a result of an untrusted root certificate.
	RevocationStatusUnknown	Revocation Status	A value of <i>Pass</i> indicates that the revocation status can successfully be determined for the certificate. This may be the result of successful access to online certificate revocation lists (CRLs).
	Cyclic	Chain Built	A value of <i>Pass</i> indicates that the certificate chain for the certificate could successfully be built.
	InvalidExtension	Extensions	A value of <i>Fail</i> indicates that the X509 certificate chain is invalid as a result of an invalid extension.
	InvalidPolicyConstraints	Policy Constraints	A value of <i>Fail</i> indicates

Name	Description		
	Name	Keyfactor Command Management Portal Equivalent	Description
			that the X509 certi- ficate chain is invalid as a result of an invalid policy constraint.
	InvalidBasicConstraints	Basic Constraints	A value of <i>Fail</i> indicates that the X509 certificate chain is invalid as a result of an invalid basic constraint.
	InvalidNameConstraints	Valid Name Constraints	A value of <i>Fail</i> indicates that the X509 certificate chain is invalid as a result of an invalid name constraint.
	Has Not Supported Name Constraint	Supported Name Constraints	A value of <i>Fail</i> indicates that a name constraint for the certificate is unsupported or that the certificate has no supported name constraints.
	Has Not Defined Name Constraint	Defined Name Constraints	A value of <i>Fail</i> indicates that a name constraint for the certificate is undefined.
	Has Not Permitted Name Constraint	Permitted Name Constraints	A value of <i>Fail</i> indicates that a name constraint for the certificate is impermissible.
	Has Excluded Name Constraint	Excluded Name Constraints	A value of <i>Fail</i> indicates that a name constraint for the certificate has been excluded.

Name	Description		
	Name	Keyfactor Command Management Portal Equivalent	Description
	PartialChain	Full Chain	A value of <i>Pass</i> indicates that the certificate chain for the certificate could successfully be built up to the root certificate.
	CtlNotTimeValid	CTL Time Valid	A value of <i>Fail</i> indicates that the certificate trust list (CTL) is invalid because of an invalid time value (e.g. the CTL has expired).
	CtlNotSignatureValid	CTL Signature Valid	A value of <i>Fail</i> indicates that the certificate trust list (CTL) contains an invalid signature.
	CtlNotValidForUsage	CTL Usage Valid	A value of <i>Fail</i> indicates that the certificate trust list (CTL) is not valid for this use.
	Has Weak Signature	Strong Signature	A value of <i>Pass</i> indicates that the certificate has been signed with a secure hashing algorithm. A value of <i>Fail</i> can indicate that a hashing algorithm of MD2 or MD5 was used for the certificate.
	OfflineRevocation	CRL online	A value of <i>Pass</i> indicates that the online certificate revocation list (CRL) the chain relies on is available.

Name	Description		
	Name	Keyfactor Command Management Portal Equivalent	Description
	NoIssuanceChainPolicy	Chain Policy	A value of <i>Pass</i> indicates that there is either no certificate policy by design in the certificate or that if a group policy has specified that all certificates must have a certificate policy, the certificate policy exists in the certificate.
	ExplicitDistrust	No Explicit Distrust	A value of <i>Pass</i> indicates that the certificate is not explicitly distrusted.
	HasNotSupportedCriticalExtension	Critical Extensions	A value of <i>Pass</i> indicates that the certificate has a critical extension that is supported or has no critical extensions.

### 2.2.6.3 GET Certificates Locations ID

The GET /Certificates/Locations/{id} method is used to return details for the certificate store locations in which the certificate with the specified ID is found. This method returns HTTP 200 OK on a success with certificate store location details in the message body.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: Certificates: *Read* 

Table 132: GET Certificates Locations {id} Input Parameters

Name	In	Description
id	Path	<b>Required</b> . The Keyfactor Command reference ID of the certificate for which to retrieve certificate store location details.
CollectionId	Query	An integer specifying an optional certificate collection identifier to validate that the user executing the request has sufficient permissions to do so. If a certificate collection ID is not supplied, the user must have global permissions to complete the action. Supplying a certificate collection ID allows for a check of the user's certificate collection-level permissions to determine whether the user has sufficient permissions at a collection level to complete the action. See <i>Certificate Permissions</i> in the <i>Keyfactor Command Reference Guide</i> for more information.

Table 133: GET Certificates Locations {id} Response Data

Name	Description				
Details	An array containing the certificate stores in which the certificate is found. Certificate store details include:				
	Name	Description			
	StoreType	A string indicating the type of certificate store (e.g. Java Keystore).			
	StoreTypeId	An integer indicating the Keyfactor Command referenced ID for the type of certificate store.  Use the <i>GET CertificateStoreTypes</i> method (see <u>GET Certificate Store Types on page 518</u> ) to retrieve a list of all the certificate store types to see a complete list of types.			
	StoreCount	An integer indicating the number of stores of the type referenced by StoreType in which the certificate is found.			
	Locations	An array containing details about the specific certificate stores in which the certificate is found. The following details are included about each store:			
		Name Description			
		StoreId	A GUID that identifies the certificate store in which the certificate is located.		
		StoreTypeId	An integer indicating the Keyfactor Command reference ID for the type of certificate store.		
		ClientMachine	A string containing the client machine name. The value for this will vary depending on the certificate store type. For example, for a Java keystore or an F5 device, it is the hostname of the machine on which the store is located, but for an Amazon Web Services store, it is the FQDN of the Keyfactor Command Windows Orchestrator. See the Adding or Modifying a Certificate Store section of the Keyfactor Command Reference Guide for more information.		
		StorePath	A string containing the path to the certificate store on		

Name	Description	Description			
	Name	Description	Description		
		Name	Description		
			the target. The format for this path will vary depending on the certificate store type. For example, for a Java keystore, this will be a file path (e.g. /opt/myapp/store.jks), but for an F5 device, this will be a partition name on the device (e.g. Common). See the Adding or Modifying a Certificate Store section of the Keyfactor Command Reference Guide for more information.		
		Alias	A string containing the alias of the certificate in the certificate store. The format for this path will vary depending on the certificate store type. For example, for a Java keystore, this will be a user-provided string, but for an IIS Personal store, this will be the thumbrint of the certificate. See the <a href="PFX Enrollment">PFX Enrollment</a> section of the Keyfactor Command Reference Guide for more information.		

## 2.2.6.4 GET Certificates Identity Audit ID

The GET /Certificates/IdentityAudit/{id} method is used to return a list of all the users or groups defined in the system that have permission to the certificate ID entered. This method returns HTTP 200 OK on a success with certificate identity audit details in the message body.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: Certificates: *Read* 

Table 134: GET Certificates {id} History Input Parameters

Name	In	Description
id	Path	Required. An integer containing the Keyfactor Command reference ID of the certificate.
CollectionId	Query	An integer specifying an optional certificate collection identifier to validate that the user executing the request has sufficient permissions to do so. If a certificate collection ID is not supplied, the user must have global permissions to complete the action. Supplying a certificate collection ID allows for a check of the user's certificate collection-level permissions to determine whether the user has sufficient permissions at a collection level to complete the action. See <i>Certificate Permissions</i> in the <i>Keyfactor Command Reference Guide</i> for more information.

Table 135: GET Certificates {id} History Response Data

Name	Description			
Id	An integer containing the Keyfactor ID of the user/group.			
AccountName	A string containing the name of the Keyfactor user/group.			
IdentityType	A string that specifies	s if the account is a user or a group.		
SID	A string containing th	A string containing the SID of the user/group		
Permissions	An array of the permissions for the certificate.			
	Parameter	Description		
	Name	A string containing the name of the permission (for example: Read, EditMetadata, Import, Recover, etc)		
	GrantedBy	A string containing the list of roles or collections that grant the given permission to the user-/group.		

#### 2.2.6.5 DELETE Certificates ID

The DELETE /Certificates/{id} method is used to delete an existing certificate with the specified ID from the Keyfactor Command database. If the specified certificate has an associated private key stored in the database, this

private key is also removed. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: Certificates: *Delete* 

Certificate permission can be granted at either the global or collection level. See note under CollectionId, below.



**Tip:** Deleting a certificate with this method does not necessarily delete it permanently. The certificate will be returned to the Keyfactor Command database on the next full synchronization if synchronization for the certificate source (certificate authority, SSL endpoint, etc.) is still configured. Certificate history, metadata, and private keys do not return when certificates re-synchronize. The certificate will be assigned a different Keyfactor Command reference ID when re-added to Keyfactor Command.

Table 136: DELETE Certificates {id} Input Parameters

Name	In	Description
id	Path	<b>Required</b> . The Keyfactor Command reference ID of the certificate to delete. Use the <i>GET /Certificates</i> method (see <u>GET Certificates on page 237</u> ) to retrieve a list of certificates based on entered search criteria to determine the certificate ID. This information is also available in the certificate details for a certificate in the Keyfactor Command Management Portal.
CollectionId	Query	An integer specifying an optional certificate collection identifier to validate that the user executing the request has sufficient permissions to do so. If a certificate collection ID is not supplied, the user must have global permissions to complete the action. Supplying a certificate collection ID allows for a check of the user's certificate collection-level permissions to determine whether the user has sufficient permissions at a collection level to complete the action. See <i>Certificate Permissions</i> in the <i>Keyfactor Command Reference Guide</i> for more information.

#### 2.2.6.6 GET Certificates ID

The GET /Certificates/{id} method is used to return details for the certificate with the specified ID. This method returns HTTP 200 OK on a success with certificate details in the message body.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: Certificates: *Read* 

Table 137: GET Certificates {id} Input Parameters

Name	In	Description
id	Path	Required. An integer indicating the Keyfactor Command reference ID of the certificate.  Use the GET /Certificates method (see GET Certificates on page 237) to retrieve a list of multiple certificates to determine the desired certificate's ID.
includeLocations	Query	A Boolean that sets whether to include the <i>Locations</i> data in the response (true) or not (false). If false is selected, the <i>LocationsCount</i> and <i>Locations</i> fields will still appear in the response, but they will contain no data. The default is <i>false</i> .
include Metadata	Query	A Boolean that sets whether to include the <i>Metadata</i> data in the response (true) or not (false). If false is selected, the <i>Metadata</i> field will still appear in the response, but it will contain no data. The default is <i>false</i> .
CollectionId	Query	An integer specifying an optional certificate collection identifier to validate that the user executing the request has sufficient permissions to do so. If a certificate collection ID is not supplied, the user must have global permissions to complete the action. Supplying a certificate collection ID allows for a check of the user's certificate collection-level permissions to determine whether the user has sufficient permissions at a collection level to complete the action. See <i>Certificate Permissions</i> in the <i>Keyfactor Command Reference Guide</i> for more information.

Table 138: GET Certificates {id} Response Data

Name	Description
Id	An integer indicating the Keyfactor Command reference ID of the certificate.
Thumbprint	A string indicating the thumbprint of the certificate.
SerialNumber	A string indicating the serial number of the certificate.
IssuedDN	A string indicating the distinguished name of the certificate.
IssuedCN	A string indicating the common name of the certificate.
ImportDate	The date, in UTC, on which the certificate was imported into Keyfactor Command.
NotBefore	The date, in UTC, on which the certificate was issued by the certificate authority.
NotAfter	The date, in UTC, on which the certificate expires.
IssuerDN	A string indicating the distinguished name of the issuer.
Principalld	An integer indicating the Keyfactor Command reference ID of the principal (UPN) that requested the certificate. Typically, this field is only populated for end user certificates requested through Keyfactor Command (e.g. Mac auto-enrollment certificates). See also <i>PrinicpalName</i> .
TemplateId	An integer indicating the Keyfactor Command reference ID of the template associated with the certificate.

Name	Description			
CertState	An integer specifying the state of the certificate. The possible values are:			
	Value	Description		
	0	Unknown		
	1	Active		
	2	Revoked		
	3	Denied		
	4	Failed		
	5	Pending		
	6	Certificate Authority		
	7	Parent Certificate Authority		
KeySizeInBits	An integer specifying the key size in bits.			
КеуТуре	An integer specifying the key type of the certificate. The possible values are:			
	Value	Description		
	0	Unknown		
	1	RSA		
	2	DSA		
	3	ECC		
	4	DH		
RequesterId	An integer indicating the Keyfactor Command reference ID of the identity that requested the certificate. See also <i>RequesterName</i> .			
IssuedOU	A string indicating the organizational unit of the certificate.			
IssuedEmail	A string indicating the email address of the certificate.			
KeyUsage	An integer indicating the total key usage of the certificate. Key usage is stored in Active Directory as a single value made of a combination of values. The values that make up the key usage value include:			

Name	Description			
	Value	Function	Description	
	0	None	No key usage parameters.	
	1	Encipherment Only	The key can be used for encryption only.	
	2	CRL Signing	The key can be used to sign a certificate revocation list (CRL).	
	4	Key Certificate Signing	The key can be used to sign certificates.	
	8	Key Agreement	The key can be used to determine key agreement, such as a key created using the Diffie-Hellman key agreement algorithm.	
	16	Data Encipherment	The key can be used for data encryption.	
	32	Key Encipherment	The key can be used for key encryption.	
	64	Nonrepudiation	The key can be used for authentication.	
	128	Digital Signature	The key can be used as a digital signature.	
	32768	Decipherment Only	The key can be used for decryption only.	
	For example, a value of 160 would represent a key usage of <i>digital signature</i> with <i>key encipherment</i> . A value of 224 would add <i>nonrepudiation</i> to those.			
SigningAlgorithm	A string indicati	ng the algorithm used to	o sign the certificate.	
CertStateString	A string containing the certificate state. The possible values are:  • Unknown (0)  • Active (1)  • Revoked (2)  • Denied (3)  • Failed (4)  • Pending (5)  • Certificate Authority (6)  • Parent Certificate Authority (7)  • External Validation (8)			
KeyTypeString	A string contain shown for <i>KeyT</i>		tion (e.g. RSA) as per the types and descriptions	

Name	Description			
RevocationEffDate	The date, in UTC, on which the certificate was revoked, if applicable.			
RevocationReason	An integer indicating the reason the certificate was revoked. The possible values are:			
	Value	Description		
	0	Unspecified		
	1	Key Compromised		
	2	CA Compromised		
	3	Affiliation Changed		
	4	Superseded		
	5	Cessation Of Operation		
	6	Certificate Hold		
	999	Unknown		
RevocationComment	An internally used Keyfactor Con	nmand field.		
CertificateAuthorityId	An integer indicating the Keyfactor Command reference ID of the certificate authority that issued the certificate.			
CertificateAuthorityName	A string indicating the certificate authority that issued the certificate.			
TemplateName	A string indicating the name of the template that was used when issuing the certificate.			
ArchivedKey	A Boolean that indicates whether the certificate has a key archived in the issuing CA (true) or not (false).			
HasPrivateKey	A Boolean that indicates whethe Command (true) or not (false)	r the certificate has a private key stored in Keyfactor		
PrincipalName	A string containing the name of the principal (UPN) that requested the certificate. Typically, this field is only populated for end user certificates requested through Keyfactor Command (e.g. Mac auto-enrollment certificates).			
CertRequestId	An integer containing the Keyfactor Command reference ID of the certificate request.			
RequesterName	A string containing the name of the identity that requested the certificate.			
ContentBytes	A string containing the certificate as bytes.			
ExtendedKeyUsages	An array containing the extende	d key usages associated with the certificate. Extended		

Name	Description		
	Key data includes:		
	Name	Description	
	Id	An integer containing the Keyfactor Command reference ID of the extended key usage.	
	Oid	A string indicating the OID of the extended key usage.	
	DisplayName	A string indicating the name of the extended key usage.	

Name	Description				
SubjectAltNameElements	An array containing the subject alternative name elements of the certificate. SAN data includes:				
	Name	Description			
	Id	An integer contain SAN Element.	An integer containing the Keyfactor Command reference ID of the SAN Element.		
	Value	A string indicating	A string indicating the value of the SAN Element.		
	Туре	An integer contain values are:	ing the type of SAN element. The possible		
		Value	Description		
		0	Other Name		
		1	RFC 822 Name		
		2	DNS Name		
		3	X400 Address		
		4	Directory Name		
		5	Ediparty Name		
		6	Uniform Resource Identifier		
		7	IP Address		
		8	Registered Id		
		100	MS_NTPrincipalName		
		101	MS_NTDSReplication		
		999	Unknown		
	ValueHash	A string indicating	a hash of the SAN value.		

Name	Description	Description	
CRLDistributionPoints	An array containing the distribution points for the certificate revocation lists the certificate could be in. CRL distribution point data includes:		
	Name	Description	
	Id	An integer containing the Keyfactor Command reference ID of the CRL distribution point.	
	URL	A string indicating the URL of the CRL distribution point.	
	URLHash	URLHash A string indicating a hash of the URL.	
LocationsCount	An array containing a count of how many certificates are in each location type. This returns a list of type and count combination. For example:		
	<pre>"LocationsCount": [</pre>		
SSLLocations	An array containing the locations where the certificate is found using SSL discovery. SSL location data includes:		
	Name	Description	
	StorePath	A string indicating the machine where the certificate was discovered.	
	AgentPool	A string indicating the GUID of the orchestrator pool that performed the SSL scan on the endpoint where the certificate was discovered.	
	IPAddress	A string indicating the IP address where the certificate was discovered.	
	Port	An integer indicating the port on which the certificate was discovered.	

Name	Description	
	Name	Description
	NetworkName	A string indicating the name of the SSL network that performed the SSL scan (discovery or monitoring) on the endpoint where the certificate was discovered.

Name	Description			
Locations				
	Name	Description		
	StoreMachine	A string indicating the machine on which the certificate store is located.		
	StorePath	A string indicating the path on the machine where the cer ficate store is located. The format of this will vary depends on the type of store.		
	StoreType		cating the type of certificate store the certi- l in. Possible values are:	
		Value	Description	
		0	Java Keystore	
		2	PEM File	
		3	F5 SSL Profiles	
		4	IIS Roots	
		5	NetScaler	
		6	IIS Personal	
		7	F5 Web Server	
		8	IIS Revoked	
		9	F5 Web Server REST	
		10	F5 SSL Profiles REST	
		11	F5 CA Bundles REST	
		100	Amazon Web Services	
		101	File Transfer Protocol	
		1xx	User-defined certificate stores will be given a type ID over 101.	
	Alias	A string indication store.	ing the alias of the certificate in the certificate	
	ChainLevel	An integer stating how many certificates are below this certificate in the certificate chain stored at the given location.		

Name	Description			
Metadata	An array containing the metadata fields populated for the certificate.			
CertificateKeyId	An integer indicating the Keyfactor Command reference ID for the private key, if one exists, and public key of the certificate.			
CARowIndex	An integer containing the O	CA's reference ID for certificate.		
	Note: The <i>CARowIndex</i> has been replaced by <i>CARecordId</i> , but will remain for backward compatibility. It will only contain a non-zero value for certificates issued by Microsoft CAs. For Microsoft CA certificates, the <i>CARowIndex</i> will be equal to the <i>CARecordId</i> value parsed to an integer.			
CARecordId	A string containing the CA's	s reference ID for certificate.		
DetailedKeyUsage	An array containing details of the key usage configured for the certificate. Detailed key usage data includes:			
	Name	Description		
	CrlSign	A Boolean that indicates whether CRL signing is enabled for the certificate (true) or not (false).		
	DataEncipherment	A Boolean that indicates whether data encipherment ("Allow encryption of user data" in a Microsoft template) is enabled for the certificate (true) or not (false).		
	DecipherOnly	A Boolean that indicates whether the key of the certificate is intended for decipherment only (true) or not (false).		
	DigitalSignature	A Boolean that indicates whether digital signature is enabled for the certificate (true) or not (false).		
	EncipherOnly	A Boolean that indicates whether the key of the certificate is intended for encipherment only (true) or not (false).		
	KeyAgreement	A Boolean that indicates whether the certificate is configured for key agreement.		
	KeyCertSign	A Boolean that indicates whether the certificate is configured for certificate signing.		
	KeyEncipherment	A Boolean that indicates whether the certificate is		

Name	Description		
	Name	Description	
		configured for key encipherment.	
	NonRepudiation	A Boolean that indicates whether the certificate is configured for non-repudiation.	
	HexCode	A string containing the hexadecimal code representing the total key usage. For example, a value of a0 would indicate digital signature with key encipherment.	
KeyRecoverable	A Boolean that indicates whether the certificate key is recoverable (true) or not (false).		
Curve	A string indicating the OID of the elliptic curve algorithm configured for the certificate, for ECC templates. Well-known OIDs include:  • 1.2.840.10045.3.1.7 = P-256/prime256v1/secp256r1  • 1.3.132.0.34 = P-384/secp384r1  • 1.3.132.0.35 = P-521/secp521r1		

# 2.2.6.7 GET Certificates Metadata Compare

The GET /Certificates/Metadata/Compare method is used to compare the value of a metadata field in a certificate stored in Keyfactor Command with a provided value. This can be used to prevent exposing sensitive data while still providing functionality. For example, with this method, a metadata attribute can be used along with the certificate itself as a second authentication factor to a third-party application. This method returns HTTP 200 OK on a success with a response of *true* if the compared values match or *false* if they do not.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: Certificates: *Read* 

Table 139: GET Certificates Metadata Compare Input Parameters

Name	In	Description
certificateId	Query	<b>Required</b> . An integer containing the Keyfactor Command reference ID of the certificate containing the metadata value to be compared.
metadataFieldName	Query	<b>Required</b> . A string containing the name of the metadata field whose value should be compared.
value	Query	Required. A string containing the value for comparison.
collectionId	Query	An integer specifying an optional certificate collection identifier to validate that the user executing the request has sufficient permissions to do so. If a certificate collection ID is not supplied, the user must have global permissions to complete the action. Supplying a certificate collection ID allows for a check of the user's certificate collection-level permissions to determine whether the user has sufficient permissions at a collection level to complete the action. See <i>Certificate Permissions</i> in the <i>Keyfactor Command Reference Guide</i> for more information.

# 2.2.6.8 GET Certificates ID History

The GET /Certificates/{id}/History method is used to return details for the history of transactions for a certificate with the specified ID. History records are stored for a certificate for a variety of activities including initial import or enrollment, revocation, key recovery, additions or removals from certificate stores, renewals, and certificate discoveries in various certificate stores. For more information about certificate history records, see the <a href="Methodology: Certificate">Certificate</a> <a href="Details">Details</a> section of the \*Keyfactor Command \*Reference Guide. This method returns HTTP 200 OK on a success with certificate history details in the message body.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: Certificates: *Read* 

Table 140: GET Certificates {id} History Input Parameters

Name	In	Description
id	Path	<b>Required</b> . An integer containing the Keyfactor Command reference ID of the certificate.
CollectionId	Query	An integer specifying an optional certificate collection identifier to validate that the user executing the request has sufficient permissions to do so. If a certificate collection ID is not supplied, the user must have global permissions to complete the action. Supplying a certificate collection ID allows for a check of the user's certificate collection-level permissions to determine whether the user has sufficient permissions at a collection level to complete the action. See <i>Certificate Permissions</i> in the <i>Keyfactor Command Reference Guide</i> for more information.
query.pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.
query.returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.
query.sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <code>OperationStart</code> .
query.sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.

Table 141: GET Certificates {id} History Response Data

Name	Description
Id	An integer containing the Keyfactor Command reference ID of the certificate.
OperationStart	The date, in UTC, on which the operation begin.
OperationEnd	The date, in UTC, on which the operation completed.
Username	The name of the user who initiated the transaction that created the history record (e.g. enrolled for the certificate, revoked the certificate), in DOMAIN\\username format.
Comment	A string containing a comment that provides more information about the history record. For example (for a metadata field):  AppOwnerEmailAddress has been updated from 'john.smith@keyexample.com' to 'martha.jones@keyexample.com'
Action	A string naming the action that was taken. For example:  Metadata Update

## 2.2.6.9 DELETE Certificates

The DELETE /Certificates method is used to delete multiple certificates from the Keyfactor Command database in one request. The certificate IDs should be supplied in the request body as a JSON array of integers. If the specified certificate(s) have associated private key(s) stored in the database, these private keys are also removed. This endpoint returns 204 with no content upon success. IDs of any certificates that could not be deleted are returned in the response body. Delete operations will continue until the entire array of IDs has been processed.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: Certificates: *Delete* 

Certificate permission can be granted at either the global or collection level. See note under CollectionId, below.



**Tip:** Deleting a certificate with this method does not necessarily delete it permanently. The certificate will be returned to the Keyfactor Command database on the next full synchronization if synchronization for the certificate source (certificate authority, SSL endpoint, etc.) is still configured. Certificate history, metadata, and private keys do not return when certificates re-synchronize. The certificate will be assigned a different Keyfactor Command reference ID when re-added to Keyfactor Command.

Table 142: DELETE Certificates Input Parameters

Name	In	Description
ids	Body	Required. Array of Keyfactor Command certificate IDs for certificates that should be deleted in the form:  [123,789,567]
CollectionId	Query	An integer specifying an optional certificate collection identifier to validate that the user executing the request has sufficient permissions to do so. If a certificate collection ID is not supplied, the user must have global permissions to complete the action. Supplying a certificate collection ID allows for a check of the user's certificate collection-level permissions to determine whether the user has sufficient permissions at a collection level to complete the action. See <i>Certificate Permissions</i> in the <i>Keyfactor Command Reference Guide</i> for more information.

## 2.2.6.10 GET Certificates

The GET /Certificates method is used to return a list of certificates with certificate details. Results can be limited to selected keys using filtering, and URL parameters can be used to specify paging and the level of information detail. This method returns HTTP 200 OK on a success with the requested certificates, as determined by filtering, and their certificate details.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: Certificates: *Read* 

Table 143: GET Certificates Input Parameters

Name	In	Description
includeLocations	Quer- y	A Boolean that sets whether to include the <i>Locations</i> data in the response (true) or not (false). If false is selected, the <i>LocationsCount</i> and <i>Locations</i> fields will still appear in the response, but they will contain no data. The default is <i>false</i> .
includeMetadat- a	Quer- y	A Boolean that sets whether to include the <i>Metadata</i> data in the response (true) or not (false). If false is selected, the <i>Metadata</i> field will still appear in the response, but it will contain no data. The default is <i>false</i> .
includeHasPriv- ateKey	Quer- y	A Boolean that sets whether to include the correct value for <code>HasPrivateKey</code> in the response (true) or not (false). If false is selected, the <code>HasPrivateKey</code> field will appear in the response with a value of <code>false</code> regardless of whether the certificate actually has a stored private key or not. The default is <code>false</code> .
CollectionId	Quer- y	An integer specifying an optional certificate collection identifier to validate that the user executing the request has sufficient permissions to do so. If a certificate collection ID is not supplied, the user must have global permissions to complete the action. Supplying a certificate collection ID allows for a check of the user's certificate collection-level permissions to determine whether the user has sufficient permissions at a collection level to complete the action. See <i>Certificate Permissions</i> in the <i>Keyfactor Command Reference Guide</i> for more information.
includeRevoked	Quer- y	A Boolean that sets whether to include revoked certificates in the results (true) or not (false). The default is <i>false</i> .
includeExpired	Quer- y	A Boolean that sets whether to include expired certificates in the results (true) or not (false). The default is <i>false</i> .

Name	In	Description			
queryString	Quer- y				
		ArchivedKey	• EKU	• OU	• Sign- ingAlgorithm
		• CertId	• EKUNam- e	<ul> <li>NetBIOSPrin- cipal (alias: Prin- cipalName)</li> </ul>	• SSLDNSName
		• <i>CA</i>	<ul> <li>HasPriv- ateKey</li> </ul>	• PublicKey	<ul> <li>SSLIPAddress         <ul> <li>(alias:</li> <li>SsIHostName)</li> </ul> </li> </ul>
		• CertState	• ImportD- ate	<ul> <li>NetBIOSReq- uester (alias: Requester- Name)</li> </ul>	• SSLNet- workName
		<ul> <li>CertStoreFQ- DN (alias: JavaKey- storeFQDN)</li> </ul>	<ul> <li>IssuedDa- te         <ul> <li>(aliases:</li> <li>NotBe- fore and</li> <li>Effect- iveDate)</li> </ul> </li> </ul>	<ul> <li>Revoc- ationDate (alias: Revoc- ationEffDate</li> <li>)</li> </ul>	• SSLPort
		<ul> <li>CertStorePa- th (alias: JavaKey- storePath)</li> </ul>	• IssuerDN	• Revoker	• SAN
		• CN (alias: IssuedCN)	<ul><li>KeySize (alias: KeyS- izeInBits)</li></ul>	• RFC2818Co- mpliant	<ul> <li>TemplateDis- playName (alias: TemplateNam- e)</li> </ul>
		• DN (alias: IssuedDN)	• КеуТуре	<ul> <li>SelfSigned</li> </ul>	<ul> <li>TemplateShort- Name</li> </ul>
		<ul> <li>Expir- ationDate (alias: NotAfter)</li> </ul>	• KeyUsag- e	• Seri- alNumber	• Thumbprint
		The following fields have CARequestID  • CertRequestId	ve been deprecated	and will be ignored if i	ncluded in a request:
		• IsPfx			

Name	In	Description
pageReturned	Quer- y	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.
returnLimit	Quer- y	An integer that specifies how many results to return per page. The default is 50.
sortField	Quer- y	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>Id</i> .
sortAscending	Quer- y	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.

Table 144: GET Certificates Response Data

Name	Description
Id	An integer indicating the Keyfactor Command reference ID of the certificate.
Thumbprint	A string indicating the thumbprint of the certificate.
SerialNumber	A string indicating the serial number of the certificate.
IssuedDN	A string indicating the distinguished name of the certificate.
IssuedCN	A string indicating the common name of the certificate.
ImportDate	The date, in UTC, on which the certificate was imported into Keyfactor Command.
NotBefore	The date, in UTC, on which the certificate was issued by the certificate authority.
NotAfter	The date, in UTC, on which the certificate expires.
IssuerDN	A string indicating the distinguished name of the issuer.
Principalld	An integer indicating the Keyfactor Command reference ID of the principal (UPN) that requested the certificate. Typically, this field is only populated for end user certificates requested through Keyfactor Command (e.g. Mac auto-enrollment certificates). See also <i>PrinicpalName</i> .
TemplateId	An integer indicating the Keyfactor Command reference ID of the template associated with the certificate.

Name	Description		
CertState	An integer specifying the state of the certificate. The possible values are:		
	Value	Description	
	0	Unknown	
	1	Active	
	2	Revoked	
	3	Denied	
	4	Failed	
	5	Pending	
	6	Certificate Authority	
	7	Parent Certificate Authority	
KeySizeInBits	An integer specifying the key size in bits.		
КеуТуре	An integer specifying the key type of the certificate. The possible values are:		
	Value	Description	
	0	Unknown	
	1	RSA	
	2	DSA	
	3	ECC	
	4	DH	
RequesterId	An integer indicating the Keyfactor Command reference ID of the identity that requested the certificate. See also <i>RequesterName</i> .		
IssuedOU	A string indicating the organizational unit of the certificate.		
IssuedEmail	A string indicating the email address of the certificate.		
KeyUsage	An integer indicating the total key usage of the certificate. Key usage is stored in Active Directory as a single value made of a combination of values. The values that make up the key usage value include:		

Name	Description			
	Value	Function	Description	
	0	None	No key usage parameters.	
	1	Encipherment Only	The key can be used for encryption only.	
	2	CRL Signing	The key can be used to sign a certificate revocation list (CRL).	
	4	Key Certificate Signing	The key can be used to sign certificates.	
	8	Key Agreement	The key can be used to determine key agreement, such as a key created using the Diffie-Hellman key agreement algorithm.	
	16	Data Encipherment	The key can be used for data encryption.	
	32	Key Encipherment	The key can be used for key encryption.	
	64	Nonrepudiation	The key can be used for authentication.	
	128	Digital Signature	The key can be used as a digital signature.	
	32768	Decipherment Only	The key can be used for decryption only.	
	For example, a value of 160 would represent a key usage of <i>digital signature</i> with <i>key encipherment</i> . A value of 224 would add <i>nonrepudiation</i> to those.			
SigningAlgorithm	A string indicati	ng the algorithm used to	o sign the certificate.	
CertStateString	A string containing the certificate state. The possible values are:  • Unknown (0)  • Active (1)  • Revoked (2)  • Denied (3)  • Failed (4)  • Pending (5)  • Certificate Authority (6)  • Parent Certificate Authority (7)  • External Validation (8)			
KeyTypeString	A string contain shown for <i>KeyT</i>		tion (e.g. RSA) as per the types and descriptions	

Name	Description		
RevocationEffDate	The date, in UTC, on which the certificate was revoked, if applicable.		
RevocationReason	An integer indicating the reason the certificate was revoked. The possible values are:		
	Value	Description	
	0	Unspecified	
	1	Key Compromised	
	2	CA Compromised	
	3	Affiliation Changed	
	4	Superseded	
	5	Cessation Of Operation	
	6	Certificate Hold	
	999	Unknown	
RevocationComment	An internally used Keyfactor Command field.		
CertificateAuthorityId	An integer indicating the Keyfactor Command reference ID of the certificate authority that issued the certificate.		
CertificateAuthorityName	A string indicating the certificate authority that issued the certificate.		
TemplateName	A string indicating the name of the template that was used when issuing the certificate.		
ArchivedKey	A Boolean that indicates whether the certificate has a key archived in the issuing CA (true) or not (false).		
HasPrivateKey	A Boolean that indicates whether the certificate has a private key stored in Keyfactor Command (true) or not (false)		
PrincipalName	A string containing the name of the principal (UPN) that requested the certificate. Typically, this field is only populated for end user certificates requested through Keyfactor Command (e.g. Mac auto-enrollment certificates).		
CertRequestId	An integer containing the Keyfactor Command reference ID of the certificate request.		
RequesterName	A string containing the name of the identity that requested the certificate.		
ContentBytes	A string containing the certificate as bytes.		
ExtendedKeyUsages	An array containing the extende	d key usages associated with the certificate. Extended	

Name	Description	
	Key data includes:	
	Name	Description
	Id	An integer containing the Keyfactor Command reference ID of the extended key usage.
	Oid	A string indicating the OID of the extended key usage.
	DisplayName	A string indicating the name of the extended key usage.

Name	Description				
SubjectAltNameElements	An array contai includes:	An array containing the subject alternative name elements of the certificate. SAN data includes:			
	Name	Description			
	Id	An integer contain SAN Element.	An integer containing the Keyfactor Command reference ID of the SAN Element.		
	Value	A string indicating	A string indicating the value of the SAN Element.		
	Туре	An integer contain values are:	ning the type of SAN element. The possible		
		Value	Description		
		0	Other Name		
		1	RFC 822 Name		
		2	DNS Name		
		3	X400 Address		
		4	Directory Name		
		5	Ediparty Name		
		6	Uniform Resource Identifier		
		7	IP Address		
		8	Registered Id		
		100	MS_NTPrincipalName		
		101	MS_NTDSReplication		
		999	Unknown		
	ValueHash	A string indicating	g a hash of the SAN value.		

Name	Description		
CRLDistributionPoints	An array containing the distribution points for the certificate revocation lists the certificate could be in. CRL distribution point data includes:		
	Name D	Description	
		n integer containing the Keyfactor Command reference ID of the RL distribution point.	
	URL A	string indicating the URL of the CRL distribution point.	
	URLHash A	string indicating a hash of the URL.	
LocationsCount		count of how many certificates are in each location type. This and count combination. For example:	
	<pre>"LocationsCount": [</pre>		
SSLLocations	An array containing t	he locations where the certificate is found using SSL discovery. SSL s:	
	Name	Description	
	StorePath	A string indicating the machine where the certificate was discovered.	
	AgentPool	A string indicating the GUID of the orchestrator pool that performed the SSL scan on the endpoint where the certificate was discovered.	
	IPAddress	A string indicating the IP address where the certificate was discovered.	
	Port	An integer indicating the port on which the certificate was discovered.	

Name	Description		
	Name	Description	
	NetworkName	A string indicating the name of the SSL network that performed the SSL scan (discovery or monitoring) on the endpoint where the certificate was discovered.	

Name	Description		
Locations			
	Name	Description	
	StoreMachine	A string indicating the machine on which the certificate stollocated.	
	StorePath	A string indicating the path on the machine where the certificate store is located. The format of this will vary depending on the type of store.	
	StoreType		cating the type of certificate store the certi- d in. Possible values are:
		Value	Description
		0	Java Keystore
		2	PEM File
		3	F5 SSL Profiles
		4	IIS Roots
		5	NetScaler
		6	IIS Personal
		7	F5 Web Server
		8	IIS Revoked
		9	F5 Web Server REST
		10	F5 SSL Profiles REST
		11	F5 CA Bundles REST
		100	Amazon Web Services
		101	File Transfer Protocol
		1xx	User-defined certificate stores will be given a type ID over 101.
	Alias	A string indication store.	ing the alias of the certificate in the certificate
	ChainLevel		ing how many certificates are below this certi- rtificate chain stored at the given location.

Name	Description				
Metadata	An array containing the metadata fields populated for the certificate.				
CertificateKeyId	An integer indicating the Keyfactor Command reference ID for the private key, if one exists, and public key of the certificate.				
CARowIndex	An integer containing the O	An integer containing the CA's reference ID for certificate.			
	backward compati	index has been replaced by CARecordId, but will remain for bility. It will only contain a non-zero value for certificates t CAs. For Microsoft CA certificates, the CARowIndex will be cordId value parsed to an integer.			
CARecordId	A string containing the CA's	s reference ID for certificate.			
DetailedKeyUsage	An array containing details of the key usage configured for the certificate. Detailed key usage data includes:				
	Name	Description			
	CrlSign	A Boolean that indicates whether CRL signing is enabled for the certificate (true) or not (false).			
	DataEncipherment	A Boolean that indicates whether data encipherment ("Allow encryption of user data" in a Microsoft template) is enabled for the certificate (true) or not (false).			
	DecipherOnly	A Boolean that indicates whether the key of the certificate is intended for decipherment only (true) or not (false).			
	DigitalSignature	A Boolean that indicates whether digital signature is enabled for the certificate (true) or not (false).			
	EncipherOnly	A Boolean that indicates whether the key of the certificate is intended for encipherment only (true) or not (false).			
	KeyAgreement	A Boolean that indicates whether the certificate is configured for key agreement.			
	KeyCertSign	A Boolean that indicates whether the certificate is configured for certificate signing.			
	KeyEncipherment A Boolean that indicates whether the certificate is				

Name	Description			
	Name	Description		
		configured for key encipherment.		
	NonRepudiation	A Boolean that indicates whether the certificate is configured for non-repudiation.		
	HexCode	A string containing the hexadecimal code representing the total key usage. For example, a value of a0 would indicate digital signature with key encipherment.		
KeyRecoverable	A Boolean that indicates w	hether the certificate key is recoverable (true) or not (false).		
Curve	A string indicating the OID of the elliptic curve algorithm configured for the certificate, for ECC templates. Well-known OIDs include:  • 1.2.840.10045.3.1.7 = P-256/prime256v1/secp256r1  • 1.3.132.0.34 = P-384/secp384r1  • 1.3.132.0.35 = P-521/secp521r1			

## 2.2.6.11 PUT Certificates Metadata

The PUT /Certificates/Metadata method is used to update one or more metadata values for a specified certificate. Any existing values for the metadata fields submitted with this update will be overwritten with the new values provided. For more granular control over updating only metadata fields that do not already contain a value, use the PUT /Certificates/Metadata/All method (see PUT Certificates Metadata All on the next page). This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: Certificates: *EditMetadata* 

Table 145: PUT Certificates Metadata Input Parameters

Name	In	Description
Id	Body	<b>Required</b> . An integer specifying the Keyfactor Command reference ID for the certificate to update.
Metadata	Body	<b>Required</b> . An array containing one or more metadata key value pairs to update for the certificate. These are submitted with the metadata field name in the key and the value in the value. For example:

Name	In	Description
		<pre>"Metadata": {     "AppOwnerEmailAddress":"john.smith@keyexample.com",</pre>
CollectionId	Query	An integer specifying an optional certificate collection identifier to validate that the user executing the request has sufficient permissions to do so. If a certificate collection ID is not supplied, the user must have global permissions to complete the action. Supplying a certificate collection ID allows for a check of the user's certificate collection-level permissions to determine whether the user has sufficient permissions at a collection level to complete the action. See <i>Certificate Permissions</i> in the <i>Keyfactor Command Reference Guide</i> for more information.

# 2.2.6.12 PUT Certificates Metadata All

The PUT /Certificates/Metadata/All method is used to update one or more metadata values for a specified set of active certificates. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: Certificates: *EditMetadata* 

Table 146: PUT Certificates Metadata All Input Parameters

Name	In	Description
Query	Body	<b>Required</b> *. A string containing a query to limit the certificates to update (e.g. field1 -eq value1 AND field2 -gt value2). Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns. For querying guidelines, refer to the <i>Keyfactor Command Reference Guide</i> Certificate Search Page section. A value for one of <i>CertificateIds</i> , <i>Query</i> , or <i>CollectionId</i> is <b>required</b> .
		The query fields supported for this endpoint are:
		• ArchivedKey • EKU • OU • Sign-

Name	In	Description
		ingAlgorithm  • CertId  • EKUName  • NetBIOSPrin-  • SSLDNSName  cipal (alias:  Prin-
		cipalName)  • CA  • HasPriv- • PublicKey • SSLIPAddress ateKey (alias: SslHostName)
		<ul> <li>CertState</li> <li>ImportDa-</li> <li>NetBIOSRequ-</li> <li>SSLNet-</li> <li>ester (alias: workName</li> <li>Requester-</li> <li>Name)</li> </ul>
		<ul> <li>CertStoreFQD-</li> <li>IssuedDat-</li> <li>Revoc-</li> <li>SSLPort</li> <li>N (alias:</li> <li>e (aliases:</li> <li>ationDate</li> <li>JavaKey-</li> <li>NotBefore</li> <li>(alias: Revoc-</li> <li>storeFQDN)</li> <li>and Effect-</li> <li>iveDate)</li> </ul>
		<ul> <li>CertStorePat-</li> <li>IssuerDN</li> <li>Revoker</li> <li>SAN</li> <li>h (alias:</li> <li>JavaKey-</li> <li>storePath)</li> </ul>
		<ul> <li>CN (alias:</li> <li>KeySize</li> <li>RFC2818Com-</li> <li>IssuedCN)</li> <li>(alias:</li> <li>pliant</li> <li>playName (alias:</li> <li>TemplateName)</li> <li>izeInBits)</li> </ul>
		<ul> <li>DN (alias:</li> <li>KeyType</li> <li>SelfSigned</li> <li>TemplateShortN- ame</li> </ul>
		<ul> <li>Expir-         <ul> <li>KeyUsage</li> <li>SerialNumber</li> <li>Thumbprint</li> </ul> </li> <li>ationDate         <ul> <li>(alias:</li> </ul> </li> <li>NotAfter)</li> </ul>
		The following fields have been deprecated and will be ignored if included in a request:  • CARequestID
		<ul> <li>CertRequestId</li> <li>IsPfx</li> <li>RequestResolutionDate</li> </ul>
		Note: Queries may be done using either the primary field name or the field alias(es).
		Tip: To exclude revoked certificates from the update, include a query of:  CertState -ne \"2\"  To exclude expired certificates from the update, include a query of:

Name	In	Description		
		<pre>ExpirationDate -ge \"%TODAY%\"</pre>		
Certi- ficateIds	Body	<b>Required</b> *. An array of Keyfactor Command certificate IDs to update. A value for one of <i>CertificateIds</i> , <i>Query</i> , or <i>CollectionId</i> is <b>required</b> .		
Metadata	Body	<b>Required</b> . An array containing information about the metadata field(s) to update. The parameters are:		
		Name Description		
		Value Required. The value that should be set for the metadata field.		
		MetadataName Required. The name of the metadata field that should be updated for the certificates.		
		OverwriteExisting  A Boolean that sets whether all the certificates being updated will have their metadata field overwritten to the value being provided, including those that already have a value in the given metadata field (true) or whether only the certificates that currently have no value in the given metadata field will be saved with the new value (false). The default is false.		
		For example:		
		<pre>"Metadata": [</pre>		

Name	In	Description		
		<pre>{     "MetadataName": "BusinessUnit", // This is a Multiple Choice field.     "Value": "E-Business", // This is a value pre-defined for the field.     "OverwriteExisting": true }, {     "MetadataName": "TicketResolutionDate", // This is a Date field in yyyy-mm-dd format.     "Value": "2021-07-23",     "OverwriteExisting": true } </pre>		
Collec- tionId	Query	Required*. An integer specifying an optional certificate collection identifier to validate that the user executing the request has sufficient permissions to do so. If a certificate collection ID is not supplied, the user must have global permissions to complete the action. Supplying a certificate collection ID allows for a check of the user's certificate collection-level permissions to determine whether the user has sufficient permissions at a collection level to complete the action. See <i>Certificate Permissions</i> in the <i>Keyfactor Command Reference Guide</i> for more information.  This field can also be used to specify the certificate collection containing certificates that should be updated. A value for one of <i>CertificateIds</i> , <i>Query</i> , or <i>CollectionId</i> is <b>required</b> .		

# 2.2.6.13 POST Certificates Import

The POST /Certificates/Import method is used to import a certificate provided in the request body into Keyfactor Command. This method returns HTTP 200 OK on a success with a message body containing information about the import.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: Certificates: *Import* 

Table 147: POST Certificates Import Input Parameters

Name	In	Description	
Certificate	Body	<b>Required</b> . The base-64 encoded contents of the certificate that is to be imported into Keyfactor Command.	
Password	Body	<b>Required</b> *. The password used to decrypt the imported PFX. This field is <b>required</b> if a PFX certificate is provided in the <i>Certificate</i> field.	
Metadata	Body	A list of certificate metadata that will be associated with the certificate once it is imported. This is provided as a set of key value pairs with the metadata field name in the key and the value in the value. For example:	
		<pre>"Metadata": {     "AppOwnerFirstName": "John",     "AppOwnerLastName": "Smith" }</pre>	
Storelds	Body	A list of the certificate store GUIDs that the imported certificate will be installed into.	

Name	In	Description			
StoreTypes	Body				
		Name	Name Description		
		StoreTypeId		tore type being used. There must be one for each D used. The possible values are:	
			Value	Description	
			0	Java Keystore	
			2	PEM File	
			3	F5 SSL Profiles	
			4	IIS Roots	
			5	NetScaler	
			6	IIS Personal	
			7	F5 Web Server	
			8	IIS Revoked	
			9	F5 Web Server REST	
			10	F5 SSL Profiles REST	
			11	F5 CA Bundles REST	
			100	Amazon Web Services	
			101	File Transfer Protocol	
		Alias	1xx	User-defined certificate stores will be given a type ID over 101.	
			upon entry int varies depend F5 device, it se device file syst file named My keystore assoc types don't rec section of the	tring providing an alias to be used for the certificate of the certificate store. The function of the alias ing on the certificate store type. For example, for an erves as the file name used to store the file in the em, minus the extension (e.g. use alias MyFile for a File.pfx) while for a Java keystore, it is stored in the ciated with the certificate. Some certificate store quire an alias and some do. See the Add Certificate Keyfactor Command Reference Guide for more this field may be required depending on the store	
		Overwrite	A Boolean tha	t sets whether a certificate in the store with the Alic	
EŸFACTO	R	10.1 Keyfac	(true) or not (f Use the <i>GET Co</i> ficates Location	lerice อุเศษษาitten with the certificate being importeralse).  ertificates/Locations/{id} method (see GET Certins ID on page 216) to retrieve a list of the locations tificate is in to determine the alias used for the cert	

Name	In	Description
Schedule	Body	The time the imported certificate should be scheduled to be installed into the certificate store. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).

Table 148: POST Certificates Import Response Data

Name	Description		
ImportStatus	The status of the import job indicating, for example, whether the certificate was newly created in Keyfactor Command or already existed in Keyfactor Command and was just updated based on provided private key, metadata, or location information.		
InvaildKeyStores	Which key store items fa	iled with some information. Included parameters are:	
	Name	Description	
	KeystoreId	The ID of the store that failed.	
	ClientMachine	The client machine of the store that failed.	
	StorePath	The path to the location of the certificate store that failed.	
	Alias	The alias for the certificate in the store that failed.	
	Reason	The simple reason why it failed.	
	Explanation	A more specific reason for the failure.	
JobStatus	The state of all certificate store jobs.		

## 2.2.6.14 POST Certificates Revoke

The POST /Certificates/Revoke method is used to revoke one or more certificates with the specified ID(s). This method returns HTTP 200 OK on a success with



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: Certificates: *Revoke* 



**Note:** As of Keyfactor Command version 10, enrollment (PFX and CSR), renewal, and revocation requests all flow through Keyfactor Command workflow. This will result in no changes to the enrollment, renewal, and revocation user experience unless customizations have been added in workflow (see <a href="Workflow Definitions">Workflow Definitions</a>).

Table 149: POST Certificates Revoke Input Parameters

Name	In	Description		
CertificateIDs	Body		rray containing the list of Keyfactor Command reference IDs for certi- ould be revoked.	
Reason	Body	An integer cont values are:	taining the specific reason that the certificate is being revoked. Available	
		Value	Description	
		-1	Remove from Hold	
		0	Unspecified	
		1	Key Compromised	
		2	CA Compromised	
		3	Affiliation Changed	
		4	Superseded	
		5	Cessation of Operation	
		6	Certificate Hold	
		7	Remove from CRL. Only valid in the case that a cert is already on a CRL in a manner that it can be removed, such as Certificate Hold	
		The default is <i>L</i>	Inspecified.	
Comment	Body	<b>Required</b> . A str being revoked.	ing containing a freeform reason or comment on why the certificate is	
EffectiveDate	Body	given using the	me when the certificate will be revoked. The date and time should be ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-The default is the current date and time.	
CollectionId	Body	executing the r	cifying an optional certificate collection identifier to validate that the user equest has sufficient permissions to do so. If a certificate collection ID is ne user must have global permissions to complete the action. Supplying a	

Name	In	Description
		certificate collection ID allows for a check of the user's certificate collection-level permissions to determine whether the user has sufficient permissions at a collection level to complete the action. See <i>Certificate Permissions</i> in the <i>Keyfactor Command Reference Guide</i> for more information.

# 2.2.6.15 POST Certificates Analyze

The POST /Certificates/Analyze method is used to parse a raw binary certificate returned from a CA into human-readable list of certificate details. This method returns HTTP 200 OK on a success with a list of the contents of the certificate.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: Certificates: *Read* 

Table 150: POST Certificates Analyze Input Parameters

Name	In	Description
Certificate	Body	<b>Required</b> . The base-64 encoded PEM string of the certificate, <b>not</b> including the header and footer (e.gBEGIN CERTIFICATE andEND CERTIFICATE).
Password	Body	The password used to encrypt the private key of the certificate for a base-64 encoded PEM containing the certificate's private key (BEGIN ENCRYPTED PRIVATE KEY).

Table 151: POST Certificates Analyze Response Data

Name	Description
IssuedDN	A string containing the distinguished name of the certificate.
IssuerDN	A string containing the distinguished name of the issuer.
Thumbprint	A string containing the thumbprint of the certificate.
NotAfter	The date/time, in UTC, on which the certificate expires.
NotBefore	The date/time, in UTC, on which the certificate was issued by the certificate authority.
Metadata	An array containing the metadata fields populated for the certificate.
IsEndEntity	A boolean flag is marked true if the certificate is the end entity of the chain.

#### 2.2.6.16 POST Certificates Recover

The POST /Certificates/Recover method is used to recover or download a certificate with private key. For certificates that are available for key recovery from the Microsoft CA, the certificate is recovered from the CA. For certificates with a private key stored in Keyfactor Command, the certificate is downloaded from Keyfactor Command. This method returns HTTP 200 OK on a success with a base-64-encoded representation of the certificate and private key, including optional certificate chain, in PEM or PFX format. For certificates without private keys in DER, PEM or P7B format, use the *POST* /Certificates/Download method (see POST Certificates Download on page 263).



**Tip:** CA-level key recovery is supported for Microsoft CAs to allow recovery of private keys for certificates enrolled outside of Keyfactor Command. CA-level key archiving is not supported for enrollments done through Keyfactor Command. CA-level key recovery is not supported for EJBCA CAs. For enrollments done through Keyfactor Command for either Microsoft or EJBCA CAs, use Keyfactor Command private key retention (see Details Tab).



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: Certificates: *Recover* 

Table 152: POST Certificates Recover Input Parameters

Name	In	Description
Password	Body	Required. The password to set on the certificate.
CertID	Body	Required*. The Keyfactor Command reference ID of the certificate to retrieve.  One of the following is required:  • CertID  • Thumbprint  • SerialNumber and IssuerDN
SerialNumber	Body	Required*. The serial number of the certificate to retrieve.  One of the following is required:  • CertID  • Thumbprint  • SerialNumber and IssuerDN
IssuerDN	Body	Required*. The distinguished name of the issuer of the certificate to retrieve.  One of the following is required:  • CertID  • Thumbprint  • SerialNumber and IssuerDN
Thumbprint	Body	Required*. The thumbprint of the certificate to retrieve.  One of the following is required:  • CertID  • Thumbprint  • SerialNumber and IssuerDN
IncludeChain	Body	A Boolean indicating whether to include the certificate chain with the certificate (true) or not (false). If you select <i>true</i> , you must select a certificate format of PEM or P7B.
CollectionId	Query	An integer specifying an optional certificate collection identifier to validate that the user executing the request has sufficient permissions to do so. If a certificate collection ID is not supplied, the user must have global permissions to complete the action. Supplying a certificate collection ID allows for a check of the user's certificate collection-level permissions to determine whether the user has sufficient permissions at a collection level to complete the action. See <i>Certificate Permissions</i> in the <i>Keyfactor Command Reference Guide</i> for more information.
x-certificateformat	Header	The desired output format for the certificate. Supported options are:  • PEM  • PFX

Table 153: POST Certificates Recover Response Data

Name	Description			
PFX	The base-64-encoded representation of the certificate in PEM or PFX format with the optional certificate chain. The string will need to be base-64 decoded for both PEM and PFX. This can be accomplished in a number of ways. For example, using PowerShell and a manually generated file containing just the base-64 string returned in the response (not the full response):			
	<pre>\$b64 = Get-Content 'C:\path\to\source\file' \$targetFile = 'C:\path\to\target\file'</pre>			
	<pre>\$bytes = [Convert]::FromBase64String(\$b64) [IO.File]::WriteAllBytes(\$targetFile, \$bytes) Using PowerShell within the script where the full response (including two key/value pairs) is returned and</pre>			
	<pre>placed in the variable \$response:  \$ResponseContent = \$response.Content   ConvertFrom-Json</pre>			
	<pre>\$targetFile = 'C:\path_to_target_file\'+\$ResponseContent.FileName</pre>			
	<pre>\$bytes = [Convert]::FromBase64String(\$ResponseContent.PFX) [IO.File]::WriteAllBytes(\$targetFile, \$bytes) In the second case, the name provided in FileName is used for the PFX output file.</pre>			
FileName	The CN of the certificate presented as a file name (e.g. mycertificatekeyexamplecom.pfx).			

## 2.2.6.17 POST Certificates Download

The POST /Certificates/Download method is used to download a certificate from Keyfactor Command. This method returns HTTP 200 OK on a success with the base-64-encoded certificate without private key, including optional certificate chain, in DER, PEM of P7B format. For certificates with private keys in PEM or PFX format, use the *POST /Certificates/Recover* method (see <u>POST Certificates Recover on page 261</u>).



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: Certificates: *Recover* 

Table 154: POST Certificates Download Input Parameters

Name	In	Description	
CertID	Body	Required*. The Keyfactor Command reference ID of the certificate to retrieve.  One of the following is required:  • CertID  • Thumbprint  • SerialNumber and IssuerDN	
SerialNumber	Body	Required*. The serial number of the certificate to retrieve.  One of the following is required:  • CertID  • Thumbprint  • SerialNumber and IssuerDN	
IssuerDN	Body	Required*. The distinguished name of the issuer of the certificate to retrieve.  One of the following is required:  • CertID  • Thumbprint  • SerialNumber and IssuerDN	
Thumbprint	Body	Required*. The thumbprint of the certificate to retrieve.  One of the following is required:  • CertID  • Thumbprint  • SerialNumber and IssuerDN	
IncludeChain	Body	A Boolean indicating whether to include the certificate chain with the certificate (true) or not (false). If you select <i>true</i> , you must select a certificate format of PEM or P7B.	
CollectionId	Query	An integer specifying an optional certificate collection identifier to validate that the user executing the request has sufficient permissions to do so. If a certificate collection ID is not supplied, the user must have global permissions to complete the action. Supplying a certificate collection ID allows for a check of the user's certificate collection-level permissions to determine whether the user has sufficient permissions at a collection level to complete the action. See <i>Certificate Permissions</i> in the <i>Keyfactor Command Reference Guide</i> for more information.	
x-certificateformat	Header	<ul> <li>DER Not supported if IncludeChain is set to true.</li> <li>PEM</li> <li>P7B</li> <li>Only supported if IncludeChain is set to true</li> </ul>	

Table 155: POST Certificates Download Response Data

Name	Description
Content	The base-64-encoded certificate in DER, PEM or P7B format with the optional certificate chain.

## 2.2.6.18 POST Certificates Revoke All

The POST /Certificates/RevokeAll method is used to revoke all the certificates in the specified query or collection ID. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: Certificates: *Revoke* 

Certificate permission can be granted at either the global or collection level. See note under CollectionId, below.



**Note:** As of Keyfactor Command version 10, enrollment (PFX and CSR), renewal, and revocation requests all flow through Keyfactor Command workflow. This will result in no changes to the enrollment, renewal, and revocation user experience unless customizations have been added in workflow (see <a href="Workflow Definitions">Workflow Definitions</a>).

Table 156: POST Certificates Revoke All Input Parameters

Name	In	Description	
Query	Body	Required*. A string containing a query to limit the certificates to revoke (e.g. field1 - eq value1 AND field2 -gt value2). Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns. For querying guidelines, refer to the Keyfactor Command Reference Guide Certificate Search Page section. A value for either Query or CollectionId is required. If both Query and CollectionId are specified, certificates from both sources will be revoked.	
Reason	Body	An integer containing the specific reason that the certificates are being revoked.  Available values are:	
		Value	Description
		-1	Remove from Hold
		0	Unspecified
		1	Key Compromised

Name	In	Description		
		Value	Description	
		2	CA Compromised	
		3	Affiliation Changed	
		4	Superseded	
		5	Cessation of Operation	
		6	Certificate Hold	
		7	Remove from CRL	
		999	Unknown	
		The default is <i>Unspecified</i> .		
Comment	Body	<b>Required</b> . A string containing a freeform reason or comment on why the certificates are being revoked.		
EffectiveDate	Body	The date and time when the certificate will be revoked. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z). The default is the current date and time.		
IncludeRevoked	Body	A Boolean that indicates whether revoked certificates should be included in the revocation (true) or not (false). The default is <i>false</i> .		
IncludeExpired	Body	A Boolean that indicates whether expired certificates should be included in the revocation (true) or not (false). The default is <i>false</i> .		
CollectionId	Query	<b>Required</b> *. An integer specifying an optional certificate collection identifier to validate that the user executing the request has sufficient permissions to do so. If a certificate collection ID is not supplied, the user must have global permissions to complete the action. Supplying a certificate collection ID allows for a check of the user's certificate collection-level permissions to determine whether the user has sufficient permissions at a collection level to complete the action. See <i>Certificate Permissions</i> in the <i>Keyfactor Command Reference Guide</i> for more information. This field can also be used to specify the certificate collection containing certificates that should be revoked. A value for either <i>Query</i> or <i>CollectionId</i> is <b>required</b> . If both <i>Query</i> and <i>CollectionId</i> are specified, certificates from both sources will be revoked.		

# 2.2.6.19 DELETE Certificates Query

The DELETE /Certificates/query method is used to delete a group of active certificates from Keyfactor Command that match the criteria provided in the body. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: Certificates: *Delete* 

Certificate permission can be granted at either the global or collection level. See note under CollectionId, below.

Table 157: DELETE Certificates Query Input Parameters

Name	In	Description
sq	Body	Required. Query to limit the requested set of certificates that should be deleted in the form (without parameter name):  "CN –contains \"mycertificate.keyexample.com\""  See Certificate Search Page section of the Keyfactor Command Reference Guide for querying guidelines to build your body query.  Tip: Revoked and expired certificates are excluded from the selection regardless of the query you enter.
CollectionId	Query	An integer specifying an optional certificate collection identifier to validate that the user executing the request has sufficient permissions to do so. If a certificate collection ID is not supplied, the user must have global permissions to complete the action. Supplying a certificate collection ID allows for a check of the user's certificate collection-level permissions to determine whether the user has sufficient permissions at a collection level to complete the action. See <i>Certificate Permissions</i> in the <i>Keyfactor Command Reference Guide</i> for more information.

#### 2.2.6.20 DELETE Certificates Private Key

The DELETE /Certificates/PrivateKey method is used to delete the stored private key of each certificate ID in the list provided in the body from the Keyfactor Command platform. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: Certificates: *Delete* 

Certificate permission can be granted at either the global or collection level. See note under CollectionId, below.

Table 158: DELETE Certificates Private Key Input Parameters

Name	In	Description
ids	Body	<b>Required</b> . An array of Keyfactor Command reference IDs for certificates for which the associated private keys should be deleted in the form:  [123,789,567]
CollectionId	Query	An integer specifying an optional certificate collection identifier to validate that the user executing the request has sufficient permissions to do so. If a certificate collection ID is not supplied, the user must have global permissions to complete the action. Supplying a certificate collection ID allows for a check of the user's certificate collection-level permissions to determine whether the user has sufficient permissions at a collection level to complete the action. See <i>Certificate Permissions</i> in the <i>Keyfactor Command Reference Guide</i> for more information.

### 2.2.6.21 DELETE Certificates Private Key ID

The DELETE /Certificates/PrivateKey/{id} method is used to delete the stored private key of the submitted certificate ID. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: Certificates: *Delete* 

Certificate permission can be granted at either the global or collection level. See note under CollectionId, below.

Table 159: DELETE Certificates Private Key {id} Input Parameters

Name	In	Description
id	Path	Required. The Keyfactor Command reference ID of the certificate whose private key should be deleted.  Use the GET /Certificates method (see GET Certificates on page 237) to retrieve a list of certificates based on entered search criteria to determine the certificate ID. This information is also available in the certificate details for a certificate in the Keyfactor Command Management Portal.
CollectionId	Query	An integer specifying an optional certificate collection identifier to validate that the user executing the request has sufficient permissions to do so. If a certificate collection ID is not supplied, the user must have global permissions to complete the action. Supplying a certificate collection ID allows for a check of the user's certificate collection-level permissions to determine whether the user has sufficient permissions at a collection level to complete the action. See <i>Certificate Permissions</i> in the <i>Keyfactor Command Reference Guide</i> for more information.

# 2.2.7 Certificate Authority

The CertificateAuthority component of the Keyfactor API includes methods for listing, creating, updating and deleting certificate authority records in Keyfactor Command as well as for publishing CRLs.

Table 160: Certificate Authority Endpoints

Endpoint	Method	Description	Link
/{id}	DELETE	Deletes the certificate authority record for the specified ID.	DELETE Certificate Authority  ID below
/{id}	GET	Returns details for the certificate authority identified by the specified ID.	GET Certificate Authority ID on the next page
/	GET	Returns a list of all certificate authorities.	GET Certificate Authority on page 283
/	POST	Creates a new certificate authority record.	POST Certificate Authority on page 296
/	PUT	Updates an existing certificate authority record.	PUT Certificate Authority on page 322
/Test	POST	Validates that the certificate authority with the provided information can be reached.	POST Certificate Authority Test on page 349
/PublishCRL	POST	Publishes the Certificate Revocation List of the given certificate authority.	POST Certificate Authority PublishCRL on page 351

### 2.2.7.1 DELETE Certificate Authority ID

The DELETE /CertificateAuthority/{id} endpoint is used to delete the certificate authority record with the specified Keyfactor Command reference ID. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: PkiManagement: *Modify* 



**Note:** You can't delete a CA from Keyfactor Command that has active records associated with it (e.g. certificates, certificate requests).

Table 161: DELETE Certificate Authority {id} Input Parameters

Name	In	Description
id	Path	<b>Required</b> . An integer that specifies the Keyfactor Command reference ID of the certificate authority record to delete.

# 2.2.7.2 GET Certificate Authority ID

The POST /CertificateAuthority method is used to retrieve details for a specified certificate authority. This method returns HTTP 200 OK on a success with the details for the certificate authority.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: PkiManagement: *Read* 

Table 162: GET Certificate Authority {id} Input Parameters

Name	In	Description
id	Path	<b>Required</b> . An integer that specifies the Keyfactor Command ID of the certificate authority record to retrieve.

Table 163: GET Certificate Authority {id} Response Data

Name	Description
Id	An integer indicating the Keyfactor Command identifier for the certificate authority. The ID is automatically assigned by Keyfactor Command.
LogicalName	A string indicating the logical name of the certificate authority.
HostName	A string indicating the DNS hostname (for DCOM configurations) or URL (for HTTPS configurations) of the certificate authority (e.g. myca.keyexample.com or https://myca.keyexample.com).
Delegate	A Boolean that sets whether management interactions with the certificate authority via Keyfactor Command should be done in the context of the user making the request ( <i>true</i> ). If set to <i>false</i> , these interactions are done in the context of the service account under which the Keyfactor Command application pool is running unless <i>ExplicitCredentials</i> is true.
	Important: Delegation is only supported with Microsoft CAs and has limitations. Be sure to read more about delegation in Certificate Authority Operations: Adding or Modifying a CA Record in the Keyfactor Command Reference Guide before setting this option to true.
DelegateEnrollment	A Boolean that sets whether enrollment to the certificate authority via Keyfactor Command should be done in the context of the user making the request ( <i>true</i> ). If set to <i>false</i> , enrollment is done in the context of the service account under which the Keyfactor Command application pool is running unless <i>ExplicitCredentials</i> is true.
	Important: Delegation is only supported with Microsoft CAs and has limitations. Be sure to read more about delegation in <i>Certificate Authority Operations: Adding or Modifying a CA Record</i> in the <i>Keyfactor Command Reference Guide</i> before setting this option to true.
ForestRoot	A string indicating the forest root name or DNS domain name for the certificate authority (e.g. keyexample.com).
	Note: This field is retained for legacy purposes and will auto-populate with the value provided in the <i>ConfigurationTenant</i> field.
ConfigurationTenant	A string indicating the forest root name or DNS domain name for the certificate authority (e.g. keyexample.com).  For EJBCA CAs, this is a reference ID and does not need to be the DNS domain name. The short hostname of the EJBCA CA server makes a good reference ID.

Name	Description
	Important: EJBCA and Microsoft CAs cannot be configured with the same Configuration Tenant, so do not set this to the DNS domain name for an EJBCA CA if you will also be configuring Microsoft CAs in the same DNS domain.
Remote	A Boolean that sets whether communications with the certificate authority are done via a Keyfactor Windows Orchestrator configured to manage remote CAs. If set to <i>true</i> , a value must be provided for the <i>Agent</i> . The default is <i>false</i> .
Agent	A string indicating the GUID of the Keyfactor Windows Orchestrator or Keyfactor Universal Orchestrator configured to manage the certificate authority (see <i>Remote</i> ).
Standalone	A Boolean that sets whether the certificate authority is a standalone CA ( <i>true</i> ) or not ( <i>false</i> ). If both <i>Standalone</i> is set to <i>true</i> and <i>AllowedEnrollmentTypes</i> is set to 1 or 3, <i>KeyRetention</i> may be set. The default is <i>false</i> .
MonitorThresholds	A Boolean that sets whether threshold monitoring is enabled. If set to <i>true</i> , email alerts will be sent when certificate issuance or failures (including denials) since the last threshold alert was sent falls outside the configured limits. If this option is set to <i>true</i> , the following additional fields should also be set:  • IssuanceMax  • IssuanceMin  • FailureMax  The DenialMax field has been deprecated and should always be zero.  Monitoring is not supported for CAs accessed with the Keyfactor Windows Orchestrator or Keyfactor Universal Orchestrator.  The default is <i>false</i> .  See also <i>ThresholdCheck</i> to configure the monitoring frequency.  Note: For full functionality of threshold monitoring, you must also configure email recipients for threshold alerts. These are configured globally rather than on a CA-by-CA basis. See <i>Certificate Authority Monitoring</i> in the <i>Keyfactor Command Reference Guide</i> for more information.
IssuanceMax	An integer that sets the maximum number of certificates that can be issued in the period between scheduled threshold monitoring alert emails before an alert is triggered. If more certificates than this are issued in the period, a notification will be included in the threshold monitoring email. This value is unset by default.
IssuanceMin	An integer that sets the minimum number of certificates that should be issued in the period between scheduled threshold monitoring alert emails before an alert is triggered. If fewer certificates than this are issued in the period, a notification will be included in the threshold monitoring email. This value is unset by default.

Name	Description		
FailureMax	An integer that sets the maximum number of certificate requests that can fail or be denied in the period between scheduled threshold monitoring alert emails before an alert is triggered. If more certificate requests than this fail in the period, a notification will be included in the threshold monitoring email. This value is unset by default.		
RFCEnforcement	A Boolean that sets whether certificate enrollments made through Keyfactor Command for this CA must include at least one DNS SAN ( <i>true</i> ) or not ( <i>false</i> ). In the Keyfactor Command Management Portal, this causes the CN entered in PFX enrollment to automatically be replicated as a SAN, which the user can either change or accept. For CSR enrollment, if the CSR does not have a SAN that matches the CN, one will automatically be added to the certificate if this is set. The default is <i>false</i> .  Tip: The <i>RFCEnforcement</i> option at the CA level is used only for standalone CAs. RFC enforcement for enterprise CAs is configured on a template-by-template basis (see <u>PUT</u> Templates on page 1195).		
Properties	Additional properties about the certificate authority. This field is used to store the configuration for the <i>Sync External Certificates</i> option. This option allows foreign certificates that have been imported into a Microsoft CA to be synchronized to Keyfactor Command along with the certificates issued by the Microsoft CA. The setting is referenced using the following format:  {\"syncExternal\":true} OR {\"syncExternal\":false}		
AllowedEn- rollmentTypes	An integer that sets the type(s) of enrollment that are allowed through Keyfactor Command for the certificate authority. Possible values are:		
	Value	Description	
	1	PFX Enrollment	
	2	CSR Enrollment	
	3	PFX and CSR Enrollment	
	This value is unset by default.		
KeyRetention	An integer that sets the type of key ible values are:	y retention to enable for the certificate authority, if any. Poss-	
	Value	Description	
	0	Key Retention Disabled	
	1	Indefinite	

Name	Description		
	Value	Description	
	2	After Expiration	
	3	From Issuance	
	Values of 2 and 3 require setting <i>KeyRetentionDays</i> .  This value is unset by default.		
	tion for enterprise CAs is contemplates on page 1195).  KeyRetention on a CA may set to true and AllowedEnrition must be configured w	ion at the CA level is used only for standalone CAs. Key retenonfigured on a template-by-template basis (see PUT only be set to a value other than zero if both <i>Standalone</i> is <i>collmentTypes</i> is set to 1 or 3. Some level of private key retenhen using PFX enrollment with a standalone CA. See <i>Certises: Adding or Modifying a CA Record</i> in the <i>Keyfactor</i> or more information.	
KeyRetentionDays		of days for which to retain the private keys for certificates before scheduling them for deletion. This value is unset by	
ExplicitCredentials	or not (false). Set this to true for Configured for integrated authentic	cit credentials are enabled for this certificate authority ( <i>true</i> )  As that do not support integrated authentication or are not cation and enter credentials in the <i>ExplicitUser</i> and <i>Explinity</i> supported for Microsoft CAs. The default is <i>false</i> .	
	tication is not supported. I Microsoft CAs, Keyfactor C servers joined to the local	rue primarily for Microsoft CAs where integrated authen- ntegrated authentication is generally supported for A gateways, or Keyfactor CA management gateways on Active Directory forest in which Keyfactor Command is rectory forests in a two-way trust with this forest.	
SubscriberTerms		d a checkbox on the enrollment pages to force users to agree rolling (true) or not (false). The default is <i>false</i> .	
		e custom terms using the URL to Subscriber Terms applic- ion Settings: Enrollment Tab in the Keyfactor Command Refer- nation.	
ExplicitUser	the forest in which the Microsoft C	n the format DOMAIN\username, for a service account user in CA resides or, for non-domain-joined machines, local machine e on which the CA is installed when ExplicitCredentials is set	

#### Description Name to true. Tip: This service account user needs appropriate permissions in the Microsoft CA security settings to accomplish the tasks you plan to carry out for this CA through Keyfactor Command. For example: · Certificate enrollment · Certificate revocation Certificate key recovery • Certificate request approval and denial These tasks will be carried out on the CA in the context of the credentials you provide here. Access control for these tasks on CAs is controlled with Keyfactor Command security (see Security Roles and Identities in the Keyfactor Command Reference Guide) and the AllowedRequesters option. **Note:** When the *ExplicitCredentials* option is configured, enrollment and other tasks (e.g. revocation) is done in the context of the user configured here, not the user making the request in Keyfactor Command. This overrides the existing AD security policy used by Keyfactor Command. **ExplicitPassword** A string containing the password for the ExplicitUser. A Boolean that sets whether the allowed requesters option is enabled (true) or not (false). See UseAllowedRequesters also AllowedRequesters. The default is false. **Tip:** This option is supported for all CAs, but it must be used for Microsoft CAs where integrated authentication is not supported and EJBCA CAs. Integrated authentication is generally supported for Microsoft CAs, Keyfactor CA gateways, or Keyfactor CA management gateways on servers joined to the local Active Directory forest in which Keyfactor Command is installed and any Active Directory forests in a two-way trust with this forest. Since Keyfactor Command cannot make use of the access control model of the CA itself to determine which users can enroll for certificates at either a template or CA level without using integrated authentication, this setting replaces that functionality. This setting is similar to setting request certificates for the selected security roles at the CA level on a Microsoft CA. Tip: For CAs in a two-way trust you don't usually need to enable UseAllowedRequesters on the CA, though this may be required in some circumstances depending on the security configuration in the environment. However, templates for a two-way trust environment always require configuration of this option at a template

level to support enrollment (see Configuring Template Options in the Keyfactor

Command Reference Guide and see PUT Templates on page 1195).

#### Description Name An array of Keyfactor Command security roles that are allowed to enroll for certificates via AllowedRequesters Keyfactor Command for this CA. For example: "AllowedRequesters": [ "Power Users", "Read Only" ] The allowed requesters option is used to select Keyfactor Command security roles that a user must belong to in order to successfully enroll for certificates in Keyfactor Command via this CA. This is used for EJBCA CAs and Microsoft CAs where integrated authentication is not supported. Integrated authentication is generally supported for Microsoft CAs, Keyfactor CA gateways, or Keyfactor CA management gateways on servers joined to the local Active Directory forest in which Keyfactor Command is installed and any Active Directory forests in a two-way trust with this forest. Since Keyfactor Command cannot make use of the access control model of the CA itself to determine which users can enroll for certificates at either a template or CA level without using integrated authentication, this setting replaces that functionality. This setting is similar to setting request certificates for the selected security roles at the CA level on a Microsoft CA. In addition to granting permissions at the CA level, you need to enable the UseAllowedRequesters option to grant permissions on a template-by-template basis (see PUT Templates on page 1195). The values set here are only considered if *UseAllowedRequesters* is set to *true*. FullScan The schedule for the full synchronization of this certificate authority. The following schedule types are supported: Name Description Off Turn off a previously configured schedule. Interval A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database. Name Description Minutes An integer indicating the number of minutes between each interval. For example, every hour:

Name	Description	
	Name	Description
		"Interval": {     "Minutes": 60 }
	Daily	A dictionary that indicates a job scheduled to run every day at the same time with the parameter:
		Name Description
		Time The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
		For example, daily at 11:30 pm:
		"Daily": {     "Time": "2022-02-25T23:30:00Z" }
	Weekly	A dictionary that indicates a job scheduled to run on a specific day or days every week at the same time with the parameters:
		Name Description
		Time The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
		Days  An array of values representing the days of the week on which to run the job. These can either be entered as integers (0 for Sunday, 1 for Monday, etc.) or as days of the week (e.g. "Sunday").
		For example, every Monday, Wednesday and Friday at 5:30 pm:
		"Weekly": {     "Days": [     "Monday",     "Wednesday",     "Friday"
		"Friday"

Name	Description		
	Name	Description	
		], "Time": "2022-02-27T17:30:00Z" }	
	sched	e: Although the Swagger Example Value may show examples of various other dules, only the schedules shown here—that are available in the Management all for this functionality—are valid for this endpoint.	
	Tip: There are two types of synchronization schedules available for CAs—Full and Incremental. You do not necessarily need to configure both types. A full scan reads all the certificates and certificate requests in the CA database and synchronizes them to Keyfactor Command regardless of their current state in Keyfactor Command. An incremental scan reads the certificates and certificate requests in the CA database that have been generated since the last full or incremental scan and synchronizes them to Keyfactor Command. A common configuration would be a full scan once or twice a week to provide a clean image of the CA database with a frequent incremental scan to provide timely updates to Keyfactor Command. For a large CA database, a full scan can take a long time to complete. Since an incremental scan only synchronizes updates that have occurred to the CA database since the last synchronization was run, this process is generally quick (other than for the initial synchronization when Keyfactor Command is first installed). The frequency of the incremental scans would depend on the volume of certificate requests coming into the CA.		
IncrementalScan		e for the incremental synchronization of this certificate authority. The following es are supported:	
	Name	Description	
	Off	Turn off a previously configured schedule.	
	Interval	A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database.	
		Name Description	
		Minutes An integer indicating the number of minutes between each interval.	

Name Description Name Description For example, every hour: "Interval": { "Minutes": 60 Daily A dictionary that indicates a job scheduled to run every day at the same time with the parameter: Description Name Time The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z). For example, daily at 11:30 pm: "Daily": { "Time": "2022-02-25T23:30:00Z" Weekly A dictionary that indicates a job scheduled to run on a specific day or days every week at the same time with the parameters: Name Description Time The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z). An array of values representing the days of the week on Days which to run the job. These can either be entered as integers (0 for Sunday, 1 for Monday, etc.) or as days of the week (e.g. "Sunday"). For example, every Monday, Wednesday and Friday at 5:30 pm: "Weekly": { "Days": [ "Monday",

### Description Name Description Name "Wednesday", "Friday" ], "Time": "2022-02-27T17:30:00Z" Note: Although the Swagger Example Value may show examples of various other schedules, only the schedules shown here—that are available in the Management Portal for this functionality—are valid for this endpoint. ThresholdCheck The schedule for threshold monitoring checks on this certificate authority (see MonitorThresholds). The following schedule types are supported: Description Name Off Turn off a previously configured schedule. Interval A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database. **Description** Name Minutes An integer indicating the number of minutes between each interval. For example, every hour: "Interval": { "Minutes": 60 } Daily A dictionary that indicates a job scheduled to run every day at the same time

with the parameter:

Name	Description		
	Name		
		Name	Description
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
		For example, da	aily at 11:30 pm:
		"Daily": {     "Time": }	"2022-02-25T23:30:00Z"
	Note: Although the Swagger Example Value may show examples of various other schedules, only the schedules shown here—that are available in the Management Portal for this functionality—are valid for this endpoint.		
САТуре	An integer indicating the type of CA:  • 0—DCOM  • 1—HTTPS		
AuthCer- tificatePassword	An array indicating the password for the certificate to use to authenticate to the EJBCA CA.  Supported methods to store certificate and associated password information are:		
			mation in the Keyfactor secrets table.
			er-defined username or password that is encrypted and stored Command database.
	• Load th	e credential infor	mation from a PAM provider.
	See <i>Privileged Access Management (PAM)</i> in the <i>Keyfactor Command Reference</i> and <u>PAM Providers on page 709</u> for more information.		
	Value	Descrip	tion
	SecretValue	_	containing the password used to security the EJBCA CA client cation certificate.
	Parameters		indicating the parameters to supply for PAM authentication. Il vary depending on the PAM provider.

Name	Description		
	Value	Description	
	Provider	A string indicating the ID of the PAM provider.  Use the GET /PamProviders method (see GET PAM Providers on page 724) to retrieve a list of all the PAM providers to determine the ID.	
	Due to its sensitive nature, this value is not returned in responses.		
AuthCertificate	An array containing information about the client certificate used to provide authentication to the EJBCA CA. This certificate is used to authenticate to the EJBCA database for synchronization, enrollment and management of certificates.  Authentication certificate values include:		
	Value	Description	
	IssuedDN	A string indicating the distinguished name of the client certificate used to authenticate to the EJBCA CA in X.500 format. For example: "IssuedDN": "CN=SuperAdmin,OU=IT,O=\"Key Example, Inc.\",L=Independence,ST=OH,C=US"	
	IssuerDN	A string indicating the distinguished name of the EJBCA CA in X.500 format.	
	Thumbprint	A string indicating the thumbprint of the client certificate used to authenticate to the EJBCA CA.	
	ExpirationDate A string indicating the expiration date of the client certificate authenticate to the EJBCA CA.		
EnforceUniqueDN	A Boolean that sets whether the unique DN requirement is enforced on the CA ( <i>true</i> ) or not ( <i>false</i> ).  Checking this will cause Keyfactor Command, upon enrollment, to search the EJBCA CA for end entities with DNs that match the DN in the certificate request. If a matching DN is found, the process will update the existing end entity in EJBCA with the new certificate request information rather than creating a new end entity. If you enable this option in Keyfactor Command, it must also be enabled on the matching EJBCA CA. A mismatch in these settings can result in enrollment failures.  This setting applies to HTTPS CAs only.		
LastScan	A string indicating the date, in UTC, on which a synchronization was last performed for the CA.		

# 2.2.7.3 GET Certificate Authority

The GET /CertificateAuthority method is used to retrieve a list of certificate authorities defined in Keyfactor Command. This method returns HTTP 200 OK on a success with details for all the defined certificate authorities.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: PkiManagement: *Read* 

Table 164: GET Certificate Authority Input Parameters

Name	In	Description
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>Id</i> .
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.

Table 165: GET Certificate Authority Response Data

Name	Description		
ld	An integer indicating the Keyfactor Command identifier for the certificate authority. The ID is automatically assigned by Keyfactor Command.		
LogicalName	A string indicating the logical name of the certificate authority.		
HostName	A string indicating the DNS hostname (for DCOM configurations) or URL (for HTTPS configurations) of the certificate authority (e.g. myca.keyexample.com or https://myca.keyexample.com).		
Delegate	A Boolean that sets whether management interactions with the certificate authority via Keyfactor Command should be done in the context of the user making the request ( <i>true</i> ). If set to <i>false</i> , these interactions are done in the context of the service account under which the Keyfactor Command application pool is running unless <i>ExplicitCredentials</i> is true.		
	Important: Delegation is only supported with Microsoft CAs and has limitations. Be sure to read more about delegation in Certificate Authority Operations: Adding or Modifying a CA Record in the Keyfactor Command Reference Guide before setting this option to true.		
DelegateEnrollment	A Boolean that sets whether enrollment to the certificate authority via Keyfactor Command should be done in the context of the user making the request ( <i>true</i> ). If set to <i>false</i> , enrollment is done in the context of the service account under which the Keyfactor Command application pool is running unless <i>ExplicitCredentials</i> is true.		
	Important: Delegation is only supported with Microsoft CAs and has limitations. Be sure to read more about delegation in <i>Certificate Authority Operations: Adding or Modifying a CA Record</i> in the <i>Keyfactor Command Reference Guide</i> before setting this option to true.		
ForestRoot	A string indicating the forest root name or DNS domain name for the certificate authority (e.g. keyexample.com).		
	Note: This field is retained for legacy purposes and will auto-populate with the value provided in the <i>ConfigurationTenant</i> field.		
ConfigurationTenant	A string indicating the forest root name or DNS domain name for the certificate authority (e.g. keyexample.com).  For EJBCA CAs, this is a reference ID and does not need to be the DNS domain name. The short heatness of the EJBCA CA server makes a good reference ID.		
	hostname of the EJBCA CA server makes a good reference ID.		

Name	Description
	Important: EJBCA and Microsoft CAs cannot be configured with the same Configuration Tenant, so do not set this to the DNS domain name for an EJBCA CA if you will also be configuring Microsoft CAs in the same DNS domain.
Remote	A Boolean that sets whether communications with the certificate authority are done via a Keyfactor Windows Orchestrator configured to manage remote CAs. If set to <i>true</i> , a value must be provided for the <i>Agent</i> . The default is <i>false</i> .
Agent	A string indicating the GUID of the Keyfactor Windows Orchestrator or Keyfactor Universal Orchestrator configured to manage the certificate authority (see <i>Remote</i> ).
Standalone	A Boolean that sets whether the certificate authority is a standalone CA ( <i>true</i> ) or not ( <i>false</i> ). If both <i>Standalone</i> is set to <i>true</i> and <i>AllowedEnrollmentTypes</i> is set to 1 or 3, <i>KeyRetention</i> may be set. The default is <i>false</i> .
MonitorThresholds	A Boolean that sets whether threshold monitoring is enabled. If set to <i>true</i> , email alerts will be sent when certificate issuance or failures (including denials) since the last threshold alert was sent falls outside the configured limits. If this option is set to <i>true</i> , the following additional fields should also be set:  • IssuanceMax  • IssuanceMin  • FailureMax  The DenialMax field has been deprecated and should always be zero.  Monitoring is not supported for CAs accessed with the Keyfactor Windows Orchestrator or Keyfactor Universal Orchestrator.  The default is <i>false</i> .  See also <i>ThresholdCheck</i> to configure the monitoring frequency.  Note: For full functionality of threshold monitoring, you must also configure email recipients for threshold alerts. These are configured globally rather than on a CA-by-CA basis. See <i>Certificate Authority Monitoring</i> in the <i>Keyfactor Command Reference Guide</i> for more information.
IssuanceMax	An integer that sets the maximum number of certificates that can be issued in the period between scheduled threshold monitoring alert emails before an alert is triggered. If more certificates than this are issued in the period, a notification will be included in the threshold monitoring email. This value is unset by default.
IssuanceMin	An integer that sets the minimum number of certificates that should be issued in the period between scheduled threshold monitoring alert emails before an alert is triggered. If fewer certificates than this are issued in the period, a notification will be included in the threshold monitoring email. This value is unset by default.

Name	Description		
FailureMax	An integer that sets the maximum number of certificate requests that can fail or be denied in the period between scheduled threshold monitoring alert emails before an alert is triggered. If more certificate requests than this fail in the period, a notification will be included in the threshold monitoring email. This value is unset by default.		
RFCEnforcement	A Boolean that sets whether certificate enrollments made through Keyfactor Command for this CA must include at least one DNS SAN ( <i>true</i> ) or not ( <i>false</i> ). In the Keyfactor Command Management Portal, this causes the CN entered in PFX enrollment to automatically be replicated as a SAN, which the user can either change or accept. For CSR enrollment, if the CSR does not have a SAN that matches the CN, one will automatically be added to the certificate if this is set. The default is <i>false</i> .  Tip: The <i>RFCEnforcement</i> option at the CA level is used only for standalone CAs. RFC		
	enforcement for enterprise  Templates on page 1195).	e CAs is configured on a template-by-template basis (see <u>PUT</u>	
Properties	Additional properties about the certificate authority. This field is used to store the configuration for the <i>Sync External Certificates</i> option. This option allows foreign certificates that have been imported into a Microsoft CA to be synchronized to Keyfactor Command along with the certificates issued by the Microsoft CA. The setting is referenced using the following format:  {\"syncExternal\":true} OR {\"syncExternal\":false}		
AllowedEn- rollmentTypes	An integer that sets the type(s) of the certificate authority. Possible	enrollment that are allowed through Keyfactor Command for values are:	
	Value	Description	
	1	PFX Enrollment	
	2	CSR Enrollment	
	3 PFX and CSR Enrollment		
	This value is unset by default.		
KeyRetention	An integer that sets the type of key retention to enable for the certificate authority, if any. Posible values are:		
	Value	Description	
	0	Key Retention Disabled	
	1	Indefinite	

Name	Description			
	Value	Description		
	2	After Expiration		
	3	From Issuance		
	Values of 2 and 3 require setting <i>K</i> . This value is unset by default.	eyRetentionDays.		
	Tip: The KeyRetention option at the CA level is used only for standalone CAs. Key retention for enterprise CAs is configured on a template-by-template basis (see PUT Templates on page 1195).  KeyRetention on a CA may only be set to a value other than zero if both Standalone is set to true and AllowedEnrollmentTypes is set to 1 or 3. Some level of private key retention must be configured when using PFX enrollment with a standalone CA. See Certificate Authority Operations: Adding or Modifying a CA Record in the Keyfactor Command Reference Guide for more information.			
KeyRetentionDays	An integer indicating the number of days for which to retain the private keys for certificates issued by this certificate authority before scheduling them for deletion. This value is unset by default.			
ExplicitCredentials	A Boolean that sets whether explicit credentials are enabled for this certificate authority ( <i>true</i> ) or not ( <i>false</i> ). Set this to <i>true</i> for CAs that do not support integrated authentication or are not configured for integrated authentication and enter credentials in the <i>ExplicitUser</i> and <i>ExplicitPassword</i> fields. This option is only supported for Microsoft CAs. The default is <i>false</i> .			
	tication is not supported. I Microsoft CAs, Keyfactor C servers joined to the local	rue primarily for Microsoft CAs where integrated authen- ntegrated authentication is generally supported for A gateways, or Keyfactor CA management gateways on Active Directory forest in which Keyfactor Command is rectory forests in a two-way trust with this forest.		
SubscriberTerms		d a checkbox on the enrollment pages to force users to agree rolling (true) or not (false). The default is <i>false</i> .		
		e custom terms using the URL to Subscriber Terms applic- ion Settings: Enrollment Tab in the Keyfactor Command Refer- nation.		
ExplicitUser	the forest in which the Microsoft C	n the format DOMAIN\username, for a service account user in CA resides or, for non-domain-joined machines, local machine e on which the CA is installed when ExplicitCredentials is set		

### Description Name to true. Tip: This service account user needs appropriate permissions in the Microsoft CA security settings to accomplish the tasks you plan to carry out for this CA through Keyfactor Command. For example: · Certificate enrollment · Certificate revocation Certificate key recovery • Certificate request approval and denial These tasks will be carried out on the CA in the context of the credentials you provide here. Access control for these tasks on CAs is controlled with Keyfactor Command security (see Security Roles and Identities in the Keyfactor Command Reference Guide) and the AllowedRequesters option. **Note:** When the *ExplicitCredentials* option is configured, enrollment and other tasks (e.g. revocation) is done in the context of the user configured here, not the user making the request in Keyfactor Command. This overrides the existing AD security policy used by Keyfactor Command. **ExplicitPassword** A string containing the password for the ExplicitUser. A Boolean that sets whether the allowed requesters option is enabled (true) or not (false). See UseAllowedRequesters also AllowedRequesters. The default is false. **Tip:** This option is supported for all CAs, but it must be used for Microsoft CAs where integrated authentication is not supported and EJBCA CAs. Integrated authentication is generally supported for Microsoft CAs, Keyfactor CA gateways, or Keyfactor CA management gateways on servers joined to the local Active Directory forest in which Keyfactor Command is installed and any Active Directory forests in a two-way trust with this forest. Since Keyfactor Command cannot make use of the access control model of the CA itself to determine which users can enroll for certificates at either a template or CA level without using integrated authentication, this setting replaces that functionality. This setting is similar to setting request certificates for the selected security roles at the CA level on a Microsoft CA. Tip: For CAs in a two-way trust you don't usually need to enable UseAllowedRequesters on the CA, though this may be required in some circumstances

depending on the security configuration in the environment. However, templates for a two-way trust environment always require configuration of this option at a template level to support enrollment (see *Configuring Template Options* in the *Keyfactor* 

Command Reference Guide and see PUT Templates on page 1195).

#### Description Name An array of Keyfactor Command security roles that are allowed to enroll for certificates via AllowedRequesters Keyfactor Command for this CA. For example: "AllowedRequesters": [ "Power Users", "Read Only" ] The allowed requesters option is used to select Keyfactor Command security roles that a user must belong to in order to successfully enroll for certificates in Keyfactor Command via this CA. This is used for EJBCA CAs and Microsoft CAs where integrated authentication is not supported. Integrated authentication is generally supported for Microsoft CAs, Keyfactor CA gateways, or Keyfactor CA management gateways on servers joined to the local Active Directory forest in which Keyfactor Command is installed and any Active Directory forests in a two-way trust with this forest. Since Keyfactor Command cannot make use of the access control model of the CA itself to determine which users can enroll for certificates at either a template or CA level without using integrated authentication, this setting replaces that functionality. This setting is similar to setting request certificates for the selected security roles at the CA level on a Microsoft CA. In addition to granting permissions at the CA level, you need to enable the UseAllowedRequesters option to grant permissions on a template-by-template basis (see PUT Templates on page 1195). The values set here are only considered if *UseAllowedRequesters* is set to *true*. FullScan The schedule for the full synchronization of this certificate authority. The following schedule types are supported: Name Description Off Turn off a previously configured schedule. Interval A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database. Name Description Minutes An integer indicating the number of minutes between each interval. For example, every hour:

Name	Description		
	Name	Description	
		"Interval" "Minutes	
	Daily	A dictionary that with the param	at indicates a job scheduled to run every day at the same time eter:
		Name	Description
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
		For example, da	aily at 11:30 pm:
		"Daily": {     "Time": }	"2022-02-25T23:30:00Z"
	Weekly		nt indicates a job scheduled to run on a specific day or days he same time with the parameters:
		Name	Description
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
		Days	An array of values representing the days of the week on which to run the job. These can either be entered as integers (0 for Sunday, 1 for Monday, etc.) or as days of the week (e.g. "Sunday").
		"Weekly": "Days": "Mono	day", nesday",

Name	Description		
	Name	Description	
		], "Time": "2022-02-27T17:30:00Z" }	
	sched	: Although the Swagger Example Value may show examples of various other dules, only the schedules shown here—that are available in the Management all for this functionality—are valid for this endpoint.	
	Tip: There are two types of synchronization schedules available for CAs—Full and Incremental. You do not necessarily need to configure both types. A full scan reads all the certificates and certificate requests in the CA database and synchronizes them to Keyfactor Command regardless of their current state in Keyfactor Command. An incremental scan reads the certificates and certificate requests in the CA database that have been generated since the last full or incremental scan and synchronizes them to Keyfactor Command. A common configuration would be a full scan once or twice a week to provide a clean image of the CA database with a frequent incremental scan to provide timely updates to Keyfactor Command. For a large CA database, a full scan can take a long time to complete. Since an incremental scan only synchronizes updates that have occurred to the CA database since the last synchronization was run, this process is generally quick (other than for the initial synchronization when Keyfactor Command is first installed). The frequency of the incremental scans would depend on the volume of certificate requests coming into the CA.		
IncrementalScan		for the incremental synchronization of this certificate authority. The following es are supported:	
	Name	Description	
	Off	Turn off a previously configured schedule.	
	Interval	A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database.	
		Name Description	
		Minutes An integer indicating the number of minutes between each interval.	

Name	Description		
	Name	Description	
		For example, ev	ery hour:
		"Interval": "Minutes }	
	Daily	A dictionary that with the parame	t indicates a job scheduled to run every day at the same time eter:
		Name	Description
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
		For example, da	ily at 11:30 pm:
		"Daily": {     "Time": }	"2022-02-25T23:30:00Z"
	Weekly		t indicates a job scheduled to run on a specific day or days ne same time with the parameters:
		Name	Description
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
		Days	An array of values representing the days of the week on which to run the job. These can either be entered as integers (0 for Sunday, 1 for Monday, etc.) or as days of the week (e.g. "Sunday").
		For example, even "Weekly": {     "Days":     "Mond	[

### Description Name Description Name "Wednesday", "Friday" ], "Time": "2022-02-27T17:30:00Z" Note: Although the Swagger Example Value may show examples of various other schedules, only the schedules shown here—that are available in the Management Portal for this functionality—are valid for this endpoint. ThresholdCheck The schedule for threshold monitoring checks on this certificate authority (see MonitorThresholds). The following schedule types are supported: Description Name Off Turn off a previously configured schedule. Interval A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database. **Description** Name Minutes An integer indicating the number of minutes between each interval. For example, every hour: "Interval": { "Minutes": 60 } Daily A dictionary that indicates a job scheduled to run every day at the same time

with the parameter:

Name	Description			
	Name	Description		
		Name	Description	
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
		For example, da	nily at 11:30 pm:	
		"Daily": {     "Time": "2022-02-25T23:30:00Z" }		
	sched	ules, only the sch	ragger Example Value may show examples of various other edules shown here—that are available in the Management ality—are valid for this endpoint.	
САТуре	An integer indicating the type of CA:  • 0—DCOM  • 1—HTTPS			
AuthCer- tificatePassword	An array indicating the password for the certificate to use to authenticate to the EJBCA CA.  Supported methods to store certificate and associated password information are:  • Store the credential information in the Keyfactor secrets table.  A Keyfactor secret is a user-defined username or password that is encrypted and stored securely in the Keyfactor Command database.  • Load the credential information from a PAM provider.  See Privileged Access Management (PAM) in the Keyfactor Command Reference Guide and PAM Providers on page 709 for more information.			
	Value	Descrip	tion	
	SecretValue	_	containing the password used to security the EJBCA CA client cation certificate.	
	Parameters		indicating the parameters to supply for PAM authentication. Il vary depending on the PAM provider.	

Name	Description		
	Value	Description	
	Provider	A string indicating the ID of the PAM provider.  Use the GET /PamProviders method (see GET PAM Providers on page 724) to retrieve a list of all the PAM providers to determine the ID.	
	Due to its sensitive nature, this value is not returned in responses.		
AuthCertificate	An array containing information about the client certificate used to provide authentication to the EJBCA CA. This certificate is used to authenticate to the EJBCA database for synchronization, enrollment and management of certificates.  Authentication certificate values include:		
	Value	Description	
	IssuedDN	A string indicating the distinguished name of the client certificate used to authenticate to the EJBCA CA in X.500 format. For example: "IssuedDN": "CN=SuperAdmin,OU=IT,O=\"Key Example, Inc.\",L=Independence,ST=OH,C=US"	
	IssuerDN	A string indicating the distinguished name of the EJBCA CA in X.500 format.	
	Thumbprint	A string indicating the thumbprint of the client certificate used to authenticate to the EJBCA CA.	
	ExpirationDate A string indicating the expiration date of the client certificate authenticate to the EJBCA CA.		
EnforceUniqueDN	A Boolean that sets whether the unique DN requirement is enforced on the CA ( <i>true</i> ) or not ( <i>false</i> ).  Checking this will cause Keyfactor Command, upon enrollment, to search the EJBCA CA for end entities with DNs that match the DN in the certificate request. If a matching DN is found, the process will update the existing end entity in EJBCA with the new certificate request information rather than creating a new end entity. If you enable this option in Keyfactor Command, it must also be enabled on the matching EJBCA CA. A mismatch in these settings can result in enrollment failures.  This setting applies to HTTPS CAs only.		
LastScan	A string indicating the date, in UTC, on which a synchronization was last performed for the CA.		

# 2.2.7.4 POST Certificate Authority

The POST /CertificateAuthority method is used to create a new certificate authority record in Keyfactor Command. This method returns HTTP 200 OK on a success with details for the CA configuration.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: PkiManagement: *Modify* 

Table 166: POST Certificate Authority Input Parameters

Name	In	Description		
LogicalName	Body	Required. A string indicating the logical name of the certificate authority.		
HostName	Body	<b>Required</b> . A string indicating the DNS hostname (for DCOM configurations) or URL (for HTTPS configurations) of the certificate authority (e.g. myca.keyexample.com or https://myca.keyexample.com).		
Delegate	Body	A Boolean that sets whether management interactions with the certificate authority via Keyfactor Command should be done in the context of the user making the request ( <i>true</i> ). If set to <i>false</i> , these interactions are done in the context of the service account under which the Keyfactor Command application pool is running unless <i>ExplicitCredentials</i> is true.		
		Important: Delegation is only supported with Microsoft CAs and has limitations. Be sure to read more about delegation in Certificate Authority Operations: Adding or Modifying a CA Record in the Keyfactor Command Reference Guide before setting this option to true.		
DelegateEnrollment	Body	A Boolean that sets whether enrollment to the certificate authority via Keyfactor Command should be done in the context of the user making the request ( <i>true</i> ). If set to <i>false</i> , enrollment is done in the context of the service account under which the Keyfactor Command application pool is running unless <i>ExplicitCredentials</i> is true.		
		Important: Delegation is only supported with Microsoft CAs and has limitations. Be sure to read more about delegation in Certificate Authority Operations: Adding or Modifying a CA Record in the Keyfactor Command Reference Guide before setting this option to true.		
ForestRoot		A string indicating the forest root name or DNS domain name for the certificate authority (e.g. keyexample.com).		
		<b>Note:</b> This field is retained for legacy purposes and will auto-populate with the value provided in the <i>ConfigurationTenant</i> field.		
ConfigurationTenant	Body	Required. A string indicating the forest root name or DNS domain name for the certificate authority (e.g. keyexample.com).  For EJBCA CAs, this is a reference ID and does not need to be the DNS domain name.  The short hostname of the EJBCA CA server makes a good reference ID.		
		Important: EJBCA and Microsoft CAs cannot be configured with the same  Configuration Tenant, so do not set this to the DNS domain name for an EJBCA  CA if you will also be configuring Microsoft CAs in the same DNS domain.		

Name	In	Description		
Remote	Body	A Boolean that sets whether communications with the certificate authority are done via a Keyfactor Windows Orchestrator configured to manage remote CAs. If set to <i>true</i> , a value must be provided for the <i>Agent</i> . The default is <i>false</i> .		
Agent	Body	A string indicating the GUID of the Keyfactor Windows Orchestrator or Keyfactor Universal Orchestrator configured to manage the certificate authority (see <i>Remote</i> ).		
Standalone	Body	A Boolean that sets whether the certificate authority is a standalone CA ( <i>true</i> ) or not ( <i>false</i> ). If both <i>Standalone</i> is set to <i>true</i> and <i>AllowedEnrollmentTypes</i> is set to 1 or 3, <i>KeyRetention</i> may be set. The default is <i>false</i> .		
MonitorThresholds	Body	A Boolean that sets whether threshold monitoring is enabled. If set to true, email alerts will be sent when certificate issuance or failures (including denials) since the last threshold alert was sent falls outside the configured limits. If this option is set to true, the following additional fields should also be set:  • IssuanceMax  • IssuanceMin  • FailureMax  The DenialMax field has been deprecated and should always be zero.  Monitoring is not supported for CAs accessed with the Keyfactor Windows Orchestrator or Keyfactor Universal Orchestrator.  The default is false.  See also ThresholdCheck to configure the monitoring frequency.  Note: For full functionality of threshold monitoring, you must also configure email recipients for threshold alerts. These are configured globally rather than on a CA-by-CA basis. See Certificate Authority Monitoring in the Keyfactor Command Reference Guide for more information.		
IssuanceMax	Body	An integer that sets the maximum number of certificates that can be issued in the period between scheduled threshold monitoring alert emails before an alert is triggered. If more certificates than this are issued in the period, a notification will be included in the threshold monitoring email. This value is unset by default.		
IssuanceMin	Body	An integer that sets the minimum number of certificates that should be issued in the period between scheduled threshold monitoring alert emails before an alert is triggered. If fewer certificates than this are issued in the period, a notification will be included in the threshold monitoring email. This value is unset by default.		
FailureMax	Body	An integer that sets the maximum number of certificate requests that can fail or be denied in the period between scheduled threshold monitoring alert emails before an alert is triggered. If more certificate requests than this fail in the period, a notification will be included in the threshold monitoring email. This value is unset by default.		

Name	In	Description		
RFCEnforcement	Body	A Boolean that sets whether certificate enrollments made through Keyfactor Command for this CA must include at least one DNS SAN ( <i>true</i> ) or not ( <i>false</i> ). In the Keyfactor Command Management Portal, this causes the CN entered in PFX enrollment to automatically be replicated as a SAN, which the user can either change or accept. For CSR enrollment, if the CSR does not have a SAN that matches the CN, one will automatically be added to the certificate if this is set.  The default is <i>false</i> .  Tip: The <i>RFCEnforcement</i> option at the CA level is used only for standalone CAs. RFC enforcement for enterprise CAs is configured on a template-bytemplate basis (see <a href="PUT Templates on page 1195">PUT Templates on page 1195</a> ).		
Properties	Body	Required. Additional properties about the certificate authority. This field is used to store the configuration for the <i>Sync External Certificates</i> option. This option allows foreign certificates that have been imported into a Microsoft CA to be synchronized to Keyfactor Command along with the certificates issued by the Microsoft CA. The setting is referenced using the following format:  {\"syncExternal\":true} OR {\"syncExternal\":false}		
AllowedEn- rollmentTypes	Body	An integer that sets the type(s) Command for the certificate au	of enrollment that are allowed through Keyfactor thority. Possible values are:	
		Value	Description	
		1	PFX Enrollment	
		2	CSR Enrollment	
		3	PFX and CSR Enrollment	
		This value is unset by default.		
KeyRetention	Body	An integer that sets the type of key retention to enable for the certificate authority, if any. Possible values are:		
		Value	Description	
		0	Key Retention Disabled	
		1	Indefinite	
		2	After Expiration	
		3	From Issuance	

Name	In	Description		
		Values of 2 and 3 require setting <i>KeyRetentionDays</i> .  This value is unset by default.		
		Tip: The KeyRetention option at the CA level is used only for standalone CAs. Key retention for enterprise CAs is configured on a template-by-template basis (see PUT Templates on page 1195).  KeyRetention on a CA may only be set to a value other than zero if both Standalone is set to true and AllowedEnrollmentTypes is set to 1 or 3. Some level of private key retention must be configured when using PFX enrollment with a standalone CA. See Certificate Authority Operations: Adding or Modifying a CA Record in the Keyfactor Command Reference Guide for more information.		
KeyRetentionDays	Body	An integer indicating the number of days for which to retain the private keys for certificates issued by this certificate authority before scheduling them for deletion. This value is unset by default.		
ExplicitCredentials	Body	A Boolean that sets whether explicit credentials are enabled for this certificate authority (true) or not (false). Set this to true for CAs that do not support integrated authentication or are not configured for integrated authentication and enter credentials in the ExplicitUser and ExplicitPassword fields. This option is only supported for Microsoft CAs. The default is false.  Tip: This option is set to true primarily for Microsoft CAs where integrated		
		authentication is not supported. Integrated authentication is generally supported for Microsoft CAs, Keyfactor CA gateways, or Keyfactor CA management gateways on servers joined to the local Active Directory forest in which Keyfactor Command is installed and any Active Directory forests in a two-way trust with this forest.		
SubscriberTerms	Body	A Boolean that sets whether to add a checkbox on the enrollment pages to force users to agree to a custom set of terms before enrolling (true) or not (false). The default is false.		
		Tip: Configure a link to the custom terms using the URL to Subscriber Terms application setting. See Application Settings: Enrollment Tab in the Keyfactor Command Reference Guide for more information.		
ExplicitUser	Body	A string indicating the username, in the format DOMAIN\username, for a service account user in the forest in which the Microsoft CA resides or, for non-domain-joined machines, local machine account credentials on the machine on which the CA is installed when <i>ExplicitCredentials</i> is set to <i>true</i> .		
		Tip: This service account user needs appropriate permissions in the Microsoft		

Name	In	Description		
		CA security settings to accomplish the tasks you plan to carry out for this CA through Keyfactor Command. For example:  Certificate enrollment  Certificate revocation  Certificate key recovery  Certificate request approval and denial These tasks will be carried out on the CA in the context of the credentials you provide here. Access control for these tasks on CAs is controlled with Keyfactor Command security (see Security Roles and Identities in the Keyfactor Command Reference Guide) and the AllowedRequesters option.  Note: When the ExplicitCredentials option is configured, enrollment and other tasks (e.g. revocation) is done in the context of the user configured here, not the user making the request in Keyfactor Command. This overrides the existing AD security policy used by Keyfactor Command.		
ExplicitPassword	Body	A string containing the password for the <i>ExplicitUser</i> .		
UseAl- lowedRequesters	Body	A Boolean that sets whether the allowed requesters option is enabled (true) or not (false). See also AllowedRequesters. The default is false.  Tip: This option is supported for all CAs, but it must be used for Microsoft CAs where integrated authentication is not supported and EJBCA CAs. Integrated authentication is generally supported for Microsoft CAs, Keyfactor CA gateways, or Keyfactor CA management gateways on servers joined to the local Active Directory forest in which Keyfactor Command is installed and any Active Directory forests in a two-way trust with this forest. Since Keyfactor Command cannot make use of the access control model of the CA itself to determine which users can enroll for certificates at either a template or CA level without using integrated authentication, this setting replaces that functionality. This setting is similar to setting request certificates for the selected security roles at the CA level on a Microsoft CA.  Tip: For CAs in a two-way trust you don't usually need to enable UseAllowedRequesters on the CA, though this may be required in some circumstances depending on the security configuration in the environment. However, templates for a two-way trust environment always require configuration of this option at a template level to support enrollment (see Configuring Template Options in the Keyfactor Command Reference Guide and see PUT Templates on page 1195).		
AllowedRequesters	Body	An array of Keyfactor Command security roles that are allowed to enroll for certificates		

Name	In	Description		
		"Allowed "Powe	Requesters": [ In Users", In Only"	
		The allowed requesters option is used to select Keyfactor Command security roles that a user must belong to in order to successfully enroll for certificates in Keyfactor Command via this CA.  This is used for EJBCA CAs and Microsoft CAs where integrated authentication is not supported. Integrated authentication is generally supported for Microsoft CAs, Keyfactor CA gateways, or Keyfactor CA management gateways on servers joined to the local Active Directory forest in which Keyfactor Command is installed and any Active Directory forests in a two-way trust with this forest. Since Keyfactor Command cannot make use of the access control model of the CA itself to determine which users can enroll for certificates at either a template or CA level without using integrated authentication, this setting replaces that functionality. This setting is similar to setting request certificates for the selected security roles at the CA level on a Microsoft CA.  In addition to granting permissions at the CA level, you need to enable the UseAllowedRequesters option to grant permissions on a template-by-template basis (see PUT Templates on page 1195).  The values set here are only considered if UseAllowedRequesters is set to true.		
FullScan	Body	The schedule for the full synchronization of this certificate authority. The following schedule types are supported:		
		Name	Description	
		Off	Turn off a previously configured schedule.	
		Interval	A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database.	
			Name Description	
			Minutes An integer indicating the number of minutes between each interval.	
			For example, every hour:	

Name	In	Description		
		Name	Description	
			"Interval": "Minutes }	
		Daily	A dictionary that time with the pa	it indicates a job scheduled to run every day at the same arameter:
			Name	Description
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
		Weekly	For example, da	nily at 11:30 pm:
			"Daily": {     "Time": }	"2022-02-25T23:30:00Z"
				It indicates a job scheduled to run on a specific day or k at the same time with the parameters:
			Name	Description
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
			Days	An array of values representing the days of the week on which to run the job. These can either be entered as integers (0 for Sunday, 1 for Monday, etc.) or as days of the week (e.g. "Sunday").
			For example, ev  "Weekly": {  "Days":  "Mono	[

Name In Description

# Name Description "Wednesday", "Friday" 1, "Time": "2022-02-27T17:30:00Z" }



**Note:** Although the Swagger *Example Value* may show examples of various other schedules, only the schedules shown here—that are available in the Management Portal for this functionality—are valid for this endpoint.

For example:

```
"FullScan": {
    "Daily": {
        "Time": "2022-05-27T17:30:00Z"
    }
}
```

Or:



Tip: There are two types of synchronization schedules available for CAs—Full and Incremental. You do not necessarily need to configure both types. A full scan reads all the certificates and certificate requests in the CA database and synchronizes them to Keyfactor Command regardless of their current state in Keyfactor Command. An incremental scan reads the certificates and certificate requests in the CA database that have been generated since the last full or incremental scan and synchronizes them to Keyfactor Command. A common configuration would be a full scan once or twice a week to provide a clean image of the CA database with a frequent incremental scan to provide timely updates to Keyfactor Command. For a large CA database, a full scan can take a

Name	In	Description	ı	
		that I this p Keyfa	have occurred to to process is generall actor Command is	Since an incremental scan only synchronizes updates the CA database since the last synchronization was run, y quick (other than for the initial synchronization when first installed). The frequency of the incremental scans yolume of certificate requests coming into the CA.
IncrementalScan	Body		for the incremen edule types are su	tal synchronization of this certificate authority. The apported:
		Name	Description	
		Off	Turn off a previo	ously configured schedule.
		Interval	the specified pa	t indicates a job scheduled to run every x minutes with rameter. Any interval that is selected in the UI will be nutes when stored in the database.
			Name	Description
			Minutes	An integer indicating the number of minutes between each interval.
			For example, ev	ery hour:
			"Interval": "Minutes }	,
		Daily	A dictionary that	indicates a job scheduled to run every day at the same trameter:
			Name	Description
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
			For example, da	ily at 11:30 pm:

Name	In	Description		
		Name	Description	
			"Daily": {     "Time": }	"2022-02-25T23:30:00Z"
		Weekly		it indicates a job scheduled to run on a specific day or k at the same time with the parameters:
			Name	Description
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
			Days	An array of values representing the days of the week on which to run the job. These can either be entered as integers (0 for Sunday, 1 for Monday, etc.) or as days of the week (e.g. "Sunday").
			For example, ev	very Monday, Wednesday and Friday at 5:30 pm:
			"Weekly": {     "Days":	
			"Mono	day",
			"Fric	nesday", day"
		], "Time": }	"2022-02-27T17:30:00Z"	
		othe	er schedules, only	wagger Example Value may show examples of various the schedules shown here—that are available in the or this functionality—are valid for this endpoint.
ThresholdCheck	Body			onitoring checks on this certificate authority (see <i>Monit</i> -schedule types are supported:

Name	In	Description		
		Name	Description	
		Off	Turn off a previo	usly configured schedule.
		Interval	the specified par	indicates a job scheduled to run every x minutes with ameter. Any interval that is selected in the UI will be nutes when stored in the database.
			Name	Description
			Minutes	An integer indicating the number of minutes between each interval.
			For example, eve	ery hour:
			"Interval": "Minutes' }	
		Daily	A dictionary that time with the par	indicates a job scheduled to run every day at the same rameter:
			Name	Description
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
			For example, dai	ly at 11:30 pm:
			"Daily": {     "Time": ' }	'2022-02-25T23:30:00Z"
		othe	er schedules, only th	ragger Example Value may show examples of various ne schedules shown here—that are available in the this functionality—are valid for this endpoint.
САТуре	Body	An integer indicating the type of CA:  • 0—DCOM		

Name	In	Description																
		• 1—HTTPS																
AuthCer- tificatePassword	′	<ul> <li>An array indicating the password for the certificate to use to authenticate to the EJBCA CA.</li> <li>Supported methods to store certificate and associated password information are: <ul> <li>Store the credential information in the Keyfactor secrets table.</li> <li>A Keyfactor secret is a user-defined username or password that is encrypted and stored securely in the Keyfactor Command database.</li> <li>Load the credential information from a PAM provider.</li> <li>See Privileged Access Management (PAM) in the Keyfactor Command Reference Guide and PAM Providers on page 709 for more information.</li> </ul> </li> </ul>																
		Value	Description															
		SecretValue	A string containing the password used to security the EJBCA CA client authentication certificate.															
		Parameters	An array indicating the parameters to supply for PAM authentication. These will vary depending on the PAM provider.															
		Provider	A string indicating the ID of the PAM provider.  Use the GET /PamProviders method (see GET PAM Providers on page 724) to retrieve a list of all the PAM providers to determine the ID.															
		For example, the pa	ssword stored as a Keyfactor secret will look like:															
																	{     "SecretValue }	e": "MySuperSecretPassword"
														value—1 in this exar	d as a CyberArk PAM secret will look like (where the Provider mple—is the Id value from GET PAM Providers on page 724 and the eference the folder name and object name in the CyberArk safe):			
		The password stored	d as a Delinea PAM secret will look like (where the Provider value—1															

Name	In	Description	
		in this example—is the Id value from <u>GET PAM Providers on page 724</u> and the SecretId is the ID if the secret created in the Delinea secret server for this purpose):	
		<pre>{     "Provider": "1",     "Parameters":{         "SecretId":"MyEJBCAPasswordId"     } }</pre>	
		Due to its sensitive nature, this value is not returned in responses.	
AuthCertificate	Body	An array containing information about the client certificate used to provide authentication to the EJBCA CA. This certificate is used to authenticate to the EJBCA database for synchronization, enrollment and management of certificates.  The syntax is the same as for <i>AuthCertificatePassword</i> .	
EnforceUniqueDN	Body	A Boolean that sets whether the unique DN requirement is enforced on the CA ( <i>true</i> ) or not ( <i>false</i> ).  Checking this will cause Keyfactor Command, upon enrollment, to search the EJBCA CA for end entities with DNs that match the DN in the certificate request. If a matching DN is found, the process will update the existing end entity in EJBCA with the new certificate request information rather than creating a new end entity. If you enable this option in Keyfactor Command, it must also be enabled on the matching EJBCA CA. A mismatch in these settings can result in enrollment failures.  This setting applies to HTTPS CAs only.	
LastScan	Body	A string indicating the date, in UTC, on which a synchronization was last performed for the CA.	

Table 167: POST Certificate Authority Response Data

Name	Description
Id	An integer indicating the Keyfactor Command identifier for the certificate authority. The ID is automatically assigned by Keyfactor Command.
LogicalName	A string indicating the logical name of the certificate authority.
HostName	A string indicating the DNS hostname (for DCOM configurations) or URL (for HTTPS configurations) of the certificate authority (e.g. myca.keyexample.com or https://-myca.keyexample.com).
Delegate	A Boolean that sets whether management interactions with the certificate authority via Keyfactor Command should be done in the context of the user making the request ( <i>true</i> ). If set to <i>false</i> , these interactions are done in the context of the service account under which the Keyfactor Command application pool is running unless <i>ExplicitCredentials</i> is true.
	Important: Delegation is only supported with Microsoft CAs and has limitations. Be sure to read more about delegation in <i>Certificate Authority Operations: Adding or Modifying a CA Record</i> in the <i>Keyfactor Command Reference Guide</i> before setting this option to true.
DelegateEnrollment	A Boolean that sets whether enrollment to the certificate authority via Keyfactor Command should be done in the context of the user making the request ( <i>true</i> ). If set to <i>false</i> , enrollment is done in the context of the service account under which the Keyfactor Command application pool is running unless <i>ExplicitCredentials</i> is true.
	Important: Delegation is only supported with Microsoft CAs and has limitations. Be sure to read more about delegation in <i>Certificate Authority Operations: Adding or Modifying a CA Record</i> in the <i>Keyfactor Command Reference Guide</i> before setting this option to true.
ForestRoot	A string indicating the forest root name or DNS domain name for the certificate authority (e.g. keyexample.com).
	Note: This field is retained for legacy purposes and will auto-populate with the value provided in the <i>ConfigurationTenant</i> field.
ConfigurationTenant	A string indicating the forest root name or DNS domain name for the certificate authority (e.g. keyexample.com).  For EJBCA CAs, this is a reference ID and does not need to be the DNS domain name. The short
	hostname of the EJBCA CA server makes a good reference ID.

Name	Description
	Important: EJBCA and Microsoft CAs cannot be configured with the same Configuration Tenant, so do not set this to the DNS domain name for an EJBCA CA if you will also be configuring Microsoft CAs in the same DNS domain.
Remote	A Boolean that sets whether communications with the certificate authority are done via a Keyfactor Windows Orchestrator configured to manage remote CAs. If set to <i>true</i> , a value must be provided for the <i>Agent</i> . The default is <i>false</i> .
Agent	A string indicating the GUID of the Keyfactor Windows Orchestrator or Keyfactor Universal Orchestrator configured to manage the certificate authority (see <i>Remote</i> ).
Standalone	A Boolean that sets whether the certificate authority is a standalone CA ( <i>true</i> ) or not ( <i>false</i> ). If both <i>Standalone</i> is set to <i>true</i> and <i>AllowedEnrollmentTypes</i> is set to 1 or 3, <i>KeyRetention</i> may be set. The default is <i>false</i> .
MonitorThresholds	A Boolean that sets whether threshold monitoring is enabled. If set to <i>true</i> , email alerts will be sent when certificate issuance or failures (including denials) since the last threshold alert was sent falls outside the configured limits. If this option is set to <i>true</i> , the following additional fields should also be set:  • IssuanceMax  • IssuanceMin  • FailureMax  The DenialMax field has been deprecated and should always be zero.  Monitoring is not supported for CAs accessed with the Keyfactor Windows Orchestrator or Keyfactor Universal Orchestrator.  The default is <i>false</i> .  See also <i>ThresholdCheck</i> to configure the monitoring frequency.  Note: For full functionality of threshold monitoring, you must also configure email recipients for threshold alerts. These are configured globally rather than on a CA-by-CA basis. See <i>Certificate Authority Monitoring</i> in the <i>Keyfactor Command Reference Guide</i> for more information.
IssuanceMax	An integer that sets the maximum number of certificates that can be issued in the period between scheduled threshold monitoring alert emails before an alert is triggered. If more certificates than this are issued in the period, a notification will be included in the threshold monitoring email. This value is unset by default.
IssuanceMin	An integer that sets the minimum number of certificates that should be issued in the period between scheduled threshold monitoring alert emails before an alert is triggered. If fewer certificates than this are issued in the period, a notification will be included in the threshold monitoring email. This value is unset by default.

Name	Description		
FailureMax	An integer that sets the maximum number of certificate requests that can fail or be denied in the period between scheduled threshold monitoring alert emails before an alert is triggered. If more certificate requests than this fail in the period, a notification will be included in the threshold monitoring email. This value is unset by default.		
RFCEnforcement	A Boolean that sets whether certificate enrollments made through Keyfactor Command for this CA must include at least one DNS SAN ( <i>true</i> ) or not ( <i>false</i> ). In the Keyfactor Command Management Portal, this causes the CN entered in PFX enrollment to automatically be replicated as a SAN, which the user can either change or accept. For CSR enrollment, if the CSR does not have a SAN that matches the CN, one will automatically be added to the certificate if this is set. The default is <i>false</i> .  Tip: The <i>RFCEnforcement</i> option at the CA level is used only for standalone CAs. RFC		
	enforcement for enterprise CAs is configured on a template-by-template basis (see <u>PUT Templates on page 1195</u> ).		
Properties	Additional properties about the certificate authority. This field is used to store the configuration for the <i>Sync External Certificates</i> option. This option allows foreign certificates that have been imported into a Microsoft CA to be synchronized to Keyfactor Command along with the certificates issued by the Microsoft CA. The setting is referenced using the following format:  {\"syncExternal\":true} OR {\"syncExternal\":false}		
AllowedEn- rollmentTypes	An integer that sets the type(s) of the certificate authority. Possible	enrollment that are allowed through Keyfactor Command for values are:	
	Value	Description	
	1	PFX Enrollment	
	2	CSR Enrollment	
	3 PFX and CSR Enrollment		
	This value is unset by default.		
KeyRetention	An integer that sets the type of key retention to enable for the certificate authority, if any ible values are:		
	Value	Description	
	0	Key Retention Disabled	
	1	Indefinite	

Name	Description		
	Value	Description	
	2	After Expiration	
	3	From Issuance	
	Values of 2 and 3 require setting <i>K</i> . This value is unset by default.	eyRetentionDays.	
	tion for enterprise CAs is c <u>Templates on page 1195</u> ). <i>KeyRetention</i> on a CA may set to <i>true</i> and <i>AllowedEnr</i> tion must be configured w	ion at the CA level is used only for standalone CAs. Key retenonfigured on a template-by-template basis (see PUT only be set to a value other than zero if both <i>Standalone</i> is <i>collmentTypes</i> is set to 1 or 3. Some level of private key retenhen using PFX enrollment with a standalone CA. See <i>Certises: Adding or Modifying a CA Record</i> in the <i>Keyfactor</i> or more information.	
KeyRetentionDays		of days for which to retain the private keys for certificates before scheduling them for deletion. This value is unset by	
ExplicitCredentials	or not (false). Set this to true for Configured for integrated authentic	cit credentials are enabled for this certificate authority ( <i>true</i> )  As that do not support integrated authentication or are not cation and enter credentials in the <i>ExplicitUser</i> and <i>Explinity</i> supported for Microsoft CAs. The default is <i>false</i> .	
	tication is not supported. I Microsoft CAs, Keyfactor C servers joined to the local	rue primarily for Microsoft CAs where integrated authen- ntegrated authentication is generally supported for A gateways, or Keyfactor CA management gateways on Active Directory forest in which Keyfactor Command is rectory forests in a two-way trust with this forest.	
SubscriberTerms		d a checkbox on the enrollment pages to force users to agree rolling (true) or not (false). The default is <i>false</i> .	
		e custom terms using the <i>URL to Subscriber Terms</i> applic- ion Settings: Enrollment Tab in the Keyfactor Command Refer- nation.	
ExplicitUser	the forest in which the Microsoft C	n the format DOMAIN\username, for a service account user in CA resides or, for non-domain-joined machines, local machine e on which the CA is installed when ExplicitCredentials is set	

# Description Name to true. Tip: This service account user needs appropriate permissions in the Microsoft CA security settings to accomplish the tasks you plan to carry out for this CA through Keyfactor Command. For example: · Certificate enrollment · Certificate revocation Certificate key recovery • Certificate request approval and denial These tasks will be carried out on the CA in the context of the credentials you provide here. Access control for these tasks on CAs is controlled with Keyfactor Command security (see Security Roles and Identities in the Keyfactor Command Reference Guide) and the AllowedRequesters option. **Note:** When the *ExplicitCredentials* option is configured, enrollment and other tasks (e.g. revocation) is done in the context of the user configured here, not the user making the request in Keyfactor Command. This overrides the existing AD security policy used by Keyfactor Command. **ExplicitPassword** A string containing the password for the ExplicitUser. A Boolean that sets whether the allowed requesters option is enabled (true) or not (false). See UseAllowedRequesters also AllowedRequesters. The default is false. **Tip:** This option is supported for all CAs, but it must be used for Microsoft CAs where integrated authentication is not supported and EJBCA CAs. Integrated authentication is generally supported for Microsoft CAs, Keyfactor CA gateways, or Keyfactor CA management gateways on servers joined to the local Active Directory forest in which Keyfactor Command is installed and any Active Directory forests in a two-way trust with this forest. Since Keyfactor Command cannot make use of the access control model of the CA itself to determine which users can enroll for certificates at either a template or CA level without using integrated authentication, this setting replaces that functionality. This setting is similar to setting request certificates for the selected security roles at the CA level on a Microsoft CA. Tip: For CAs in a two-way trust you don't usually need to enable UseAllowedRequesters on the CA, though this may be required in some circumstances depending on the security configuration in the environment. However, templates for a

two-way trust environment always require configuration of this option at a template level to support enrollment (see *Configuring Template Options* in the *Keyfactor* 

Command Reference Guide and see PUT Templates on page 1195).

#### Description Name An array of Keyfactor Command security roles that are allowed to enroll for certificates via AllowedRequesters Keyfactor Command for this CA. For example: "AllowedRequesters": [ "Power Users", "Read Only" ] The allowed requesters option is used to select Keyfactor Command security roles that a user must belong to in order to successfully enroll for certificates in Keyfactor Command via this CA. This is used for EJBCA CAs and Microsoft CAs where integrated authentication is not supported. Integrated authentication is generally supported for Microsoft CAs, Keyfactor CA gateways, or Keyfactor CA management gateways on servers joined to the local Active Directory forest in which Keyfactor Command is installed and any Active Directory forests in a two-way trust with this forest. Since Keyfactor Command cannot make use of the access control model of the CA itself to determine which users can enroll for certificates at either a template or CA level without using integrated authentication, this setting replaces that functionality. This setting is similar to setting request certificates for the selected security roles at the CA level on a Microsoft CA. In addition to granting permissions at the CA level, you need to enable the UseAllowedRequesters option to grant permissions on a template-by-template basis (see PUT Templates on page 1195). The values set here are only considered if *UseAllowedRequesters* is set to *true*. FullScan The schedule for the full synchronization of this certificate authority. The following schedule types are supported: Name Description Off Turn off a previously configured schedule. Interval A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database. Name Description Minutes An integer indicating the number of minutes between each interval. For example, every hour:

Name	Description		
	Name	Description	
		"Interval": {     "Minutes": 60 }	
	Daily	A dictionary that indicates a job scheduled to run every day at the same time with the parameter:	
		Name Description	
		Time The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
		For example, daily at 11:30 pm:	
		"Daily": {     "Time": "2022-02-25T23:30:00Z" }	
	Weekly	A dictionary that indicates a job scheduled to run on a specific day or days every week at the same time with the parameters:	
		Name Description	
		Time The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
		Days  An array of values representing the days of the week on which to run the job. These can either be entered as integers (0 for Sunday, 1 for Monday, etc.) or as days of the week (e.g. "Sunday").	
		For example, every Monday, Wednesday and Friday at 5:30 pm:	
		"Weekly": {     "Days": [     "Monday",     "Wednesday",     "Friday"	
		"Friday"	

Name	Description			
	Name	Description		
		], "Time": "2022-02-27T17:30:00Z" }		
	sched	e: Although the Swagger Example Value may show examples of various other dules, only the schedules shown here—that are available in the Management all for this functionality—are valid for this endpoint.		
	Tip: There are two types of synchronization schedules available for CAs—Full and Incremental. You do not necessarily need to configure both types. A full scan reads all the certificates and certificate requests in the CA database and synchronizes them to Keyfactor Command regardless of their current state in Keyfactor Command. An incremental scan reads the certificates and certificate requests in the CA database that have been generated since the last full or incremental scan and synchronizes them to Keyfactor Command. A common configuration would be a full scan once or twice a week to provide a clean image of the CA database with a frequent incremental scan to provide timely updates to Keyfactor Command. For a large CA database, a full scan can take a long time to complete. Since an incremental scan only synchronizes updates that have occurred to the CA database since the last synchronization was run, this process is generally quick (other than for the initial synchronization when Keyfactor Command is first installed). The frequency of the incremental scans would depend on the volume of certificate requests coming into the CA.			
IncrementalScan	The schedule for the incremental synchronization of this certificate authority. The following schedule types are supported:			
	Name	Description		
	Off	Turn off a previously configured schedule.		
	Interval	A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database.		
		Name Description		
		Minutes An integer indicating the number of minutes between each interval.		

Name	Description		
	Name	Description	
		For example, ev	ery hour:
		"Interval": "Minutes }	
	Daily	A dictionary that with the parame	t indicates a job scheduled to run every day at the same time eter:
		Name	Description
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
		For example, da	ily at 11:30 pm:
		"Daily": {     "Time": }	"2022-02-25T23:30:00Z"
	Weekly		t indicates a job scheduled to run on a specific day or days ne same time with the parameters:
		Name	Description
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
		Days	An array of values representing the days of the week on which to run the job. These can either be entered as integers (0 for Sunday, 1 for Monday, etc.) or as days of the week (e.g. "Sunday").
		For example, even "Weekly": {     "Days":     "Mond	[

# Description Name Description Name "Wednesday", "Friday" ], "Time": "2022-02-27T17:30:00Z" Note: Although the Swagger Example Value may show examples of various other schedules, only the schedules shown here—that are available in the Management Portal for this functionality—are valid for this endpoint. ThresholdCheck The schedule for threshold monitoring checks on this certificate authority (see MonitorThresholds). The following schedule types are supported: Description Name Off Turn off a previously configured schedule. Interval A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database. **Description** Name Minutes An integer indicating the number of minutes between each interval. For example, every hour: "Interval": { "Minutes": 60 } Daily A dictionary that indicates a job scheduled to run every day at the same time

with the parameter:

Name	Description				
	Name	Description			
		Name	Description		
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).		
		For example, da	aily at 11:30 pm:		
		"Daily": {     "Time": }	"2022-02-25T23:30:00Z"		
	Note: Although the Swagger Example Value may show examples of various other schedules, only the schedules shown here—that are available in the Management Portal for this functionality—are valid for this endpoint.				
САТуре	An integer indicating the type of CA:  • 0—DCOM  • 1—HTTPS				
AuthCer- tificatePassword			rd for the certificate to use to authenticate to the EJBCA CA. rtificate and associated password information are:		
	A Keyfac	tor secret is a us	erration in the Keyfactor secrets table. er-defined username or password that is encrypted and stored Command database.		
	Load the	credential infor	mation from a PAM provider.		
	See <i>Privileged Access Management (PAM)</i> in the <i>Keyfactor Command Reference Guid</i> and <u>PAM Providers on page 709</u> for more information.				
	Value	Descrip	tion		
	SecretValue	_	containing the password used to security the EJBCA CA client cation certificate.		
	Parameters An array indicating the parameters to supply for PAM authenticatio These will vary depending on the PAM provider.				

Name	Description		
	Value	Description	
	Provider	A string indicating the ID of the PAM provider.  Use the GET /PamProviders method (see GET PAM Providers on page 724) to retrieve a list of all the PAM providers to determine the ID.	
	Due to its sensitive n	ature, this value is not returned in responses.	
AuthCertificate	the EJBCA CA. This ce enrollment and mana	information about the client certificate used to provide authentication to extificate is used to authenticate to the EJBCA database for synchronization, agement of certificates.	
	Value	Description	
	IssuedDN	A string indicating the distinguished name of the client certificate used to authenticate to the EJBCA CA in X.500 format. For example: "IssuedDN": "CN=SuperAdmin,OU=IT,O=\"Key Example, Inc.\",L=Independence,ST=OH,C=US"	
	IssuerDN	A string indicating the distinguished name of the EJBCA CA in X.500 format.	
	Thumbprint	A string indicating the thumbprint of the client certificate used to authenticate to the EJBCA CA.	
	ExpirationDate	A string indicating the expiration date of the client certificate used to authenticate to the EJBCA CA.	
EnforceUniqueDN	A Boolean that sets whether the unique DN requirement is enforced on the CA ( <i>true</i> ) or not ( <i>false</i> ).  Checking this will cause Keyfactor Command, upon enrollment, to search the EJBCA CA for end entities with DNs that match the DN in the certificate request. If a matching DN is found, the process will update the existing end entity in EJBCA with the new certificate request information rather than creating a new end entity. If you enable this option in Keyfactor Command, it must also be enabled on the matching EJBCA CA. A mismatch in these settings can result in enrollment failures.  This setting applies to HTTPS CAs only.		
LastScan	A string indicating the	e date, in UTC, on which a synchronization was last performed for the CA.	

# 2.2.7.5 PUT Certificate Authority

The PUT / Certificate Authority method is used to update a certificate authority record in Keyfactor Command. This method returns HTTP 200 OK on a success with details for the CA configuration.



**Tip:** The following permissions (see Security Overview) are required to use this feature: PkiManagement: Modify



Warning: Any previously populated fields that are not submitted with their full existing data using this method will be cleared of their existing data. When using this method, you should first do a GET to retrieve all the values for the record you want to update, enter corrected data into the field(s) you want to update, and then submit all the fields using PUT, including the fields that contain values but which you are not changing.

Table 168: PUT Certificate Authority Input Parameters

Name	In	Description	
ld	Body	<b>Required</b> . An integer indicating the Keyfactor Command identifier for the certificate authority. The ID is automatically assigned by Keyfactor Command.	
LogicalName	Body	Required. A string indicating the logical name of the certificate authority.	
HostName	Body	<b>Required</b> . A string indicating the DNS hostname (for DCOM configurations) or URL (for HTTPS configurations) of the certificate authority (e.g. myca.keyexample.com or https://myca.keyexample.com).	
Delegate	Body	A Boolean that sets whether management interactions with the certificate authority via Keyfactor Command should be done in the context of the user making the request (true). If set to false, these interactions are done in the context of the service account under which the Keyfactor Command application pool is running unless ExplicitCredentials is true.	
		Important: Delegation is only supported with Microsoft CAs and has limitations. Be sure to read more about delegation in Certificate Authority Operations: Adding or Modifying a CA Record in the Keyfactor Command Reference Guide before setting this option to true.	
DelegateEnrollment	Body	A Boolean that sets whether enrollment to the certificate authority via Keyfactor Command should be done in the context of the user making the request ( <i>true</i> ). If set to <i>false</i> , enrollment is done in the context of the service account under which the Keyfactor Command application pool is running unless <i>ExplicitCredentials</i> is true.  Important: Delegation is only supported with Microsoft CAs and has limitations. Be sure to read more about delegation in <i>Certificate Authority Operations: Adding or Modifying a CA Record</i> in the <i>Keyfactor Command Reference</i>	
		Guide before setting this option to true.	
ForestRoot	Body	A string indicating the forest root name or DNS domain name for the certificate authority (e.g. keyexample.com).	
		Note: This field is retained for legacy purposes and will auto-populate with the value provided in the <i>ConfigurationTenant</i> field.	
ConfigurationTenant	Body	Required. A string indicating the forest root name or DNS domain name for the certificate authority (e.g. keyexample.com).  For EJBCA CAs, this is a reference ID and does not need to be the DNS domain name.  The short hostname of the EJBCA CA server makes a good reference ID.  Important: EJBCA and Microsoft CAs cannot be configured with the same	
		A string indicating the forest root name or DNS domain name for the certificate authority (e.g. keyexample.com).  Note: This field is retained for legacy purposes and will auto-populate with the value provided in the ConfigurationTenant field.  Required. A string indicating the forest root name or DNS domain name for the certificate authority (e.g. keyexample.com).  For EJBCA CAs, this is a reference ID and does not need to be the DNS domain name. The short hostname of the EJBCA CA server makes a good reference ID.	

Name	In	Description		
		Configuration Tenant, so do not set this to the DNS domain name for an EJBCA CA if you will also be configuring Microsoft CAs in the same DNS domain.		
Remote	Body	A Boolean that sets whether communications with the certificate authority are done via a Keyfactor Windows Orchestrator configured to manage remote CAs. If set to <i>true</i> , a value must be provided for the <i>Agent</i> . The default is <i>false</i> .		
Agent	Body	A string indicating the GUID of the Keyfactor Windows Orchestrator or Keyfactor Universal Orchestrator configured to manage the certificate authority (see <i>Remote</i> ).		
Standalone	Body	A Boolean that sets whether the certificate authority is a standalone CA ( <i>true</i> ) or not ( <i>false</i> ). If both <i>Standalone</i> is set to <i>true</i> and <i>AllowedEnrollmentTypes</i> is set to 1 or 3, <i>KeyRetention</i> may be set. The default is <i>false</i> .		
MonitorThresholds	Body	A Boolean that sets whether threshold monitoring is enabled. If set to true, email alerts will be sent when certificate issuance or failures (including denials) since the last threshold alert was sent falls outside the configured limits. If this option is set to true, the following additional fields should also be set:  • IssuanceMax  • IssuanceMin  • FailureMax  The DenialMax field has been deprecated and should always be zero.  Monitoring is not supported for CAs accessed with the Keyfactor Windows Orchestrator or Keyfactor Universal Orchestrator.  The default is false.  See also ThresholdCheck to configure the monitoring frequency.  Note: For full functionality of threshold monitoring, you must also configure email recipients for threshold alerts. These are configured globally rather than on a CA-by-CA basis. See Certificate Authority Monitoring in the Keyfactor Command Reference Guide for more information.		
IssuanceMax	Body	An integer that sets the maximum number of certificates that can be issued in the period between scheduled threshold monitoring alert emails before an alert is triggered. If more certificates than this are issued in the period, a notification will be included in the threshold monitoring email. This value is unset by default.		
IssuanceMin	Body	An integer that sets the minimum number of certificates that should be issued in the period between scheduled threshold monitoring alert emails before an alert is triggered. If fewer certificates than this are issued in the period, a notification will be included in the threshold monitoring email. This value is unset by default.		
FailureMax	Body	An integer that sets the maximum number of certificate requests that can fail or be		

Name	In	Description		
		denied in the period between scheduled threshold monitoring alert emails before an alert is triggered. If more certificate requests than this fail in the period, a notification will be included in the threshold monitoring email. This value is unset by default.		
RFCEnforcement	Body	A Boolean that sets whether certificate enrollments made through Keyfactor Command for this CA must include at least one DNS SAN ( <i>true</i> ) or not ( <i>false</i> ). In the Keyfactor Command Management Portal, this causes the CN entered in PFX enrollment to automatically be replicated as a SAN, which the user can either change or accept. For CSR enrollment, if the CSR does not have a SAN that matches the CN, one will automatically be added to the certificate if this is set.  The default is <i>false</i> .		
		CAs. RFC enforcement f	ent option at the CA level is used only for standalone for enterprise CAs is configured on a template-by-Templates on page 1195).	
Properties	Body	Required. Additional properties about the certificate authority. This field is used to store the configuration for the <i>Sync External Certificates</i> option. This option allows foreign certificates that have been imported into a Microsoft CA to be synchronized to Keyfactor Command along with the certificates issued by the Microsoft CA. The setting is referenced using the following format:  {\"syncExternal\":true} OR {\"syncExternal\":false}		
AllowedEn- rollmentTypes	Body	An integer that sets the type(s) of enrollment that are allowed through Keyfacto Command for the certificate authority. Possible values are:		
		Value	Description	
		1	PFX Enrollment	
		2	CSR Enrollment	
		3	PFX and CSR Enrollment	
		This value is unset by default.		
KeyRetention	Body	An integer that sets the type of any. Possible values are:	key retention to enable for the certificate authority, if	
		Value	Description	
		0	Key Retention Disabled	

Name	In	Description	
		Value	Description
		1	Indefinite
		2	After Expiration
		3	From Issuance
		Values of 2 and 3 require setting. This value is unset by default.	g KeyRetentionDays.
		Key retention for enterplaces on KeyRetention on a CA me dalone is set to true and private key retention me standalone CA. See Cert	option at the CA level is used only for standalone CAs. orise CAs is configured on a template-by-template basis page 1195).  nay only be set to a value other than zero if both StandallowedEnrollmentTypes is set to 1 or 3. Some level of just be configured when using PFX enrollment with a stificate Authority Operations: Adding or Modifying a CA Command Reference Guide for more information.
KeyRetentionDays	Body	An integer indicating the number of days for which to retain the private keys for certificates issued by this certificate authority before scheduling them for deletion. This value is unset by default.	
ExplicitCredentials	Body	(true) or not (false). Set this to to tication or are not configured for	plicit credentials are enabled for this certificate authority crue for CAs that do not support integrated authenor integrated authentication and enter credentials in the credit of the control of the co
		authentication is not su supported for Microsof ment gateways on serve	o true primarily for Microsoft CAs where integrated pported. Integrated authentication is generally t CAs, Keyfactor CA gateways, or Keyfactor CA manageers joined to the local Active Directory forest in which installed and any Active Directory forests in a two-way
SubscriberTerms	Body		add a checkbox on the enrollment pages to force users ns before enrolling (true) or not (false). The default is
			the custom terms using the <i>URL to Subscriber Terms</i> Application Settings: Enrollment Tab in the Keyfactor

Name	In	Description										
		Command Reference Guide for more information.										
ExplicitUser	Body	A string indicating the username, in the format DOMAIN\username, for a service account user in the forest in which the Microsoft CA resides or, for non-domain-joined machines, local machine account credentials on the machine on which the CA is installed when <i>ExplicitCredentials</i> is set to <i>true</i> .										
		Tip: This service account user needs appropriate permissions in the Microsoft CA security settings to accomplish the tasks you plan to carry out for this CA through Keyfactor Command. For example:  Certificate enrollment  Certificate revocation  Certificate revocation  Certificate request approval and denial These tasks will be carried out on the CA in the context of the credentials you provide here. Access control for these tasks on CAs is controlled with Keyfactor Command security (see Security Roles and Identities in the Keyfactor Command Reference Guide) and the AllowedRequesters option.  Note: When the ExplicitCredentials option is configured, enrollment and other tasks (e.g. revocation) is done in the context of the user configured here, not the user making the request in Keyfactor Command. This overrides the existing AD security policy used by Keyfactor Command.										
ExplicitPassword	Body	A string containing the password for the <i>ExplicitUser</i> .										
UseAl- lowedRequesters	Body	Body	Body	Body	Body	Body	Body	Body	Body	Body	Body	A Boolean that sets whether the allowed requesters option is enabled ( <i>true</i> ) or not ( <i>false</i> ). See also <i>AllowedRequesters</i> . The default is <i>false</i> .
		Tip: This option is supported for all CAs, but it must be used for Microsoft CAs where integrated authentication is not supported and EJBCA CAs. Integrated authentication is generally supported for Microsoft CAs, Keyfactor CA gateways, or Keyfactor CA management gateways on servers joined to the local Active Directory forest in which Keyfactor Command is installed and any Active Directory forests in a two-way trust with this forest. Since Keyfactor Command cannot make use of the access control model of the CA itself to determine which users can enroll for certificates at either a template or CA level without using integrated authentication, this setting replaces that functionality. This setting is similar to setting request certificates for the selected security roles at the CA level on a Microsoft CA.										

Name	In	Description	
		Tip: For CAs in a two-way trust you don't usually need to enable <i>UseAl-lowedRequesters</i> on the CA, though this may be required in some circumstances depending on the security configuration in the environment. However, templates for a two-way trust environment always require configuration of this option at a template level to support enrollment (see <i>Configuring Template Options</i> in the <i>Keyfactor Command Reference Guide</i> and see <a href="PUT Templates on page 1195">PUT Templates on page 1195</a> ).	
AllowedRequesters	Body	An array of Keyfactor Command security roles that are allowed to enroll for certificates via Keyfactor Command for this CA. For example:	
		"AllowedRequesters": [     "Power Users",     "Read Only" ]	
		The allowed requesters option is used to select Keyfactor Command security roles that a user must belong to in order to successfully enroll for certificates in Keyfactor Command via this CA.	
		This is used for EJBCA CAs and Microsoft CAs where integrated authentication is not supported. Integrated authentication is generally supported for Microsoft CAs, Keyfactor CA gateways, or Keyfactor CA management gateways on servers joined to the local Active Directory forest in which Keyfactor Command is installed and any Active Directory forests in a two-way trust with this forest. Since Keyfactor Command cannot make use of the access control model of the CA itself to determine which users can enroll for certificates at either a template or CA level without using integrated authentication, this setting replaces that functionality. This setting is similar to setting request certificates for the selected security roles at the CA level on a Microsoft CA.	
		In addition to granting permissions at the CA level, you need to enable the <i>UseAl-lowedRequesters</i> option to grant permissions on a template-by-template basis (see PI Templates on page 1195).  The values set here are only considered if <i>UseAllowedRequesters</i> is set to <i>true</i> .	
FullScan	Body	The schedule for the full synchronization of this certificate authority. The following schedule types are supported:	
		Name Description	
		Off Turn off a previously configured schedule.	

Name	In	Description			
		Name	Description		
		Interval	the specified pa	it indicates a job scheduled to run every x minutes with arameter. Any interval that is selected in the UI will be inutes when stored in the database.	
			Name	Description	
			Minutes	An integer indicating the number of minutes between each interval.	
			For example, ev	very hour:	
			"Interval": "Minutes }		
		Daily	A dictionary that indicates a job scheduled to run every day at the same time with the parameter:		
			Name	Description	
				Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
			For example, da	nily at 11:30 pm:	
			"Daily": {     "Time": }	"2022-02-25T23:30:00Z"	
		Weekly		It indicates a job scheduled to run on a specific day or k at the same time with the parameters:	
			Name	Description	
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC	

Name	In	Description	Description		
		Name	Description		
			Name	Description	
				time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
			Days	An array of values representing the days of the week on which to run the job. These can either be entered as integers (0 for Sunday, 1 for Monday, etc.) or as days of the week (e.g. "Sunday").	
			For example, ev	very Monday, Wednesday and Friday at 5:30 pm:	
			"Fric	[ day", nesday",	
		othe	er schedules, only	wagger Example Value may show examples of various the schedules shown here—that are available in the or this functionality—are valid for this endpoint.	
		For example	::		
			nn": { .y": { ime": "2022-05-	-27T17:30:00Z"	
		Or:			
			nn": { (ly": { Days": [  "Monday",  "Wednesday",  "Friday"		

Name	In	Description	
		], "Time": "2022-05-27T17:30:00Z" }	
		Tip: There are two types of synchronization schedules available for CAs—Full and Incremental. You do not necessarily need to configure both types. A full scan reads all the certificates and certificate requests in the CA database and synchronizes them to Keyfactor Command regardless of their current state in Keyfactor Command. An incremental scan reads the certificates and certificate requests in the CA database that have been generated since the last full or incremental scan and synchronizes them to Keyfactor Command. A common configuration would be a full scan once or twice a week to provide a clean image of the CA database with a frequent incremental scan to provide timely updates to Keyfactor Command. For a large CA database, a full scan can take a long time to complete. Since an incremental scan only synchronizes updates that have occurred to the CA database since the last synchronization was run, this process is generally quick (other than for the initial synchronization when Keyfactor Command is first installed). The frequency of the incremental scans would depend on the volume of certificate requests coming into the CA.	
IncrementalScan	Body	The schedule for the incremental synchronization of this certificate authority. The following schedule types are supported:	
		Name Description	
		Off Turn off a previously configured schedule.	
			Interval A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database.
		Name Description	
		Minutes An integer indicating the number of minutes between each interval.	
		For example, every hour:	
		"Interval": {	

Name	In	Description		
		Name	e Description	
			"Minutes	s": 60
		Daily	A dictionary that	at indicates a job scheduled to run every day at the same arameter:
			Name	Description
		Weekly	Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
			For example, da	aily at 11:30 pm:
			"Daily": {     "Time": }	"2022-02-25T23:30:00Z"
				nt indicates a job scheduled to run on a specific day or k at the same time with the parameters:
			Name	Description
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
			Days	An array of values representing the days of the week on which to run the job. These can either be entered as integers (0 for Sunday, 1 for Monday, etc.) or as days of the week (e.g. "Sunday").
			For example, ev "Weekly": {     "Days":     "Mono	]

Name	In	Description		
		Name	Description	
			"Wednesday",     "Friday" ],     "Time": "2022-02-27T17:30:00Z" }	
		othe	e: Although the Swagger Example Value may show examples of various er schedules, only the schedules shown here—that are available in the nagement Portal for this functionality—are valid for this endpoint.	
ThresholdCheck	Body	The schedule for threshold monitoring checks on this certificate authority (see <i>Monit-orThresholds</i> ). The following schedule types are supported:  Name  Description		
		Off	Turn off a previously configured schedule.	
		Interval	A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database.	
			Name Description	
			Minutes An integer indicating the number of minutes between each interval.	
			For example, every hour:	
			"Interval": {     "Minutes": 60 }	
		Daily	A dictionary that indicates a job scheduled to run every day at the same time with the parameter:	

Name	In	Description			
		Name	Name Description		
			Name	e Description	
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
			For exam	mple, daily at 11:30 pm:	
				ly": { Time": "2022-02-25T23:30:00Z"	
		othe	r schedules	gh the Swagger Example Value may show examples of various es, only the schedules shown here—that are available in the Portal for this functionality—are valid for this endpoint.	
САТуре	Body	An integer in  • 0—DCC  • 1—HT	ОМ	he type of CA:	
AuthCer- tificatePassword	Body	An array indicating the password for the certificate to use to authenticate to the EJBCA CA.  Supported methods to store certificate and associated password information are:  • Store the credential information in the Keyfactor secrets table.  A Keyfactor secret is a user-defined username or password that is encrypted and stored securely in the Keyfactor Command database.  • Load the credential information from a PAM provider.  See Privileged Access Management (PAM) in the Keyfactor Command Reference Guide and PAM Providers on page 709 for more information.			
		Value	ι	Description	
		SecretValu	A string containing the password used to security the EJBCA CA client authentication certificate.		
		Parameters	s A	An array indicating the parameters to supply for PAM authen-	

Name	In	Description				
		Value	Description			
			tication. These will vary depending on the PAM provider.			
		Provider	A string indicating the ID of the PAM provider.  Use the GET /PamProviders method (see GET PAM Providers on page 724) to retrieve a list of all the PAM providers to determine the ID.			
		For example, the password stored as a Keyfactor secret will look like:				
		{     "SecretValue": "MySuperSecretPassword" }				
		The password stored as a CyberArk PAM secret will look like (where the Provider value—1 in this example—is the Id value from GET PAM Providers on page 724 and Folder and Object reference the folder name and object name in the CyberArk safe				
		<pre>{     "Provider": "1",     "Parameters":{         "Folder":"MyFolderName",         "Object":"MyEJBCAClientAuthPassword"     } }</pre>				
		The password stored as a Delinea PAM secret will look like (where the Provider value—1 in this example—is the Id value from GET PAM Providers on page 724 and the SecretId is the ID if the secret created in the Delinea secret server for this purpose):				
		<pre>{     "Provider": "1",     "Parameters":{         "SecretId":"MyEJBCAPasswordId"     } }</pre>				
		Due to its sensitive	nature, this value is not returned in responses.			
AuthCertificate	Body	tication to the EJBC/ for synchronization,	information about the client certificate used to provide authen-A CA. This certificate is used to authenticate to the EJBCA database enrollment and management of certificates.  me as for AuthCertificatePassword.			

Name	In	Description
EnforceUniqueDN	Body	A Boolean that sets whether the unique DN requirement is enforced on the CA ( <i>true</i> ) or not ( <i>false</i> ).  Checking this will cause Keyfactor Command, upon enrollment, to search the EJBCA CA for end entities with DNs that match the DN in the certificate request. If a matching DN is found, the process will update the existing end entity in EJBCA with the new certificate request information rather than creating a new end entity. If you enable this option in Keyfactor Command, it must also be enabled on the matching EJBCA CA. A mismatch in these settings can result in enrollment failures.  This setting applies to HTTPS CAs only.
LastScan	Body	A string indicating the date, in UTC, on which a synchronization was last performed for the CA.

Table 169: PUT Certificate Authority Response Data

Name	Description			
Id	An integer indicating the Keyfactor Command identifier for the certificate authority. The ID is automatically assigned by Keyfactor Command.			
LogicalName	A string indicating the logical name of the certificate authority.			
HostName	A string indicating the DNS hostname (for DCOM configurations) or URL (for HTTPS configurations) of the certificate authority (e.g. myca.keyexample.com or https://myca.keyexample.com).			
Delegate	A Boolean that sets whether management interactions with the certificate authority via Keyfactor Command should be done in the context of the user making the request ( <i>true</i> ). If set to <i>false</i> , these interactions are done in the context of the service account under which the Keyfactor Command application pool is running unless <i>ExplicitCredentials</i> is true.			
	Important: Delegation is only supported with Microsoft CAs and has limitations. Be sure to read more about delegation in Certificate Authority Operations: Adding or Modifying a CA Record in the Keyfactor Command Reference Guide before setting this option to true.			
DelegateEnrollment	A Boolean that sets whether enrollment to the certificate authority via Keyfactor Command should be done in the context of the user making the request ( <i>true</i> ). If set to <i>false</i> , enrollment is done in the context of the service account under which the Keyfactor Command application pool is running unless <i>ExplicitCredentials</i> is true.			
	Important: Delegation is only supported with Microsoft CAs and has limitations. Be sure to read more about delegation in <i>Certificate Authority Operations: Adding or Modifying a CA Record</i> in the <i>Keyfactor Command Reference Guide</i> before setting this option to true.			
ForestRoot	A string indicating the forest root name or DNS domain name for the certificate authority (e.g. keyexample.com).			
	Note: This field is retained for legacy purposes and will auto-populate with the value provided in the <i>ConfigurationTenant</i> field.			
ConfigurationTenant	A string indicating the forest root name or DNS domain name for the certificate authority (e.g. keyexample.com).  For EJBCA CAs, this is a reference ID and does not need to be the DNS domain name. The short hostname of the EJBCA CA server makes a good reference ID.			

Name	Description
	Important: EJBCA and Microsoft CAs cannot be configured with the same Configuration Tenant, so do not set this to the DNS domain name for an EJBCA CA if you will also be configuring Microsoft CAs in the same DNS domain.
Remote	A Boolean that sets whether communications with the certificate authority are done via a Keyfactor Windows Orchestrator configured to manage remote CAs. If set to <i>true</i> , a value must be provided for the <i>Agent</i> . The default is <i>false</i> .
Agent	A string indicating the GUID of the Keyfactor Windows Orchestrator or Keyfactor Universal Orchestrator configured to manage the certificate authority (see <i>Remote</i> ).
Standalone	A Boolean that sets whether the certificate authority is a standalone CA ( <i>true</i> ) or not ( <i>false</i> ). If both <i>Standalone</i> is set to <i>true</i> and <i>AllowedEnrollmentTypes</i> is set to 1 or 3, <i>KeyRetention</i> may be set. The default is <i>false</i> .
MonitorThresholds	A Boolean that sets whether threshold monitoring is enabled. If set to <i>true</i> , email alerts will be sent when certificate issuance or failures (including denials) since the last threshold alert was sent falls outside the configured limits. If this option is set to <i>true</i> , the following additional fields should also be set:  • IssuanceMax  • IssuanceMin  • FailureMax  The DenialMax field has been deprecated and should always be zero.  Monitoring is not supported for CAs accessed with the Keyfactor Windows Orchestrator or Keyfactor Universal Orchestrator.  The default is <i>false</i> .  See also <i>ThresholdCheck</i> to configure the monitoring frequency.  Note: For full functionality of threshold monitoring, you must also configure email recipients for threshold alerts. These are configured globally rather than on a CA-by-CA basis. See <i>Certificate Authority Monitoring</i> in the <i>Keyfactor Command Reference Guide</i> for more information.
IssuanceMax	An integer that sets the maximum number of certificates that can be issued in the period between scheduled threshold monitoring alert emails before an alert is triggered. If more certificates than this are issued in the period, a notification will be included in the threshold monitoring email. This value is unset by default.
IssuanceMin	An integer that sets the minimum number of certificates that should be issued in the period between scheduled threshold monitoring alert emails before an alert is triggered. If fewer certificates than this are issued in the period, a notification will be included in the threshold monitoring email. This value is unset by default.

Name	Description			
FailureMax	An integer that sets the maximum number of certificate requests that can fail or be denied in the period between scheduled threshold monitoring alert emails before an alert is triggered. If more certificate requests than this fail in the period, a notification will be included in the threshold monitoring email. This value is unset by default.			
RFCEnforcement	CA must include at least one DNS ment Portal, this causes the CN en SAN, which the user can either cha	icate enrollments made through Keyfactor Command for this SAN (true) or not (false). In the Keyfactor Command Managetered in PFX enrollment to automatically be replicated as a lange or accept. For CSR enrollment, if the CSR does not have a automatically be added to the certificate if this is set.		
	Tip: The RFCEnforcement option at the CA level is used only for standalone CAs. RFC enforcement for enterprise CAs is configured on a template-by-template basis (see PUT Templates on page 1195).			
Properties	Additional properties about the certificate authority. This field is used to store the configuration for the <i>Sync External Certificates</i> option. This option allows foreign certificates that have been imported into a Microsoft CA to be synchronized to Keyfactor Command along with the certificates issued by the Microsoft CA. The setting is referenced using the following format:  {\"syncExternal\":true} OR {\"syncExternal\":false}			
AllowedEn- rollmentTypes	An integer that sets the type(s) of the certificate authority. Possible	enrollment that are allowed through Keyfactor Command for values are:		
	Value	Description		
	1	PFX Enrollment		
	2	CSR Enrollment		
	3 PFX and CSR Enrollment			
	This value is unset by default.			
KeyRetention	An integer that sets the type of ke ible values are:	y retention to enable for the certificate authority, if any. Poss-		
	Value	Description		
	0	Key Retention Disabled		
	1	Indefinite		

Name	Description			
	Value	Description		
	2	After Expiration		
	3	From Issuance		
	Values of 2 and 3 require setting <i>K</i> . This value is unset by default.	eyRetentionDays.		
	Tip: The KeyRetention option at the CA level is used only for standalone CAs. Key retention for enterprise CAs is configured on a template-by-template basis (see PUT Templates on page 1195).  KeyRetention on a CA may only be set to a value other than zero if both Standalone is set to true and AllowedEnrollmentTypes is set to 1 or 3. Some level of private key retention must be configured when using PFX enrollment with a standalone CA. See Certificate Authority Operations: Adding or Modifying a CA Record in the Keyfactor Command Reference Guide for more information.			
KeyRetentionDays		of days for which to retain the private keys for certificates before scheduling them for deletion. This value is unset by		
ExplicitCredentials	A Boolean that sets whether explicit credentials are enabled for this certificate aut or not (false). Set this to true for CAs that do not support integrated authentication configured for integrated authentication and enter credentials in the ExplicitUser a citPassword fields. This option is only supported for Microsoft CAs. The default is for			
	tication is not supported. I Microsoft CAs, Keyfactor C servers joined to the local	rue primarily for Microsoft CAs where integrated authen- ntegrated authentication is generally supported for A gateways, or Keyfactor CA management gateways on Active Directory forest in which Keyfactor Command is rectory forests in a two-way trust with this forest.		
SubscriberTerms		d a checkbox on the enrollment pages to force users to agree rolling (true) or not (false). The default is <i>false</i> .		
		e custom terms using the <i>URL to Subscriber Terms</i> applic- ion Settings: Enrollment Tab in the Keyfactor Command Refer- nation.		
ExplicitUser	the forest in which the Microsoft C	n the format DOMAIN\username, for a service account user in CA resides or, for non-domain-joined machines, local machine e on which the CA is installed when ExplicitCredentials is set		

## Description Name to true. Tip: This service account user needs appropriate permissions in the Microsoft CA security settings to accomplish the tasks you plan to carry out for this CA through Keyfactor Command. For example: · Certificate enrollment · Certificate revocation Certificate key recovery • Certificate request approval and denial These tasks will be carried out on the CA in the context of the credentials you provide here. Access control for these tasks on CAs is controlled with Keyfactor Command security (see Security Roles and Identities in the Keyfactor Command Reference Guide) and the AllowedRequesters option. **Note:** When the *ExplicitCredentials* option is configured, enrollment and other tasks (e.g. revocation) is done in the context of the user configured here, not the user making the request in Keyfactor Command. This overrides the existing AD security policy used by Keyfactor Command. **ExplicitPassword** A string containing the password for the ExplicitUser. A Boolean that sets whether the allowed requesters option is enabled (true) or not (false). See UseAllowedRequesters also AllowedRequesters. The default is false. **Tip:** This option is supported for all CAs, but it must be used for Microsoft CAs where integrated authentication is not supported and EJBCA CAs. Integrated authentication is generally supported for Microsoft CAs, Keyfactor CA gateways, or Keyfactor CA management gateways on servers joined to the local Active Directory forest in which Keyfactor Command is installed and any Active Directory forests in a two-way trust with this forest. Since Keyfactor Command cannot make use of the access control model of the CA itself to determine which users can enroll for certificates at either a template or CA level without using integrated authentication, this setting replaces that functionality. This setting is similar to setting request certificates for the selected security roles at the CA level on a Microsoft CA. Tip: For CAs in a two-way trust you don't usually need to enable UseAllowedRequesters on the CA, though this may be required in some circumstances depending on the security configuration in the environment. However, templates for a



two-way trust environment always require configuration of this option at a template level to support enrollment (see *Configuring Template Options* in the *Keyfactor* 

Command Reference Guide and see PUT Templates on page 1195).

#### Description Name An array of Keyfactor Command security roles that are allowed to enroll for certificates via AllowedRequesters Keyfactor Command for this CA. For example: "AllowedRequesters": [ "Power Users", "Read Only" ] The allowed requesters option is used to select Keyfactor Command security roles that a user must belong to in order to successfully enroll for certificates in Keyfactor Command via this CA. This is used for EJBCA CAs and Microsoft CAs where integrated authentication is not supported. Integrated authentication is generally supported for Microsoft CAs, Keyfactor CA gateways, or Keyfactor CA management gateways on servers joined to the local Active Directory forest in which Keyfactor Command is installed and any Active Directory forests in a two-way trust with this forest. Since Keyfactor Command cannot make use of the access control model of the CA itself to determine which users can enroll for certificates at either a template or CA level without using integrated authentication, this setting replaces that functionality. This setting is similar to setting request certificates for the selected security roles at the CA level on a Microsoft CA. In addition to granting permissions at the CA level, you need to enable the UseAllowedRequesters option to grant permissions on a template-by-template basis (see PUT Templates on page 1195). The values set here are only considered if *UseAllowedRequesters* is set to *true*. FullScan The schedule for the full synchronization of this certificate authority. The following schedule types are supported: Name Description Off Turn off a previously configured schedule. Interval A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database. Name Description Minutes An integer indicating the number of minutes between each interval. For example, every hour:

Name	Description		
	Name	Description	
		"Interval": {     "Minutes": 60 }	
	Daily	A dictionary that indicates a job scheduled to run every day at the same time with the parameter:	
		Name Description	
		Time The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
		For example, daily at 11:30 pm:	
		"Daily": {     "Time": "2022-02-25T23:30:00Z" }	
	Weekly	A dictionary that indicates a job scheduled to run on a specific day or days every week at the same time with the parameters:	
		Name Description	
		Time The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
		Days  An array of values representing the days of the week on which to run the job. These can either be entered as integers (0 for Sunday, 1 for Monday, etc.) or as days of the week (e.g. "Sunday").	
		For example, every Monday, Wednesday and Friday at 5:30 pm:	
		"Weekly": {     "Days": [     "Monday",     "Wednesday",	
		"Friday"	

Name	Description		
	Name	Description	
		], "Time": "2022-02-27T17:30:00Z" }	
	sched	: Although the Swagger Example Value may show examples of various other dules, only the schedules shown here—that are available in the Management all for this functionality—are valid for this endpoint.	
	Tip: There are two types of synchronization schedules available for CA mental. You do not necessarily need to configure both types. A full scar certificates and certificate requests in the CA database and synchronize Keyfactor Command regardless of their current state in Keyfactor Commental scan reads the certificates and certificate requests in the CA databeen generated since the last full or incremental scan and synchronizes Keyfactor Command. A common configuration would be a full scan one week to provide a clean image of the CA database with a frequent increprovide timely updates to Keyfactor Command. For a large CA database take a long time to complete. Since an incremental scan only synchronication was rugenerally quick (other than for the initial synchronization when Keyfact first installed). The frequency of the incremental scans would depend certificate requests coming into the CA.		
IncrementalScan		for the incremental synchronization of this certificate authority. The following es are supported:	
	Name	Description	
	Off	Turn off a previously configured schedule.	
	Interval	A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database.	
		Name Description	
		Minutes An integer indicating the number of minutes between each interval.	

Name	Description		
	Name	Description	
		For example, eve	ery hour:
		"Interval":     "Minutes' }	
	Daily	A dictionary that with the parame	indicates a job scheduled to run every day at the same time eter:
		Name	Description
	should be given using the ISO 8601 UTC	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
		For example, dai	ily at 11:30 pm:
		"Time":	"2022-02-25T23:30:00Z"
	Weekly		t indicates a job scheduled to run on a specific day or days are same time with the parameters:
		Name	Description
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
		Days	An array of values representing the days of the week on which to run the job. These can either be entered as integers (0 for Sunday, 1 for Monday, etc.) or as days of the week (e.g. "Sunday").
		For example, even "Weekly": {     "Days":     "Monda	

## Description Name Description Name "Wednesday", "Friday" ], "Time": "2022-02-27T17:30:00Z" Note: Although the Swagger Example Value may show examples of various other schedules, only the schedules shown here—that are available in the Management Portal for this functionality—are valid for this endpoint. ThresholdCheck The schedule for threshold monitoring checks on this certificate authority (see MonitorThresholds). The following schedule types are supported: Description Name Off Turn off a previously configured schedule. Interval A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database. **Description** Name Minutes An integer indicating the number of minutes between each interval. For example, every hour: "Interval": { "Minutes": 60 } Daily A dictionary that indicates a job scheduled to run every day at the same time

with the parameter:

Name	Description		
	Name	Description	
		Name	Description
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
		For example, da	aily at 11:30 pm:
		"Daily": {     "Time": }	"2022-02-25T23:30:00Z"
	schedu	ıles, only the sch	ragger Example Value may show examples of various other edules shown here—that are available in the Management ality—are valid for this endpoint.
САТуре	An integer indicating the type of CA:  • 0—DCOM  • 1—HTTPS		
AuthCer- tificatePassword			rd for the certificate to use to authenticate to the EJBCA CA. rtificate and associated password information are:
	<ul> <li>Store the credential information in the Keyfactor secrets table.         A Keyfactor secret is a user-defined username or password that is encrypted and stored securely in the Keyfactor Command database.     </li> <li>Load the credential information from a PAM provider.         See Privileged Access Management (PAM) in the Keyfactor Command Reference Guide and PAM Providers on page 709 for more information.     </li> </ul>		
	Value	Descrip	tion
	SecretValue	_	containing the password used to security the EJBCA CA client cation certificate.
	Parameters		indicating the parameters to supply for PAM authentication. Il vary depending on the PAM provider.

Name	Description	Description			
	Value	Description			
	Provider	A string indicating the ID of the PAM provider.  Use the GET /PamProviders method (see GET PAM Providers on page 724) to retrieve a list of all the PAM providers to determine the ID.			
	Due to its sensitive r	nature, this value is not returned in responses.			
AuthCertificate	the EJBCA CA. This controllment and man	An array containing information about the client certificate used to provide authentication to the EJBCA CA. This certificate is used to authenticate to the EJBCA database for synchronization, enrollment and management of certificates.  Authentication certificate values include:			
	Value	Description			
	IssuedDN	A string indicating the distinguished name of the client certificate used to authenticate to the EJBCA CA in X.500 format. For example: "IssuedDN": "CN=SuperAdmin,OU=IT,O=\"Key Example, Inc.\",L=Independence,ST=OH,C=US"			
	IssuerDN	A string indicating the distinguished name of the EJBCA CA in X.500 format.			
	Thumbprint	A string indicating the thumbprint of the client certificate used to authenticate to the EJBCA CA.			
	ExpirationDate	A string indicating the expiration date of the client certificate used to authenticate to the EJBCA CA.			
EnforceUniqueDN	A Boolean that sets whether the unique DN requirement is enforced on the CA ( <i>true</i> ) or not ( <i>false</i> ).  Checking this will cause Keyfactor Command, upon enrollment, to search the EJBCA CA for end entities with DNs that match the DN in the certificate request. If a matching DN is found, the process will update the existing end entity in EJBCA with the new certificate request information rather than creating a new end entity. If you enable this option in Keyfactor Command, it must also be enabled on the matching EJBCA CA. A mismatch in these settings can result in enrollment failures.  This setting applies to HTTPS CAs only.				
LastScan	A string indicating th	ne date, in UTC, on which a synchronization was last performed for the CA.			

# 2.2.7.6 POST Certificate Authority Test

The POST /CertificateAuthority/Test method is used to validate that a connection can be made to the certificate authority with the provided information. This method returns HTTP 200 OK on a success with details for the success or failure of the CA validation.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: PkiManagement: *Read* 

Table 170: POST Certificate Authority Test Input Parameters

Name	In	Description	
LogicalName	Body	<b>Required</b> . A string indicating the logical name of the certificate authority.	
HostName	Body	<b>Required</b> . A string indicating the DNS hostname (for DCOM configurations) or URL (for HTTPS configurations) of the certificate authority (e.g. myca.keyexample.com or https://myca.keyexample.com).	
ConfigurationTenant	Body	Required*. A string indicating the forest root name or DNS domain name for the certificate authority (e.g. keyexample.com).  This parameter is required for Microsoft CAs.	
AuthCertificatePassword	Body	<b>Required</b> *. An array indicating the password for the PKCS#12 client certificate to use to authenticate to the EJBCA CA. The password is provided in the following format:	
		{     "SecretValue": "MySuperSecretPassword" }	
		This parameter is required for EJBCA CAs.	
AuthCertificate	Body	<b>Required</b> *. An array containing the base-64 encoded PKCS#12 client certificate used to provide authentication to the EJBCA CA. This certificate is used to authenticate to the EJBCA database for synchronization, enrollment and management of certificates. The certificate is provided in the following format:	
		{     "SecretValue": "MIACAQMwgAY CAwGQAAAA" }	
		This parameter is required for EJBCA CAs.	
САТуре	Body	An integer indicating the type of CA:  • 0—DCOM  Use this option for Microsoft CAs and CA gateways.  • 1—HTTPS  Use this option for EJBCA CAs.  The default is 0.	

Table 171: POST Certificate Authority Test Response Data

Name	Description
Success	A Boolean that indicates whether the CA could successfully be reached (True) or not (False).
Message	A string indicating a message about the validation test of the certificate authority.

## 2.2.7.7 POST Certificate Authority PublishCRL

The POST /CertificateAuthority/PublishCRL method is used to publish a Certificate Revocation List from a specified Certificate Authority to its defined publication points. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: Certificates: *Revoke* 

Permissions for certificates can be set at either the global or certificate collection level. See *Certificate Permissions* in the *Keyfactor Command Reference Guide* for more information about global vs collection permissions.

Table 172: POST Certificate Authority PublishCRL Input Parameters

Name	In	Description
CertificateAuthorityHostName	Body	The host name of the machine hosting the CA. This field is optional, but is recommended.
CertificateAuthorityLogicalName	Body	Required. The logical name of the CA.

## 2.2.8 Certificate Collections

The Certificate Collections component of the Keyfactor API is used to create, list and set permissions on certificate collections.

Table 173: Certificate Collections Endpoints

Endpoint	Method	Description	Link
/{id}	GET	Returns the certificate collection with the specified ID.	GET Certificate Collections  ID on the next page
/{name}	GET	Returns the certificate collection with the specified name.	GET Certificate Collections Name on page 353
/	GET	Returns all certificate collections with details about the collection configuration.	GET Certificate Collections on page 355

Endpoint	Method	Description	Link
/	POST	Creates a new certificate collection.	POST Certificate Collections on page 357
/	PUT	Updates an existing certificate collection.	PUT Certificate Collections on page 363
/Copy	POST	Creates a new certificate collection based on an existing collection.	POST Certificate Collections Copy on page 367
/{id}/Permissions	POST	Grants the specified collection permissions for the specified role to the specified certificate collection.	POST Certificate Collections ID Permissions on page 373
		Note: This endpoint will be removed in version 11.	

#### 2.2.8.1 GET Certificate Collections ID

The GET /CertificateCollections/{id} method is used to retrieve details for a certificate collection with the specified ID. This method returns HTTP 200 OK on a success with details for the certificate collection.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: Certificates: *Read* 

Table 174: GET CertificateCollections {id} Input Parameters

Name	In	Description
id	Path	<b>Required</b> . An integer indicating the ID of the certificate collection to retrieve.  Use the <i>GET /CertificateCollections</i> method (see <u>GET Certificates on page 237</u> ) to retrieve a list of all the certificate collections to determine the certificate collection ID.

Table 175: GET CertificateCollections {id} Response Data

Name	Description		
ID	The Keyfactor Command reference ID for the certificate collection. The ID is automatically assigned by Keyfactor Command.		
Name	The name for the certificate collection. This name appears at the top of the page in the Keyfactor Command Management Portal for this collection and can be configured to appear on the Management Portal menu under Certificate Collections. It will also appear in other places within the Management Portal where you can reference certificate collections (e.g. expiration alerts and certain reports). Because it can appear on the menu and in selection dropdowns, the name should be fairly short.		
Description		s description appears at the top of the page in the Manage- n be more detailed than the collection name.	
Automated	An internally used Keyfactor Command field.		
Content	A string containing the search criteria for the collection.		
DuplicationField	An integer that sets the type of de-duplication (a.k.a. "ignore renewed certificate results by") to apply to the collection when using the collection in areas of Keyfactor Command that apply deduplication (e.g. expiration alerts). For more information, see Saving Search Criteria as a Collection in the Keyfactor Command Reference Guide. Possible values are:		
	Value	Description	
	0	None	
	1	Common Name	
	2	Distinguished Name	
	3 Principal Name		
ShowOnDashboard	A Boolean that sets whether the results from this collection are included on the Management Portal dashboard <i>Certificate Counts by Collection</i> graph ( <i>true</i> ) or not ( <i>false</i> ).		
Favorite	A Boolean that sets whether the collection appears on the Navigator—on the <i>Certificates</i> top-level menu dropdown—( <i>true</i> ) or not ( <i>false</i> ).		

#### 2.2.8.2 GET Certificate Collections Name

The GET /CertificateCollections/{name} method is used to retrieve details for a certificate collection with the specified name. This method returns HTTP 200 OK on a success with details for the certificate collection.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: Certificates: *Read* 

Table 176: GET CertificateCollections Name Input Parameters

Name	In	Description
name	Path	Required. A string indicating the name of the certificate collection to retrieve.  Use the GET /CertificateCollections method (see GET Certificates on page 237) to retrieve a list of all the certificate collections to determine the certificate collection name.  Tip: When using the Keyfactor API Endpoint Utility, provide this name without quota-
		tion marks.

Table 177: GET CertificateCollections ID Response Data

Name	Description		
ID	The Keyfactor Command reference ID for the certificate collection. The ID is automatically assigned by Keyfactor Command.		
Name	The name for the certificate collection. This name appears at the top of the page in the Keyfactor Command Management Portal for this collection and can be configured to appear on the Management Portal menu under Certificate Collections. It will also appear in other places within the Management Portal where you can reference certificate collections (e.g. expiration alerts and certain reports). Because it can appear on the menu and in selection dropdowns, the name should be fairly short.		
Description	The description for the collection. This description appears at the top of the page in the Management Portal for this collection and can be more detailed than the collection name.		
Automated	An internally used Keyfactor Command field.		
Content	A string containing the search criteria for the collection.		
DuplicationField	An integer that sets the type of de-duplication (a.k.a. "ignore renewed certificate results by") to apply to the collection when using the collection in areas of Keyfactor Command that apply deduplication (e.g. expiration alerts). For more information, see <i>Saving Search Criteria as a Collection</i> in the <i>Keyfactor Command Reference Guide</i> . Possible values are:		
	Value	Description	
	0	None	
	1	Common Name	
	2	Distinguished Name	
	3	Principal Name	
ShowOnDashboard	A Boolean that sets whether the results from this collection are included on the Management Portal dashboard <i>Certificate Counts by Collection</i> graph ( <i>true</i> ) or not ( <i>false</i> ).		
Favorite	A Boolean that sets whether the collection appears on the Navigator—on the <i>Certificates</i> top-level menu dropdown—( <i>true</i> ) or not ( <i>false</i> ).		

#### 2.2.8.3 GET Certificate Collections

The GET /CertificateCollections method is used to return a list of all certificate collections. This method returns HTTP 200 OK on a success with details about each defined certificate collection. This method allows URL parameters to specify paging and the level of information detail.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: Certificates: *Read* 

Table 178: GET Certificate Collections Input Parameters

Name	In	Description
queryString	Query	A string containing a query to limit the results (e.g. field1 -eq value1 AND field2 -gt value2). The default is to return all records. Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns for the same feature. For querying guidelines, refer to the Keyfactor Command Reference Guide: Using the Collection Manager Search Feature. The query fields supported for this endpoint are:  • Name  • Query
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>Name</i> .
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.

Table 179: GET CertificateCollections Response Data

Name	Description			
ID	The Keyfactor Command reference ID for the certificate collection. The ID is automatically assigned by Keyfactor Command.			
Name	The name for the certificate collection. This name appears at the top of the page in the Keyfactor Command Management Portal for this collection and can be configured to appear on the Management Portal menu under Certificate Collections. It will also appear in other places within the Management Portal where you can reference certificate collections (e.g. expiration alerts and certain reports). Because it can appear on the menu and in selection dropdowns, the name should be fairly short.			
Description	The description for the collection. This description appears at the top of the page in the Management Portal for this collection and can be more detailed than the collection name.			
Automated	An internally used Keyfactor Command field.			
Content	A string containing the search criteria for the collection.			
DuplicationField	An integer that sets the type of de-duplication (a.k.a. "ignore renewed certificate results by") to apply to the collection when using the collection in areas of Keyfactor Command that apply deduplication (e.g. expiration alerts). For more information, see <i>Saving Search Criteria as a Collection</i> in the <i>Keyfactor Command Reference Guide</i> . Possible values are:			
	Value	Description		
	0	None		
	1	Common Name		
	2	Distinguished Name		
	3 Principal Name			
ShowOnDashboard	A Boolean that sets whether the results from this collection are included on the Management Portal dashboard <i>Certificate Counts by Collection</i> graph ( <i>true</i> ) or not ( <i>false</i> ).			
Favorite	A Boolean that sets whether the collection appears on the Navigator—on the <i>Certificates</i> top-level menu dropdown—( <i>true</i> ) or not ( <i>false</i> ).			

#### 2.2.8.4 POST Certificate Collections

The POST /CertificateCollections method is used to create a new saved collection of certificates or update an existing collection. This method returns HTTP 200 OK on a success with details about the certificate collection.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature:

Certificates: Read

Certificate Collections: *Modify* 

Table 180: POST Certificate Collections Input Parameters

Name	In	Description	
Name	Body	Required. The name for the certificate collection. This name appears at the top of the page in the Keyfactor Command Management Portal for this collection and can be configured to appear on the Management Portal menu under Certificate Collections. It will also appear in other places within the Management Portal where you can reference certificate collections (e.g. expiration alerts and certain reports). Because it can appear on the menu and in selection dropdowns, the name should be fairly short.	
Description	Body	<b>Required</b> . The description for the collection. This description appears at the top of the page in the Management Portal for this collection and can be more detailed than the collection name.  See also <i>CopyFromId</i> .	
Query	Body	Required. A string containing the search criteria for the collection.  For example:  "Query": "(IssuedDate -ge \"%TODAY-7%\" AND  TemplateShortName -ne NULL) OR (IssuedDate -ge \"%TODAY-7%\" AND IssuerDN -contains \"keyexample\")"  See Certificate Search Pagein the Keyfactor Command Reference Guide for querying guidelines.  See also CopyFromId.	
DuplicationField	Body	An integer that sets the type of de-duplication (a.k.a. "ignore renewed certificate results by") to apply to the collection when using the collection in areas of Keyfactor Command that apply de-duplication (e.g. expiration alerts). For more information, see <i>Saving Search Criteria as a Collection</i> in the <i>Keyfactor Command Reference Guide</i> . The default is 0. Possible values are:	
		Value	Description
		0	None
		1	Common Name
		2	Distinguished Name
		3	Principal Name
ShowOnDashboard	Body	A Boolean that sets whether the results from this collection are included on the Management Portal dashboard <i>Certificate Counts by Collection</i> graph ( <i>true</i> ) or not ( <i>false</i> ). The default is <i>false</i> .	
Favorite	Body	A Boolean that sets whether the collection appears on the Navigator—on the <i>Cert ficates</i> top-level menu dropdown—( <i>true</i> ) or not ( <i>false</i> ). The default is <i>false</i> .	

Name	In	Description	
CopyFromId	Body	An integer identifying an existing certificate collection from which to copy the query string.  Use the GET /CertificateCollections method (see GET Certificate Collections on page 355) to locate the ID of the collection whose query you wish to copy.  When you use this parameter, the permissions, query and description of the existing collection are copied to the new collection. Providing the Query or Description parameter in the request overrides the copied value and replaces it with the value provided in the request if the requesting user has global Read permissions for certificates. If the requesting user is granted Read permissions to the collection via collection-level security rather than global security, the Query the user provides will be appended to the existing query rather than overwriting it. See the below example.	
		Example: Gina wants to create a new collection using the CopyFromId option. She first uses GET /CertificateCollections/{id} to list the collection she plans to copy from and sees the following results:  {     "Id": 10,     "Name": "Keyexample Collection",     "Description": "Certificates in the Keyexample Domain",     "Automated": false,     "Content": "CN -contains \"keyexample.com\"",     "DuplicationField": 2,     "ShowOnDashboard": false,     "Favorite": true }	
		Gina wants her new certificate collection to retain the same collection-level permissions as the <i>Keyexample Collection</i> . However, she wants the collection to report on a different domain name. The <i>Keyexample Collection</i> is configured to grant collection-level permissions of <i>Read</i> , <i>Edit Metadata</i> , and <i>Download with Private Key</i> to the <i>Power Users</i> role.  At the Key Example company, users with the Power Users role do not have global certificate <i>Read</i> permissions because all certificate permissions are granted using certificate collection permissions. Only full Keyfactor Command administrators have global certificate <i>Read</i> permissions. Users with the Power Users role have <i>Modify</i> permissions for certificate collections to allow them to create new collections. This level of permissions is significant for what Gina wants to do. Gina holds the Power Users role and is not a full administrator.  Gina uses POST /CertificateCollections/Copy (or POST /CertificateCollections—the behavior and output would be the same) to	

Name In Description



create a new certificate collection using the *CopyFromId* option with the following command:

```
{
   "CopyFromId": 10,
   "Name": "Keyother Collection",
   "Description": "Certificates in the Keyother Domain",
   "Query": "CN -contains \"keyother.com\"",
   "DuplicationField": 2,
   "ShowOnDashboard": false,
   "Favorite": true
}
```

In the response, Gina sees the following:

```
{
    "Id": 15,
    "Name": "Keyother Collection",
    "Description": "Certificates in the Keyother Domain",
    "Automated": false,
    "Content": "(CN -contains \"keyexample.com\") AND (CN
-contains \"keyother.com\")",
    "Query": "(CN -contains \"keyexample.com\") AND (CN -contains \"keyother.com\")",
    "DuplicationField": 2,
    "ShowOnDashboard": false,
    "Favorite": true
}
```

Notice that Gina has not achieved her desired goal. The new collection contains a query for both the keyexample.com domain and the keyother.com domain. Gina's new query was appended to the existing query rather than overwriting the existing query. This happened because Gina does not have global *Read* permissions for certificates and is done to prevent a user from increasing the scope of certificates they can view.

Gina asks Martha, who is a full Keyfactor Command administrator and has the global *Read* permissions for certificates, to copy the collection for her. Martha first deletes the first Keyother Collection that Gina created and then runs the same command that Gina ran to create a new collection.

In the response, Martha sees the following:

```
{
"Id": 16,
```

Name	In	Description
		"Name": "Keyother Collection", "Description": "Certificates in the Keyother Domain", "Automated": false, "Content": "(CN -contains \"keyother.com\")", "Query": "(CN -contains \"keyother.com\")", "DuplicationField": 2, "ShowOnDashboard": false, "Favorite": true }
		Notice that when Martha runs the command, Gina's goal is achieved.

Table 181: POST Certificate Collections Response Data

Name	Description		
ID	The Keyfactor Command reference ID for the certificate collection. The ID is automatically assigned by Keyfactor Command.		
Name	The name for the certificate collection. This name appears at the top of the page in the Keyfactor Command Management Portal for this collection and can be configured to appear on the Management Portal menu under Certificate Collections. It will also appear in other places within the Management Portal where you can reference certificate collections (e.g. expiration alerts and certain reports). Because it can appear on the menu and in selection dropdowns, the name should be fairly short.		
Description	·	s description appears at the top of the page in the Manage- n be more detailed than the collection name.	
Content	A string containing the search criteria for the collection. This field contains the same value as Query and is retained for backwards compatibility.		
Query	A string containing the search criteria for the collection.		
DuplicationField	An integer that sets the type of de-duplication (a.k.a. "ignore renewed certificate results by") to apply to the collection when using the collection in areas of Keyfactor Command that apply deduplication (e.g. expiration alerts). For more information, see <i>Saving Search Criteria as a Collection</i> in the <i>Keyfactor Command Reference Guide</i> . Possible values are:		
	Value	Description	
	0	None	
	1	Common Name	
	2	Distinguished Name	
	3	Principal Name	
ShowOnDashboard	A Boolean that sets whether the results from this collection are included on the Management Portal dashboard <i>Certificate Counts by Collection</i> graph ( <i>true</i> ) or not ( <i>false</i> ).		
Favorite	A Boolean that sets whether the collection appears on the Navigator—on the <i>Certificates</i> top-level menu dropdown—( <i>true</i> ) or not ( <i>false</i> ).		

## 2.2.8.5 PUT Certificate Collections

The PUT /CertificateCollections method is used to update an existing saved collection of certificates. This method returns HTTP 200 OK on a success with details about the certificate collection.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature:

Certificates: Read

Certificate Collections: *Modify* 

Table 182: PUT CertificateCollections Input Parameters

Name	In	Description	
ID	Body	Required. The Keyfactor Command reference ID for the certificate collection. The ID is automatically assigned by Keyfactor Command.  Use the GET /CertificateCollections method (see GET Certificate Collections on page 355) to locate the ID of the collection you wish to update.	
Name	Body	Required. The name for the certificate collection. This name appears at the top of the page in the Keyfactor Command Management Portal for this collection and can be configured to appear on the Management Portal menu under Certificate Collections. It will also appear in other places within the Management Portal where you can reference certificate collections (e.g. expiration alerts and certain reports). Because it can appear on the menu and in selection dropdowns, the name should be fairly short.	
Description	Body	<b>Required</b> . The description for the collection. This description appears at the top of the page in the Management Portal for this collection and can be more detailed than the collection name.	
Query	Body	Required. A string containing the search criteria for the collection.  For example:  "Query": "(IssuedDate -ge \"%TODAY-7%\" AND  TemplateShortName -ne NULL) OR (IssuedDate -ge \"%TODAY-7%\" AND IssuerDN -contains \"keyexample\")"  See Certificate Search Pagein the Keyfactor Command Reference Guide for querying guidelines.	
DuplicationField	Body	results by") to apply to the collection Command that apply of	de-duplication (a.k.a. "ignore renewed certificate ction when using the collection in areas of de-duplication (e.g. expiration alerts). For more Criteria as a Collection in the Keyfactor Command D. Possible values are:
		Value	Description
		0	None
		1	Common Name
		2	Distinguished Name
		3	Principal Name
ShowOnDashboard	Body	A Boolean that sets whether the results from this collection are included on the Management Portal dashboard <i>Certificate Counts by Collection</i> graph ( <i>true</i> ) or not ( <i>false</i> ). The default is <i>false</i> .	

Name	In	Description
Favorite	Body	A Boolean that sets whether the collection appears on the Navigator—on the <i>Certificates</i> top-level menu dropdown—( <i>true</i> ) or not ( <i>false</i> ). The default is <i>false</i> .

Table 183: PUT CertificateCollections Response Data

Name	Description	
ID	The Keyfactor Command reference ID for the certificate collection. The ID is automatically assigned by Keyfactor Command.	
Name	The name for the certificate collection. This name appears at the top of the page in the Keyfactor Command Management Portal for this collection and can be configured to appear on the Management Portal menu under Certificate Collections. It will also appear in other places within the Management Portal where you can reference certificate collections (e.g. expiration alerts and certain reports). Because it can appear on the menu and in selection dropdowns, the name should be fairly short.	
Description	The description for the collection. This description appears at the top of the page in the Management Portal for this collection and can be more detailed than the collection name.	
Content	A string containing the search criteria for the collection. This field contains the same value as Query and is retained for backwards compatibility.	
Query	A string containing the search criteria for the collection.	
DuplicationField	An integer that sets the type of de-duplication (a.k.a. "ignore renewed certificate results by") to apply to the collection when using the collection in areas of Keyfactor Command that apply de duplication (e.g. expiration alerts). For more information, see <i>Saving Search Criteria as a Collection</i> in the <i>Keyfactor Command Reference Guide</i> . Possible values are:	
	Value	Description
	0	None
	1	Common Name
	2	Distinguished Name
	3	Principal Name
ShowOnDashboard	A Boolean that sets whether the results from this collection are included on the Management Portal dashboard <i>Certificate Counts by Collection</i> graph ( <i>true</i> ) or not ( <i>false</i> ).	
Favorite	A Boolean that sets whether the collection appears on the Navigator—on the <i>Certificates</i> top-level menu dropdown—( <i>true</i> ) or not ( <i>false</i> ).	

## 2.2.8.6 POST Certificate Collections Copy

The POST /CertificateCollections/Copy method is used to copy an existing saved collection of certificates in order to create a new collection. The permissions, query and description of the existing collection are copied to the new collection. Providing the *Query* or *Description* parameter in the request overrides the copied value and replaces it

with the value provided in the request. This method returns HTTP 200 OK on a success with details about the new certificate collection.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature:

Certificates: Read

Certificate Collections: Modify

Table 184: POST Certificate Collections Copy Input Parameters

Name	In	Description	
Name	Body	the page in the Keyfactor Comm can be configured to appear on Collections. It will also appear in where you can reference certific	tificate collection. This name appears at the top of hand Management Portal for this collection and the Management Portal menu under Certificate other places within the Management Portal cate collections (e.g. expiration alerts and certain on the menu and in selection dropdowns, the
Description	Body	<b>Required</b> . The description for the collection. This description appears at the top of the page in the Management Portal for this collection and can be more detailed than the collection name.  See also <i>CopyFromId</i> .	
Query	Body	For example:  "Query": "(IssuedDat  TemplateShortName -n  7%\" AND IssuerDN -c	e search criteria for the collection.  e -ge \"%TODAY-7%\" AND  e NULL) OR (IssuedDate -ge \"%TODAY- ontains \"keyexample\")"  e Keyfactor Command Reference Guide for
DuplicationField Body		An integer that sets the type of de-duplication (a.k.a. "ignore renewed certificate results by") to apply to the collection when using the collection in areas of Keyfactor Command that apply de-duplication (e.g. expiration alerts). For more information, see <i>Saving Search Criteria as a Collection</i> in the <i>Keyfactor Command Reference Guide</i> . The default is 0. Possible values are:	
		Value	Description
		0	None
		1	Common Name
		2	Distinguished Name
		3	Principal Name
ShowOnDashboard	Body	A Boolean that sets whether the results from this collection are included on the Management Portal dashboard <i>Certificate Counts by Collection</i> graph ( <i>true</i> ) or not ( <i>false</i> ). The default is <i>false</i> .	
Favorite	Body	A Boolean that sets whether the collection appears on the Navigator—on the <i>Certificates</i> top-level menu dropdown—( <i>true</i> ) or not ( <i>false</i> ). The default is <i>false</i> .	

Name	In	Description
CopyFromId	Body	An integer identifying an existing certificate collection from which to copy the query string.  Use the GET /CertificateCollections method (see GET Certificate Collections on page 355) to locate the ID of the collection whose query you wish to copy.  When you use this parameter, the permissions, query and description of the existing collection are copied to the new collection. Providing the Query or Description parameter in the request overrides the copied value and replaces it with the value provided in the request if the requesting user has global Read permissions for certificates. If the requesting user is granted Read permissions to the collection via collection-level security rather than global security, the Query the user provides will be appended to the existing query rather than overwriting it. See the below example.  Example: Gina wants to create a new collection using the CopyFromId option. She first uses GET /CertificateCollections/(id) to list the collection she plans to copy from and sees the following results:  {     "Id": 10,     "Name": "Keyexample Collection",     "Description": "Certificates in the Keyexample Domain",     "Automated": false,     "Content": "CN -contains \"keyexample.com\"",     "DuplicationField": 2,     "ShowOnDashboard": false,     "Favorite": true }
		Gina wants her new certificate collection to retain the same collection-level permissions as the <i>Keyexample Collection</i> . However, she wants the collection to report on a different domain name. The <i>Keyexample Collection</i> is configured to grant collection-level permissions of <i>Read</i> , <i>Edit Metadata</i> , and <i>Download with Private Key</i> to the <i>Power Users</i> role.  At the Key Example company, users with the Power Users role do not have global certificate <i>Read</i> permissions because all certificate permissions are granted using certificate collection permissions. Only full Keyfactor Command administrators have global certificate <i>Read</i> permissions. Users with the Power Users role have <i>Modify</i> permissions for certificate collections to allow them to create new collections. This level of permissions is significant for what Gina wants to do. Gina holds the Power Users role and is not a full administrator.  Gina uses POST /CertificateCollections/Copy (or POST /CertificateCollections—the behavior and output would be the same) to

Name In Description



create a new certificate collection using the *CopyFromId* option with the following command:

```
{
   "CopyFromId": 10,
   "Name": "Keyother Collection",
   "Description": "Certificates in the Keyother Domain",
   "Query": "CN -contains \"keyother.com\"",
   "DuplicationField": 2,
   "ShowOnDashboard": false,
   "Favorite": true
}
```

In the response, Gina sees the following:

```
{
    "Id": 15,
    "Name": "Keyother Collection",
    "Description": "Certificates in the Keyother Domain",
    "Automated": false,
    "Content": "(CN -contains \"keyexample.com\") AND (CN
-contains \"keyother.com\")",
    "Query": "(CN -contains \"keyexample.com\") AND (CN -contains \"keyother.com\")",
    "DuplicationField": 2,
    "ShowOnDashboard": false,
    "Favorite": true
}
```

Notice that Gina has not achieved her desired goal. The new collection contains a query for both the keyexample.com domain and the keyother.com domain. Gina's new query was appended to the existing query rather than overwriting the existing query. This happened because Gina does not have global *Read* permissions for certificates and is done to prevent a user from increasing the scope of certificates they can view.

Gina asks Martha, who is a full Keyfactor Command administrator and has the global *Read* permissions for certificates, to copy the collection for her. Martha first deletes the first Keyother Collection that Gina created and then runs the same command that Gina ran to create a new collection.

In the response, Martha sees the following:

```
{
    "Id": 16,
```

Name	In	Description
		"Name": "Keyother Collection", "Description": "Certificates in the Keyother Domain", "Automated": false, "Content": "(CN -contains \"keyother.com\")", "Query": "(CN -contains \"keyother.com\")", "DuplicationField": 2, "ShowOnDashboard": false, "Favorite": true }
		Notice that when Martha runs the command, Gina's goal is achieved.

Table 185: POST Certificate Collections Copy Response Data

Name	Description	
ID	The Keyfactor Command reference ID for the certificate collection. The ID is automatically assigned by Keyfactor Command.	
Name	The name for the certificate collection. This name appears at the top of the page in the Keyfactor Command Management Portal for this collection and can be configured to appear on the Management Portal menu under Certificate Collections. It will also appear in other places within the Management Portal where you can reference certificate collections (e.g. expiration alerts and certain reports). Because it can appear on the menu and in selection dropdowns, the name should be fairly short.	
Description	The description for the collection. This description appears at the top of the page in the Management Portal for this collection and can be more detailed than the collection name.	
Content	A string containing the search criteria for the collection. This field contains the same value as Query and is retained for backwards compatibility.	
Query	A string containing the search criteria for the collection.	
DuplicationField	An integer that sets the type of de-duplication (a.k.a. "ignore renewed certificate results by") to apply to the collection when using the collection in areas of Keyfactor Command that apply de duplication (e.g. expiration alerts). For more information, see <i>Saving Search Criteria as a Collection</i> in the <i>Keyfactor Command Reference Guide</i> . Possible values are:	
	Value	Description
	0	None
	1	Common Name
	2	Distinguished Name
	3	Principal Name
ShowOnDashboard	A Boolean that sets whether the results from this collection are included on the Management Portal dashboard <i>Certificate Counts by Collection</i> graph ( <i>true</i> ) or not ( <i>false</i> ).	
Favorite	A Boolean that sets whether the collection appears on the Navigator—on the <i>Certificates</i> top-level menu dropdown—( <i>true</i> ) or not ( <i>false</i> ).	

## 2.2.8.7 POST Certificate Collections ID Permissions

The POST /CertificateCollections/{id}/Permissions method is used to set permissions on a certificate collection. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: Security Settings: *Modify* 



Warning: When using this method to update an existing certificate collection, all existing Roleld and Permission information must be submitted along with any updates. Any existing permissions that are not included with their full existing data (Roleld and Permission mappings) on an update using this method will be removed from the permissions for the certificate collection. There is not presently a GET method to retrieve the current state of the permissions for certificate collections.



**Note:** This method has been deprecated and will be removed from the Keyfactor API in release 11. It has been replaced by the endpoint: PUT /Security/Roles/{id}/Permissions/Collection.

Table 186: POST CertificateCollections {id} Permissions Input Parameters

Name	In	Description
id	Path	Required. An integer indicating the ID of the certificate collection to update.  Use the GET /CertificateCollections method (see GET Certificate Collections on page 355) to retrieve a list of all the certificate collections to determine the certificate collection ID.
RoleId	Body	An integer identifying the Keyfactor Command security role that you wish to grant collection security permissions to.  Use the <i>GET /Security/Roles</i> method (see <u>GET Security Roles on page 898</u> ) to retrieve a list of your defined security roles to determine the security role ID to use.
Permissions Body	An array of the collection permissions that can be granted to the role. Possible values are:  Read EditMetadata Recover Revoke Delete For example:  "Permissions": [ "Read", "Recover", "Revoke" ]	
	Permissions for certificates can be set at either the global or certificate collection level. See <i>Certificate Permissions</i> in the <i>Keyfactor Command Reference Guide</i> for more information about global vs collection permissions.	

## 2.2.9 Certificate Stores

The CertificateStores component of the Keyfactor API (formerly known as the JKS API) provides a set of methods to support management of certificate locations.

Through different remote Keyfactor orchestrators, Keyfactor Command can inventory, install, and remove certificates for each of the store types. For certain store types, additional actions are supported as well. The CertificateStores component provides a way to programmatically schedule jobs for these stores. For more information about certificate stores and their support within Keyfactor Command, see the *Keyfactor Command Reference Guide* and *Keyfactor Command Orchestrator Installation and Configuration Guide*, or contact your Keyfactor representative. The set of methods in this API component that can be used to manage certificate stores and their scheduled jobs is listed in <a href="Table 187: Certificate Stores Endpoints">Table 187: Certificate Stores Endpoints</a>.

Table 187: Certificate Stores Endpoints

Endpoint	Method	Description	
/	DELETE	Deletes multiple certificate stores specified in the request body.	DELETE Certificate Stores on the next page
/	GET	Returns all certificate stores with paging and option to specify detail level.	GET Certificate Stores on page 377
/	POST	Creates a new certificate store if valid parameters are supplied.	POST Certificate Stores on page 384
/	PUT	Updates an existing certificate store.	PUT Certificate Stores on page 404
/{id}	DELETE	Deletes a certificate store by its GUID.	DELETE Certificate Stores ID on page 424
/{id}	GET	Returns certificate store details for the specified certificate store.	GET Certificate Stores ID on page 425
/{id}/Inventory	GET	Returns certificate inventory for the specified certificate store.	GET Certificate Stores ID Inventory on page 438
/Server (*deprecated)	GET	Returns a list of certificate store servers.	GET Certificate Stores Server on page 440
/Server (*deprecated)	POST	Creates a new certificate store server.	POST Certificate Stores Server on page 441
/Server (*deprecated)	PUT	Updates an existing certificate store server.	PUT Certificate Stores Server on page 446
/Password	PUT	Updates the password for a certificate store.	PUT Certificate Stores

Endpoint	Method	Method Description	
			Password on page 450
/DiscoveryJob	PUT	Creates a job to find certificate stores.	PUT Certificate Stores Discovery Job on page 453
/AssignContainer	PUT	Assigns a certificate store to a container.	PUT Certificate Stores Assign Container on page 459
/Approve	POST	Approves an array of pending certificate stores.	POST Certificate Stores Approve on page 466
/Schedule	POST	Creates an inventory schedule for a certificate store.	POST Certificate Stores Schedule on page 475
/Reenrollment	POST	Schedules a reenrollment of a certificate into a certificate store.	POST Certificate Stores Reenrollment on page 477
/Certificates/Add	POST	Configures a management job to add a certificate to one or more stores with the provided schedule.	POST Certificate Stores Certificates Add on page 480
/Certificates/Remove	POST	Configures a management job to remove a certificate from one or more stores with the provided schedule.	POST Certificate Stores Certificates Remove on page 485

### 2.2.9.1 DELETE Certificate Stores

The DELETE /CertificateStores method is used to delete multiple certificate stores in one request. The certificate store GUIDs should be supplied in the request body as a JSON array of strings. This endpoint returns 204 with no content upon success. GUIDs of any certificate stores that could not be deleted are returned in the response body. Delete operations will continue until the entire array of GUIDs has been processed.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: CertificateStoreManagement: *Modify* 

Permissions for certificate stores can be set at either the global or certificate store container level. See *Container Permissions* in the *Keyfactor Command Reference Guide* for more information about global vs container permissions.

Table 188: DELETE Certificate Stores Input Parameters

Name	In	Description
IDs	Body	Required. An array of strings indicating Keyfactor Command certificate store GUIDs for certificate stores that should be deleted in the form:  [52fe526d-9914-4239-b74b-b47d0607cf7c,8ec160d9-3242-4eb4-956b-a7651af6c542]  Use the GET /CertificateStores method (see GET Certificate Stores below) to retrieve a list of all the certificate stores to determine the certificate store GUIDs.

## 2.2.9.2 GET Certificate Stores

The GET /CertificateStores method is used to return a list of all certificate stores defined in Keyfactor Command. The results include both approved certificates stores and certificates stores found on discovery but not yet approved. This method allows URL parameters to specify paging and the level of information detail. This method returns HTTP 200 OK on a success with details about the certificate store(s).



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: CertificateStoreManagement: *Read* 

Permissions for certificate stores can be set at either the global or certificate store container level. See *Container Permissions* in the *Keyfactor Command Reference Guide* for more information about global vs container permissions.

Table 189: GET Certificate Stores Input Parameters

Name	In	Description		
queryString	Query	A string containing a query to limit the results (e.g. field1 -eq value1 AND field2 -gt value2). The default is to return all records. Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns for the same feature. For querying guidelines, refer to the Keyfactor Command Reference Guide: Using the Certificate Store Search Feature. The query fields supported for this endpoint are:  • AddSupported (True, False)  • AgentAvailable (True, False)  • AgentId  • Approved (True, False)  • Approved (True, False)  • Approved (True, False)  • PrivateKeyAllowed (O-Forbidden, 1-Optional, 2-Required)  • Category (O-Javakeystore, 2-PEMFile, 3-F5SSLProfiles, 4-IISRoots, 5-NetScaler, 6-IISPersonal, 7-F5WebServer, 8-IISRevoked, 9-F5WebServerREST, 10-F5SSLProfilesREST, 11-F5CABundlesREST, 100-AmazonWebServices, 101-FileTransferProtocol)  • CertificateId  • StorePath  • ClientMachine  Tip: Use the following query to limit the results to only active certificate stores and not include discovery results: approved -eq true		
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.		
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.		
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>ClientMachine</i> .		
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.		

Table 190: GET Certificate Stores Response Data

Name	Description
Id	A string indicating the GUID of the certificate store within Keyfactor Command. This ID is automatically set by Keyfactor Command.
ContainerId	An integer indicating the ID of the certificate store's associated certificate store container, if applicable (see <u>GET Certificate Store Containers on page 488</u> ).
ClientMachine	The string value of the client machine. The value for this will vary depending on the certificate store type. For example, for a Java keystore or an F5 device, it is the hostname of the machine on which the store is located, but for an Amazon Web Services store, it is the FQDN of the Keyfactor Command Windows Orchestrator. See <i>Certificate Store Operations: Adding or Modifying a Certificate Store</i> in the <i>Keyfactor Command Reference Guide</i> for more information.
Storepath	A string indicating the path to the certificate store on the target. The format for this path will vary depending on the certificate store type. For example, for a Java keystore, this will be a file path (e.g. /opt/myapp/store.jks), but for an F5 device, this will be a partition name on the device (e.g. Common). See <i>Certificate Store Operations: Adding or Modifying a Certificate Store</i> in the <i>Keyfactor Command Reference Guide</i> for more information.
CertStoreIn- ventoryJobId	A string indicating the GUID that identifies the inventory job for the certificate store in the Keyfactor Command database. This will be null if an inventory schedule is not set for the certificate store.
CertStoreType	An integer indicating the ID of the certificate store type, as defined in Keyfactor Command, for this certificate store. (0-Javakeystore,2-PEMFile, 3-F5SSLProfiles,4-IISRoots, 5-NetScaler, 6-IISPersonal, 7-F5WebServer, 8-IISRevoked, 9-F5WebServerREST, 10-F5SSLProfilesREST, 11-F5CABundlesREST, 100-AmazonWebServices, 101-FileTransferProtocol)
Approved	A Boolean that indicates whether a certificate store is approved (true) or not (false). If a certificate store is approved, it can be used and updated. A certificate store that has been discovered using the discover feature but not yet marked as approved will be false here.
CreatelfMissing	A Boolean that indicates whether a new certificate store should be created with the information provided (true) or not (false). This option is only valid for Java keystores and any custom certificate store types you have defined to support this functionality.
Properties	Some types of certificate stores have additional properties that are stored in this parameter. The data is stored in a series of, typically, key value pairs that define the property name and value (see <a href="GET Certificate Store Types on page 518">GET Certificate Store Types on page 518</a> for more information).  As of Keyfactor Command v10, this parameter is used to store certificate store server user-
	names, server passwords, and the UseSSL flag. Built-in certificate stores that typically require configuration of certificate store server parameters include NetScaler and F5 stores. The legacy

#### Name

#### Description

methods for managing certificate store server credentials have been deprecated but are retained for backwards compatiblity. For more information, see <a href="POST Certificate Stores Server">POST Certificate Stores Server</a> on page 441.

When reading this field, the values are returned as simple key value pairs, with the values being individual values. When writing, the values are specified as objects, though they are typically single values.

For example, on a GET request for a *PEM* store configured with a separate private key, the contents of this field might be:

```
"{
  \"privateKeyPath\":\"/opt/app/mystore.key\",
  \"separatePrivateKey\":\"true\"
}"
```

However, the syntax used when updating the properties sets the value as a key value pair using *value* as the key. For example, on a POST or PUT request for a *PEM* store configured with a separate private key, the contents of this field might be:

```
"{
  \"privateKeyPath\":{\"value\":\"/opt/app/mystore.key\"},
  \"separatePrivateKey\":{\"value\":\"true\"}
}"
```

An example server properties parameter POST for an FTP or NetScaler store would contain:

```
"{
    \"ServerUsername\":{\"value\":{\"SecretValue\":\"User_Name\"}},
    \"ServerPassword\":{\"value\":{\"SecretValue\":\"Password\"}},
    \"ServerUseSsl\":{\"value\":\"true\"}
}"
```

An example server properties parameter POST for an FTP or NetScaler store with the username and password stored as PAM secrets would contain (where the Provider value—1 in this example—is the Id value from GET PAM Providers on page 724):

```
"{
    \"ServerUsername\":{\"value\":{\"Provider\":\"1\",\"Parameters\":
{\"SecretId\":\"User_Name\"}}},
    \"ServerPassword\":{\"Provider\":\"1\",\"Parameters\":
{\"SecretId\":\"Password\"}}},
    \"ServerUseSsl\":{\"value\":\"true\"}
}"
```

Name	Description
	Note: There are three standard properties that are used for any built-in certificate store types that require server credentials (e.g. F5):  ServerUsername ServerPassword ServerUseSsI  These replace the separate certificate store server records that existed in previous versions of Keyfactor Command. For legacy support, if credentials are not provided through store properties during creation or editing of a certificate store, Keyfactor Command will attempt to find a certificate store server record and copy the credentials from it into the store properties for future use.  Tip: Built-in stores that make use of this field include: AWS stores use this field to store secured versions of the access key and secret. F5 REST stores (all types) use this field to store secured versions of the server authentication information (ServerUsername, ServerPassword, ServerUseSsI) and primary node information (PrimaryNode, PrimaryNodeCheckRetryWaitSecs, PrimaryNodeCheckRetryMax) and F5 version (F5Version).  F5 SOAP stores (all types) use this field to store secured versions of the server authentication information (ServerUsername, ServerPassword, ServerUseSsI).  FTP stores use this field to store secured versions of the server authentication information (ServerUsername, ServerPassword, ServerUseSsI).  Ils stores (all types) use this field to store the UseSSL flag and the port for WinRM communications.  Java keystores use this field to store type (ProviderType).  NetScaler stores use this field to store secured versions of the server authentication information (ServerUsername, ServerPassword, ServerUseSsI).
AgentId	A string indicating the Keyfactor Command GUID of the orchestrator for this store.
AgentAssigned	A Boolean that indicates whether there is an orchestrator assigned to this certificate store (true) or not (false).
ContainerName	A string indicating the name of the certificate store's associated container, if applicable.
InventorySchedule	The inventory schedule for this certificate store. The following schedule types are supported:

Name	Description				
	Name	Description			
	Off	ously configured schedule.			
	Immediate	A Boolean that (false).	indicates a job scheduled to run immediately (true) or not		
		N/	some instances, jobs initially scheduled as <i>Immediate</i> will on a GET as <i>null</i> .		
	Interval	specified param	at indicates a job scheduled to run every x minutes with the neter. Any interval that is selected in the UI will be converted in stored in the database.		
		Name	Description		
		Minutes	An integer indicating the number of minutes between each interval.		
		For example, every hour:			
		"Interval":     "Minutes			
	Daily	A dictionary that indicates a job scheduled to run every day at the same time with the parameter:			
		Name	Description		
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).		
		For example, da	aily at 11:30 pm:		
		"Daily": {     "Time": }	"2022-02-25T23:30:00Z"		

Name	Description					
	Name	Descript	Description			
	ExactlyOnce	A dictionary that indicates a job scheduled to run at the time specified with the parameter:				
		Name	Description			
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).			
		For exam	ple, exactly once at 11:45 am:			
			"ExactlyOnce": {     "Time": "2022-02-27T11:45:00Z" }			
		Tip: In some instances, jobs initially scheduled as <i>Immediate</i> will appear on a GET as <i>ExactlyOnce</i> .				
	ules, onl	y the schedu	Swagger Example Value may show examples of various other schedules shown here—that are available in the Management Portal for re valid for this endpoint.			
ReenrollmentStatus			her the certificate store can use the re-enrollment function with se re-enrollment job. The following reenrollment fields are			
	Name		Description			
	Data		A Boolean that indicates whether the certificate store can use the re-enrollment function (true) or not (false).			
	AgentId		A string indicating the Keyfactor Command GUID of the orchestrator that can re-enroll the certificate store.			
	Message		A string indicating the reason the certificate store cannot reenroll, if applicable.			
	JobProperties		An array of key/value pairs for the unique parameters defined			

Name	Description		
	Name	Description	
		for the certificate store type. The *key* is the name of the specific parameter from the certificate store type definition as returned in the JobProperties on the store type using the *GET CertificateStoreTypes* method and the *value* is the value that should be set for that parameter on a certificate in the certificate store. For example, for NetScaler, the key name that is optionally used to associate a certificate with a virtual server is *NetscalerVserver* and is returned by *GET CertificateStoreTypes* like so:  "JobProperties": ["NetscalerVserver"]  It can be seen in the Keyfactor Command Management Portal when editing the certificate store type in the field for *Management Job Custom Fields*.  The setting is referenced using the following format:  "JobProperties": [	
		This field is optional.	
	CustomAliasAllowed	An integer indicating the option for a custom alias for this certificate store.  • 0—forbidden  • 1—optional  • 2—required	
SetNewPass- wordAllowed	A Boolean that indicates wh	ether the store password can be changed (true) or not (false).	
Password	Note: Secret data is responses.	s stored in the secrets table or a PAM provider and is not returned in	

# 2.2.9.3 POST Certificate Stores

The POST /CertificateStores method is used to create new certificate stores in Keyfactor Command. This method returns HTTP 200 OK on a success with details about the certificate store created.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: CertificateStoreManagement: *Modify* 

Permissions for certificate stores can be set at either the global or certificate store container level. See *Container Permissions* in the *Keyfactor Command Reference Guide* for more information about global vs container permissions.

Table 191: POST Certificate Stores Input Parameters

Name	In	Description	
ContainerId	Bod- y	An integer indicating the ID of the certificate store's associated certificate store container, if applicable (see <u>GET Certificate Store Containers on page 488</u> ).	
ClientMachine	Bod- y	<b>Required</b> . The string value of the client machine. The value for this will vary depending on the certificate store type. For example, for a Java keystore or an F5 device, it is the hostname of the machine on which the store is located, but for an Amazon Web Services store, it is the FQDN of the Keyfactor Command Windows Orchestrator. See <i>Certificate Store Operations:</i> Adding or Modifying a Certificate Store in the Keyfactor Command Reference Guide for more information.	
Storepath	Bod- y	<b>Required</b> . A string indicating the path to the certificate store on the target. The format for this path will vary depending on the certificate store type. For example, for a Java keystore, this will be a file path (e.g. /opt/myapp/store.jks), but for an F5 device, this will be a partition name on the device (e.g. Common). See <i>Certificate Store Operations: Adding or Modifying a Certificate Store</i> in the <i>Keyfactor Command Reference Guide</i> for more information.	
CertStoreInventoryJobId	Bod- y	A string indicating the GUID that identifies the inventory job for the certificate store in the Keyfactor Command database. This will be null if an inventory schedule is not set for the certificate store.	
CertStoreType	Bod- y	<b>Required</b> . An integer indicating the ID of the certificate store type, as defined in Keyfactor Command, for this certificate store. (0-Javakeystore,2-PEMFile, 3-F5SSLProfiles,4-IISRoots, 5-NetScaler, 6-IISPersonal, 7-F5WebServer, 8-IISRevoked, 9-F5WebServerREST, 10-F5SSLProfilesREST, 11-F5CABundlesREST, 100-AmazonWebServices, 101-FileTransferProtocol)	
Approved	Bod- y	A Boolean that indicates whether a certificate store is approved (true) or not (false). If a certificate store is approved, it can be used and updated. A certificate store that has been discovered using the discover feature but not yet marked as approved will be false here. The default for new stores created with this method is <i>true</i> .	
CreatelfMissing	Bod- y	A Boolean that indicates whether a new certificate store should be created with the information provided (true) or not (false). This option is only valid for Java keystores and any custom certificate store types you have defined to support this functionality. The default is <i>false</i> .	
Properties	Bod- y	Required. Some types of certificate stores have additional properties that are stored in this parameter. The data is stored in a series of, typically, key value pairs that define the property name and value (see GET Certificate Store Types on page 518 for more information).  As of Keyfactor Command v10, this parameter is used to store certificate store server usernames, server passwords, and the UseSSL flag. Built-in certificate stores that typically require configuration of certificate store server parameters include NetScaler and F5 stores. The legacy methods for managing certificate store server credentials have been deprecated but are retained for backwards compatibility. For more information, see POST Certificate Stores Server on page 441.  When reading this field, the values are returned as simple key value pairs, with the values	

# Description Name In being individual values. When writing, the values are specified as objects, though they are typically single values. For example, on a GET request for a PEM store configured with a separate private key, the contents of this field might be: \"privateKeyPath\":\"/opt/app/mystore.key\", \"separatePrivateKey\":\"true\" However, the syntax used when updating the properties sets the value as a key value pair using value as the key. For example, on a POST or PUT request for a PEM store configured with a separate private key, the contents of this field might be: \"privateKeyPath\":{\"value\":\"/opt/app/mystore.key\"}, \"separatePrivateKey\":{\"value\":\"true\"} An example server properties parameter POST for an FTP or NetScaler store would contain: \"ServerUsername\":{\"value\":{\"SecretValue\":\"User\_Name\"}}, \"ServerPassword\":{\"value\":{\"SecretValue\":\"Password\"}}, \"ServerUseSsl\":{\"value\":\"true\"} An example server properties parameter POST for an FTP or NetScaler store with the username and password stored as PAM secrets would contain (where the Provider value—1 in this example—is the Id value from GET PAM Providers on page 724): \"ServerUsername\":{\"value\":{\"Provider\":\"1\",\"Parameters\": {\"SecretId\":\"User\_Name\"}}}, \"ServerPassword\":{\"value\":{\"Provider\":\"1\",\"Parameters\": {\"SecretId\":\"Password\"}}}, \"ServerUseSsl\":{\"value\":\"true\"} Note: There are three standard properties that are used for any built-in certificate store types that require server credentials (e.g. F5): ServerUsername

ServerPassword

Name	In	Description	
		ServerUseSsl  These replace the separate certificate store server records that existed in previous versions of Keyfactor Command. For legacy support, if credentials are not provided through store properties during creation or editing of a certificate store, Keyfactor Command will attempt to find a certificate store server record and copy the credentials from it into the store properties for future use.	
		<ul> <li>Tip: Built-in stores that make use of this field include:         <ul> <li>AWS stores use this field to store secured versions of the access key and secret.</li> <li>F5 REST stores (all types) use this field to store secured versions of the server authentication information (ServerUsername, ServerPassword, ServerUseSsI) and primary node information (PrimaryNode, PrimaryNodeCheck-RetryWaitSecs, PrimaryNodeCheckRetryMax) and F5 version (F5Version).</li> <li>F5 SOAP stores (all types) use this field to store secured versions of the server authentication information (ServerUsername, ServerPassword, ServerUseSsI).</li> <li>FTP stores use this field to store secured versions of the server authentication information (ServerUsername, ServerPassword, ServerUseSsI).</li> <li>IIS stores (all types) use this field to store the UseSSL flag and the port for WinRM communications.</li> <li>Java keystores use this field to store type (ProviderType).</li> <li>NetScaler stores use this field to store secured versions of the server authentication information (ServerUsername, ServerPassword, ServerUseSsI).</li> <li>PEM stores use this field to store the path to the private key file, if defined, and the Boolean value indicating whether a separate private key path is defined.</li> </ul> </li> </ul>	
AgentId	Bod-	<b>Required</b> . A string indicating the Keyfactor Command GUID of the orchestrator for this store.	
AgentAssigned	Bod-	A Boolean that indicates whether there is an orchestrator assigned to this certificate store (true) or not (false). The default is <i>true</i> .	
ContainerName	Bod- y	A string indicating the name of the certificate store's associated container, if applicable.	
Invent- orySchedule	Bod-	The inventory schedule for this certificate store. The following schedule types are supported:	

Name	In	Description		
		Name	Description	
		Off	Turn off a previously configured schedule.	
		Immediate	A Boolean that indicates a job scheduled to run immediately (true) or not (false).	
			Tip: In some instances, jobs initially scheduled as <i>Immediate</i> will appear on a GET as <i>null</i> .	
		Interval	A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database.	
			Name Description	
			Minutes An integer indicating the number of minutes between each interval.	
			For example, every hour:	
			"Interval": {     "Minutes": 60 }	
		Daily	A dictionary that indicates a job scheduled to run every day at the same time with the parameter:	
			Name Description	
				Time  The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
			For example, daily at 11:30 pm:	
			"Daily": {     "Time": "2022-02-25T23:30:00Z" }	

Name	In	Description								
		Name	Descrip	tion						
		ExactlyOnc-		ary that indicates a job scheduled to run at the time specified parameter:						
			Name	Description						
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).						
			For exam	aple, exactly once at 11:45 am:						
				lyOnce": { me": "2022-02-27T11:45:00Z"						
			Tip: In some instances, jobs initially scheduled as <i>Immediate</i> will appear on a GET as <i>ExactlyOnce</i> .							
		schedul	es, only the	e Swagger Example Value may show examples of various other schedules shown here—that are available in the Management cionality—are valid for this endpoint.						
Reen- rollmentStatus	Bod- y	An array that indicates whether the certificate store can use the re-enrollment function with accompanying data about the re-enrollment job. The following reenrollment fields are supported:								
		Name		Description						
		Data		A Boolean that indicates whether the certificate store can use the re-enrollment function (true) or not (false).						
	A							AgentId		A string indicating the Keyfactor Command GUID of the orchestrator that can re-enroll the certificate store.
		Message		A string indicating the reason the certificate store cannot reenroll, if applicable.						
		JobProperties		An array of key/value pairs for the unique parameters defined						

Name	In	Description	Description		
		Name	Description		
			for the certificate store type. The key is the name of the specific parameter from the certificate store type definition as returned in the JobProperties on the store type using the GET CertificateStoreTypes method and the value is the value that should be set for that parameter on a certificate in the certificate store. For example, for NetScaler, the key name that is optionally used to associate a certificate with a virtual server is NetscalerVserver and is returned by GET CertificateStoreTypes like so:  "JobProperties": ["NetscalerVserver"]  It can be seen in the Keyfactor Command Management Portal when editing the certificate store type in the field for Management Job Custom Fields.  The setting is referenced using the following format:  "JobProperties": [ {"NetscalerVserver": "MyVirtualServerName"} ]  Note: The only built-in certificate store type that makes use of job properties that can be set on a certificate-by-certificate basis in the store is NetScaler. You may have custom certificate store types that make use of this functionality.  This field is optional.		
		CustomAliasAllowed	An integer indicating the option for a custom alias for this certificate store.  • 0—forbidden  • 1—optional  • 2—required		
SetNewPass- wordAllowed	Bod-	A Boolean that indicates when the default is <i>false</i> .	hether the store password can be changed (true) or not (false).		
Password	Bod- y	An array indicating the source for and details of the credential information Keyfactor Command will use to access the certificates in a specific certificate store (the store password). This is different from credential information Keyfactor Command uses to access a certificate store server as a whole. The former (this setting) is typically used for Java keystores; the latter is typically used for certificates stores on NetScaler and F5 devices and set at the server level, not the certificate store level (see <a href="POST Certificate Stores Server">POST Certificate Stores Server</a> on page 441).			

Name	In	Description	
		<ul> <li>Use no storm This option but can be</li> <li>Store the orange A Keyfactor the Keyfactor the Keyfactor the See Privile</li> </ul>	n is supported for Java keystores that would normally require a password, e configured with the no password option (see <i>Value</i> , below).  credential information in the Keyfactor secrets table.  or secret is a user-defined password that is encrypted and stored securely in stor Command database.  credential information from a PAM provider.  ged Access Management (PAM) in the Keyfactor Command Reference  PAM Providers on page 709 for more information.
		Name	Description
		Value	A string—submitted as an object—indicating a password to be stored as a Keyfactor secret.  Tip: To set the no password option on a store, submit the password with a null value. For example:  "Password": {  "Value": {null}  }  To set the value to a string to be stored in the Keyfactor secrets table, include the password in quotes. For example:  "Password": {  "Value": "MyVerySecurePassword"  }
		SecretType- Guid	A string indicating the Keyfactor Command reference GUID for the type of credentials. This value is automatically set by Keyfactor Command.
		InstanceId	The Keyfactor Command reference ID for the secret provider. If you are using a secret provider with an integer ID, this will be used. This value is automatically set by Keyfactor Command.
		InstanceGui-	The Keyfactor Command reference GUID for the secret provider. If you are using a secret provider with a GUID ID, this will be used. This value is automatically set by Keyfactor Command.
		Provider- Type Para-	An array containing the values for the PAM provider types specified by ProviderTypeParams. The provider type parameter values include:

	In	Description			
		Name	Description		
		meterValue- s	Name	Description	
			Id	The Keyfactor of provider type p	Command reference ID for the PAM parameter.
			Value	CyberArk folde	or the parameter (e.g. the name of the r where the protected object that name or password resides).
			Instancel- d		Command reference ID for the PAM are attaching to something with an will be used.
			Instance- Guid		Command reference GUID for the PAM are attaching to something with a will be used.
			Provider		ining information about the provider. details include:
				Name	Description
				Id	An integer indicating the Keyfactor Command reference ID for the PAM provider.
				Name	A string indicating the internal name for the PAM provider.
				Area	An integer indicating the area of Keyfactor Command the provider is used for. PAM providers generally have a value of 1, indicating they are used for certificate stores.
				Provider- Type	An array containing details about the provider type for the provider, including:

Name	In	Description				
		Name	Description			
			Name	Description		
				Name	Description	ı
					Name	Description
					Id	A string indicating the Keyfactor Command reference GUID for the provider type.
					Name	A string that indicates the name of the provider type.
					Provider Type Params	An array of parameters that the provider type uses for data input in Keyfactor Command when creating new PAM provider and certificate store records.  See below instance of Provider-TypeParam for details.
				Provider- Type	An array cor	taining the values for

Name	In	Description			
		Name	Description		
			Name	Description	
				Name	Description
				Para- mValues	the provider types specified by ProviderTypeParams. See the previous level of <i>Provider-TypeParamValues</i> for details.
				SecuredAre- ald	An integer indicating the Keyfactor Command reference ID for the certificate store container the PAM provider is associated with, if any.
					You can create a single PAM provider for each provider type (e.g. CyberArk), however, if you have opted to organize your certificate stores into containers, you will need to create multiple providers to match your container organization structure. The container field in the PAM provider definition is not required, but if one is supplied when creating a PAM provider, the PAM provider can only be used with certificate stores in the matching container. Likewise, a
					PAM provider defined with no container would be available for selection when setting passwords for any certificate store that also did not specify a container. A PAM provider configured in this way could be used across a variety of certificate stores (e.g. both JKS and F5) as long as they were not in containers.

Command reference ID for the PAM provider type parameter.  Name  A string indicating the internal name for the PAM provider type parameter.  DisplayName  Tor the PAM provider type parameter. For parameters with an InstanceLevel of false, this name appears on the PAM provider dialog for the parameter when a user creates a new PAM provider For parameters with an InstanceLevel of true, this name appears on the Server dialog for the parameter when a user creates and the parameter when a	Name	In	Description			
Provider- Type Param  An array of parameters that the provider type us data input in Keyfactor Command when creating PAM provider and certificate store records. PAM provider type parameters include:  Name  Description  Id  An integer indicating the Keyfact Command reference ID for the PAM provider type parameter.  Name  A string indicating the internal name for the PAM provider type parameter.  DisplayName  DisplayName  A string indicating the display name for the PAM provider type parameter. For parameters with an InstanceLevel of false, this name appears on the PAM provider when a user creates a new PAM provider for parameters with an InstanceLevel of true, this name appears on the Server dialog for the parameter when a user creates a new PAM provider for parameters with an InstanceLevel of true, this name appears on the Server dialog for the parameter when a user creates and the parameter w			Name	Description		
Type Param  data input in Keyfactor Command when creating PAM provider and certificate store records. PAM provider type parameters include:  Name  Description  Id  An integer indicating the Keyfact Command reference ID for the PAM provider type parameter.  Name  A string indicating the internal name for the PAM provider type parameter.  DisplayName  DisplayName  A string indicating the display name for the PAM provider type parameter.  For parameters with an InstanceLevel of false, this name appears on the PAM provider dialog for the parameter when a user creates a new PAM provider for parameters with an InstanceLevel of true, this name appears on the Server dialog for the parameter when a user creates an expect of true, this name appears on the Server dialog for the parameter when a user creates and parameter				Name	Description	
Id An integer indicating the Keyfact Command reference ID for the PAM provider type parameter.  Name A string indicating the internal name for the PAM provider type parameter.  DisplayNa- A string indicating the display name for the PAM provider type parameter. For parameters with an InstanceLevel of false, this name appears on the PAM provider dialog for the parameter when a user creates a new PAM provider For parameters with an InstanceLevel of true, this name appears on the Server dialog for the parameter when a user creates and the Serv				Туре	data input in K PAM provider	eyfactor Command when creating new and certificate store records. PAM
Command reference ID for the PAM provider type parameter.  Name  A string indicating the internal name for the PAM provider type parameter.  DisplayName  Tor the PAM provider type parameter. For parameters with an InstanceLevel of false, this name appears on the PAM provider dialog for the parameter when a user creates a new PAM provider For parameters with an InstanceLevel of true, this name appears on the Server dialog for the parameter when a user creates and the parameter when a					Name	Description
name for the PAM provider type parameter.  DisplayName A string indicating the display name for the PAM provider type parameter. For parameters with an InstanceLevel of false, this name appears on the PAM provider dialog for the parameter when a user creates a new PAM provider For parameters with an InstanceLevel of true, this name appears on the Server dialog for the parameter when a user creates and the par					Id	
me for the PAM provider type parameter. For parameters with an InstanceLevel of false, this name appears on the PAM provider dialog for the parameter when a user creates a new PAM provider For parameters with an InstanceLevel of true, this name appears on the Server dialog for the parameter when a user creater when a user cr					Name	name for the PAM provider type
a new PAM provider.					. ,	InstanceLevel of <i>false</i> , this name appears on the PAM provider dialog for the parameter when a user creates a new PAM provider.
					DataType	• 1 = String
						A Boolean that sets whether the parameter is used to define the

Name	In	Description				
		Name	Description			
			Name	Description		
				Name	Description	
					a field that need	figuring a certificate PAM provider , see GET PAM
				Provider- Type	An array contain provider type.	ning details for the
					Name	Descrip- tion
					Id	A string indicating the Keyfactor Command reference GUID for the PAM provider type parameter.
					Name	A string indicating the internal name for the PAM

Name	In	Description				
		Name	Description			
			Name	Description		
				Name	Description	
					Name	Descrip- tion
						provider type para- meter.
					Provider- TypeParams	Unused field
		ProviderId	An integer ind provider.	icating the Keyfa	ctor Command refer	ence ID for the PAM
		IsManaged	by a PAM prov	vider (true) or sto	the credentials for the ored in the Keyfactor by Keyfactor Comman	secrets table (false).

Table 192: POST Certificate Stores Response Data

Name	Description
ld	A string indicating the GUID of the certificate store within Keyfactor Command. This ID is automatically set by Keyfactor Command.
ContainerId	An integer indicating the ID of the certificate store's associated certificate store container, if applicable (see <u>GET Certificate Store Containers on page 488</u> ).
ClientMachine	The string value of the client machine. The value for this will vary depending on the certificate store type. For example, for a Java keystore or an F5 device, it is the hostname of the machine on which the store is located, but for an Amazon Web Services store, it is the FQDN of the Keyfactor Command Windows Orchestrator. See <i>Certificate Store Operations: Adding or Modifying a Certificate Store</i> in the <i>Keyfactor Command Reference Guide</i> for more information.
Storepath	A string indicating the path to the certificate store on the target. The format for this path will vary depending on the certificate store type. For example, for a Java keystore, this will be a file path (e.g. /opt/myapp/store.jks), but for an F5 device, this will be a partition name on the device (e.g. Common). See <i>Certificate Store Operations: Adding or Modifying a Certificate Store</i> in the <i>Keyfactor Command Reference Guide</i> for more information.
CertStoreIn- ventoryJobId	A string indicating the GUID that identifies the inventory job for the certificate store in the Keyfactor Command database. This will be null if an inventory schedule is not set for the certificate store.
CertStoreType	An integer indicating the ID of the certificate store type, as defined in Keyfactor Command, for this certificate store. (0-Javakeystore,2-PEMFile, 3-F5SSLProfiles,4-IISRoots, 5-NetScaler, 6-IISPersonal, 7-F5WebServer, 8-IISRevoked, 9-F5WebServerREST, 10-F5SSLProfilesREST, 11-F5CABundlesREST, 100-AmazonWebServices, 101-FileTransferProtocol)
Approved	A Boolean that indicates whether a certificate store is approved (true) or not (false). If a certificate store is approved, it can be used and updated. A certificate store that has been discovered using the discover feature but not yet marked as approved will be false here.
CreatelfMissing	A Boolean that indicates whether a new certificate store should be created with the information provided (true) or not (false). This option is only valid for Java keystores and any custom certificate store types you have defined to support this functionality.
Properties	Some types of certificate stores have additional properties that are stored in this parameter. The data is stored in a series of, typically, key value pairs that define the property name and value (see <a href="Meta-Europeans-518">GET Certificate Store Types on page 518</a> for more information).  As of Keyfactor Command v10, this parameter is used to store certificate store server usernames, server passwords, and the UseSSL flag. Built-in certificate stores that typically require configuration of certificate store server parameters include NetScaler and F5 stores. The legacy

#### Name

Description

methods for managing certificate store server credentials have been deprecated but are retained for backwards compatiblity. For more information, see <a href="POST Certificate Stores Server">POST Certificate Stores Server</a> on page 441.

When reading this field, the values are returned as simple key value pairs, with the values being individual values. When writing, the values are specified as objects, though they are typically single values.

For example, on a GET request for a *PEM* store configured with a separate private key, the contents of this field might be:

```
"{
  \"privateKeyPath\":\"/opt/app/mystore.key\",
  \"separatePrivateKey\":\"true\"
}"
```

However, the syntax used when updating the properties sets the value as a key value pair using *value* as the key. For example, on a POST or PUT request for a *PEM* store configured with a separate private key, the contents of this field might be:

```
"{
  \"privateKeyPath\":{\"value\":\"/opt/app/mystore.key\"},
  \"separatePrivateKey\":{\"value\":\"true\"}
}"
```

An example server properties parameter POST for an FTP or NetScaler store would contain:

```
"{
    \"ServerUsername\":{\"value\":{\"SecretValue\":\"User_Name\"}},
    \"ServerPassword\":{\"value\":{\"SecretValue\":\"Password\"}},
    \"ServerUseSsl\":{\"value\":\"true\"}
}"
```

An example server properties parameter POST for an FTP or NetScaler store with the username and password stored as PAM secrets would contain (where the Provider value—1 in this example—is the Id value from GET PAM Providers on page 724):

```
"{
    \"ServerUsername\":{\"value\":{\"Provider\":\"1\",\"Parameters\":
{\"SecretId\":\"User_Name\"}}},
    \"ServerPassword\":{\"Provider\":\"1\",\"Parameters\":
{\"SecretId\":\"Password\"}}},
    \"ServerUseSsl\":{\"value\":\"true\"}
}"
```

Name	Description
	Note: There are three standard properties that are used for any built-in certificate store types that require server credentials (e.g. F5):  ServerUsername ServerPassword ServerUseSsI  These replace the separate certificate store server records that existed in previous versions of Keyfactor Command. For legacy support, if credentials are not provided through store properties during creation or editing of a certificate store, Keyfactor Command will attempt to find a certificate store server record and copy the credentials from it into the store properties for future use.  Tip: Built-in stores that make use of this field include: AWS stores use this field to store secured versions of the access key and secret. F5 REST stores (all types) use this field to store secured versions of the server authentication information (ServerUsername, ServerPassword, ServerUseSsI) and primary node information (PrimaryNode, PrimaryNodeCheckRetryWaitSecs, PrimaryNodeCheckRetryMax) and F5 version (F5Version). F5 SOAP stores (all types) use this field to store secured versions of the server authentication information (ServerUsername, ServerPassword, ServerUseSsI). FTP stores use this field to store secured versions of the server authentication information (ServerUsername, ServerPassword, ServerUseSsI).  IIS stores (all types) use this field to store the UseSSL flag and the port for WinRM communications. Java keystores use this field to store type (ProviderType). NetScaler stores use this field to store secured versions of the server authentication information (ServerUsername, ServerPassword, ServerUseSsI).
AgentId	A string indicating the Keyfactor Command GUID of the orchestrator for this store.
AgentAssigned	A Boolean that indicates whether there is an orchestrator assigned to this certificate store (true) or not (false).
ContainerName	A string indicating the name of the certificate store's associated container, if applicable.
InventorySchedule	The inventory schedule for this certificate store. The following schedule types are supported:

Name	Description					
	Name	Description				
	Off	Turn off a previ	ously configured schedule.			
	Immediate	A Boolean that (false).	indicates a job scheduled to run immediately (true) or not			
		N/	some instances, jobs initially scheduled as <i>Immediate</i> will on a GET as <i>null</i> .			
	Interval	specified param	at indicates a job scheduled to run every x minutes with the neter. Any interval that is selected in the UI will be converted in stored in the database.			
		Name	Description			
	Daily	Minutes	An integer indicating the number of minutes between each interval.			
		For example, every hour:				
		"Interval":     "Minutes				
		A dictionary that indicates a job scheduled to run every day at the same time with the parameter:				
		Name	Description			
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).			
		For example, da	aily at 11:30 pm:			
		"Daily": {     "Time": }	"2022-02-25T23:30:00Z"			

Name	Description				
	Name	Description			
	ExactlyOnce	A dictionary that indicates a job scheduled to run at the time specified with the parameter:			
		Name	Description		
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).		
		For exam	For example, exactly once at 11:45 am:		
		"ExactlyOnce": {     "Time": "2022-02-27T11:45:00Z" }			
		Tip: In some instances, jobs initially scheduled as <i>Immediate</i> will appear on a GET as <i>ExactlyOnce</i> .			
	Note: Although the Swagger <i>Example Value</i> may show examples of various other schedules, only the schedules shown here—that are available in the Management Portal for this functionality—are valid for this endpoint.				
ReenrollmentStatus	An array that indicates whether the certificate store can use the re-enrollment function with accompanying data about the re-enrollment job. The following reenrollment fields are supported:				
	Name		Description		
	Data		A Boolean that indicates whether the certificate store can use the re-enrollment function (true) or not (false).		
	AgentId		A string indicating the Keyfactor Command GUID of the orchestrator that can re-enroll the certificate store.		
	Message		A string indicating the reason the certificate store cannot reenroll, if applicable.		
	JobProperties		An array of key/value pairs for the unique parameters defined		

Name	Description		
	Name	Description	
		for the certificate store type. The key is the name of the specific parameter from the certificate store type definition as returned in the JobProperties on the store type using the GET CertificateStoreTypes method and the value is the value that should be set for that parameter on a certificate in the certificate store. For example, for NetScaler, the key name that is optionally used to associate a certificate with a virtual server is NetscalerVserver and is returned by GET CertificateStoreTypes like so:  "JobProperties": ["NetscalerVserver"]  It can be seen in the Keyfactor Command Management Portal when editing the certificate store type in the field for Management Job Custom Fields.  The setting is referenced using the following format:  "JobProperties": [ {"NetscalerVserver": "MyVirtualServerName"} ]  Note: The only built-in certificate store type that makes use of job properties that can be set on a certificate-by-certificate basis in the store is NetScaler. You may have custom certificate store types that make use of this functionality.	
		This field is optional.	
	CustomAliasAllowed	An integer indicating the option for a custom alias for this certificate store.  • 0—forbidden  • 1—optional  • 2—required	
SetNewPass- wordAllowed	A Boolean that indicates whether the store password can be changed (true) or not (false).		
Password	Note: Secret data is responses.	s stored in the secrets table or a PAM provider and is not returned in	

## 2.2.9.4 PUT Certificate Stores

The PUT /CertificateStores method is used to update an existing certificate store in Keyfactor Command. This method returns HTTP 200 OK on a success with a message body containing the certificate store.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: CertificateStoreManagement: *Modify* 

Permissions for certificate stores can be set at either the global or certificate store container level. See *Container Permissions* in the *Keyfactor Command Reference Guide* for more information about global vs container permissions.



Warning: Any previously populated fields that are not submitted with their full existing data using this method will be cleared of their existing data. When using this method, you should first do a GET to retrieve all the values for the record you want to update, enter corrected data into the field(s) you want to update, and then submit all the fields using PUT, including the fields that contain values but which you are not changing.

Table 193: PUT Certificate Stores Input Parameters

Name	In	Description	
ld	Bod- y	A string indicating the GUID of the certificate store within Keyfactor Command. This ID is automatically set by Keyfactor Command.	
ContainerId	Bod- y	An integer indicating the ID of the certificate store's associated certificate store container, if applicable (see <u>GET Certificate Store Containers on page 488</u> ).	
ClientMachine	Bod- y	<b>Required</b> . The string value of the client machine. The value for this will vary depending on the certificate store type. For example, for a Java keystore or an F5 device, it is the hostname of the machine on which the store is located, but for an Amazon Web Services store, it is the FQDN of the Keyfactor Command Windows Orchestrator. See <i>Certificate Store Operations:</i> Adding or Modifying a Certificate Store in the Keyfactor Command Reference Guide for more information.	
Storepath	Bod- y	<b>Required</b> . A string indicating the path to the certificate store on the target. The format for this path will vary depending on the certificate store type. For example, for a Java keystore, this will be a file path (e.g. /opt/myapp/store.jks), but for an F5 device, this will be a partition name on the device (e.g. Common). See <i>Certificate Store Operations: Adding or Modifying a Certificate Store</i> in the <i>Keyfactor Command Reference Guide</i> for more information.	
CertStoreInventoryJobId	Bod- y	A string indicating the GUID that identifies the inventory job for the certificate store in the Keyfactor Command database. This will be null if an inventory schedule is not set for the certificate store.	
CertStoreType	Bod- y	<b>Required</b> . An integer indicating the ID of the certificate store type, as defined in Keyfactor Command, for this certificate store. (0-Javakeystore,2-PEMFile, 3-F5SSLProfiles,4-IISRoots, 5-NetScaler, 6-IISPersonal, 7-F5WebServer, 8-IISRevoked, 9-F5WebServerREST, 10-F5SSLProfilesREST, 11-F5CABundlesREST, 100-AmazonWebServices, 101-FileTransferProtocol)	
Approved	Bod- y	A Boolean that indicates whether a certificate store is approved (true) or not (false). If a certificate store is approved, it can be used and updated. A certificate store that has been discovered using the discover feature but not yet marked as approved will be false here. The default for new stores created with this method is <i>true</i> .	
CreatelfMissing	Bod- y	A Boolean that indicates whether a new certificate store should be created with the information provided (true) or not (false). This option is only valid for Java keystores and any custom certificate store types you have defined to support this functionality. The default is <i>false</i> .	
Properties	Bod- y	Required. Some types of certificate stores have additional properties that are stored in this parameter. The data is stored in a series of, typically, key value pairs that define the property name and value (see GET Certificate Store Types on page 518 for more information).  As of Keyfactor Command v10, this parameter is used to store certificate store server usernames, server passwords, and the UseSSL flag. Built-in certificate stores that typically require configuration of certificate store server parameters include NetScaler and F5 stores. The legacy methods for managing certificate store server credentials have been deprecated but	

Description Name In are retained for backwards compatiblity. For more information, see POST Certificate Stores Server on page 441. When reading this field, the values are returned as simple key value pairs, with the values being individual values. When writing, the values are specified as objects, though they are typically single values. For example, on a GET request for a PEM store configured with a separate private key, the contents of this field might be: \"privateKeyPath\":\"/opt/app/mystore.key\", \"separatePrivateKey\":\"true\" However, the syntax used when updating the properties sets the value as a key value pair using value as the key. For example, on a POST or PUT request for a PEM store configured with a separate private key, the contents of this field might be: \"privateKeyPath\":{\"value\":\"/opt/app/mystore.key\"}, \"separatePrivateKey\":{\"value\":\"true\"} An example server properties parameter POST for an FTP or NetScaler store would contain: "{ \"ServerUsername\":{\"value\":{\"SecretValue\":\"User\_Name\"}}, \"ServerPassword\":{\"value\":{\"SecretValue\":\"Password\"}}, \"ServerUseSsl\":{\"value\":\"true\"} }" An example server properties parameter POST for an FTP or NetScaler store with the username and password stored as PAM secrets would contain (where the Provider value—1 in this example—is the Id value from GET PAM Providers on page 724): \"ServerUsername\":{\"value\":{\"Provider\":\"1\",\"Parameters\": {\"SecretId\":\"User\_Name\"}}}, \"ServerPassword\":{\"value\":{\"Provider\":\"1\",\"Parameters\": {\"SecretId\":\"Password\"}}}, \"ServerUseSsl\":{\"value\":\"true\"}

Note: There are three standard properties that are used for any built-in certificate

Name	In	Description
	store types that require server credentials (e.g. F5):  • ServerUsername  • ServerPassword  • ServerUseSsl  These replace the separate certificate store server records that existed in previous versions of Keyfactor Command. For legacy support, if credentials are not provided through store properties during creation or editing of a certificate store, Keyfactor Command will attempt to find a certificate store server record and copy the credentials from it into the store properties for future use.	
		<ul> <li>Tip: Built-in stores that make use of this field include:         <ul> <li>AWS stores use this field to store secured versions of the access key and secret.</li> <li>F5 REST stores (all types) use this field to store secured versions of the server authentication information (ServerUsername, ServerPassword, ServerUseSsI) and primary node information (PrimaryNode, PrimaryNodeCheck-RetryWaitSecs, PrimaryNodeCheckRetryMax) and F5 version (F5Version).</li> <li>F5 SOAP stores (all types) use this field to store secured versions of the server authentication information (ServerUsername, ServerPassword, Server-UseSsI).</li> <li>FTP stores use this field to store secured versions of the server authentication information (ServerUsername, ServerPassword, ServerUseSsI).</li> <li>IIS stores (all types) use this field to store the UseSSL flag and the port for WinRM communications.</li> <li>Java keystores use this field to store type (ProviderType).</li> <li>NetScaler stores use this field to store secured versions of the server authentication information (ServerUsername, ServerPassword, ServerUseSsI).</li> <li>PEM stores use this field to store the path to the private key file, if defined, and the Boolean value indicating whether a separate private key path is defined.</li> </ul> </li> </ul>
AgentId	Bod-	<b>Required</b> . A string indicating the Keyfactor Command GUID of the orchestrator for this store.
AgentAssigned	Bod- y	A Boolean that indicates whether there is an orchestrator assigned to this certificate store (true) or not (false). The default is <i>true</i> .
ContainerName	Bod- y	A string indicating the name of the certificate store's associated container, if applicable.
Invent- orySchedule	Bod- y	The inventory schedule for this certificate store. The following schedule types are supported:

Name	In	Description	
		Name	Description
		Off	Turn off a previously configured schedule.
		Immediate	A Boolean that indicates a job scheduled to run immediately (true) or not (false).
			Tip: In some instances, jobs initially scheduled as <i>Immediate</i> will appear on a GET as <i>null</i> .
		Interval	A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database.
			Name Description
			Minutes An integer indicating the number of minutes between each interval.
			For example, every hour:
			"Interval": {     "Minutes": 60 }
		Daily	A dictionary that indicates a job scheduled to run every day at the same time with the parameter:
			Name Description
			Time  The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
			For example, daily at 11:30 pm:
			"Daily": {     "Time": "2022-02-25T23:30:00Z" }

Name	In	Description			
		Name	Descrip	tion	
		ExactlyOnc-		ary that indicates a job scheduled to run at the time specified parameter:	
			Name	Description	
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
			For exam	pple, exactly once at 11:45 am:	
				lyOnce": { me": "2022-02-27T11:45:00Z"	
			N/	ip: In some instances, jobs initially scheduled as <i>Immediate</i> vill appear on a GET as <i>ExactlyOnce</i> .	
		schedul	Note: Although the Swagger Example Value may show examples of various other schedules, only the schedules shown here—that are available in the Management Portal for this functionality—are valid for this endpoint.		
Reen- Bod- rollmentStatus y		An array that indicates whether the certificate store can use the re-enrollment function with accompanying data about the re-enrollment job. The following reenrollment fields are supported:			
		Name		Description	
		Data		A Boolean that indicates whether the certificate store can use the re-enrollment function (true) or not (false).	
		AgentId		A string indicating the Keyfactor Command GUID of the orchestrator that can re-enroll the certificate store.	
		Message		A string indicating the reason the certificate store cannot re- enroll, if applicable.	
		JobProperties		An array of key/value pairs for the unique parameters defined	

Name	In	Description	
		Name	Description
			for the certificate store type. The key is the name of the specific parameter from the certificate store type definition as returned in the JobProperties on the store type using the GET CertificateStoreTypes method and the value is the value that should be set for that parameter on a certificate in the certificate store. For example, for NetScaler, the key name that is optionally used to associate a certificate with a virtual server is NetscalerVserver and is returned by GET CertificateStoreTypes like so:  "JobProperties": ["NetscalerVserver"]  It can be seen in the Keyfactor Command Management Portal when editing the certificate store type in the field for Management Job Custom Fields.  The setting is referenced using the following format:  "JobProperties": [ {"NetscalerVserver": "MyVirtualServerName"} ]  Note: The only built-in certificate store type that makes use of job properties that can be set on a certificate-by-certificate basis in the store is NetScaler. You may have custom certificate store types that make use of this functionality.  This field is optional.
		CustomAliasAllowed	An integer indicating the option for a custom alias for this
			certificate store.  • 0—forbidden  • 1—optional
			• 2—required
SetNewPass- wordAllowed	Bod-	A Boolean that indicates w The default is <i>false</i> .	hether the store password can be changed (true) or not (false).
Password	Bod- y	Command will use to access word). This is different from ficate store server as a who the latter is typically used for the server.	rce for and details of the credential information Keyfactor is the certificates in a specific certificate store (the store passmeredential information Keyfactor Command uses to access a certicle. The former (this setting) is typically used for Java keystores; for certificates stores on NetScaler and F5 devices and set at the cate store level (see POST Certificate Stores Server on page 441).

Name	In	Description	
		<ul> <li>Use no sto This option but can be</li> <li>Store the of A Keyfacto the Keyfacto the Keyfacto See Privile</li> </ul>	n is supported for Java keystores that would normally require a password, e configured with the no password option (see <i>Value</i> , below).  credential information in the Keyfactor secrets table.  or secret is a user-defined password that is encrypted and stored securely in stor Command database.  redential information from a PAM provider.  ged Access Management (PAM) in the Keyfactor Command Reference  PAM Providers on page 709 for more information.
		Name	Description
		Value	A string—submitted as an object—indicating a password to be stored as a Keyfactor secret.  Tip: To set the no password option on a store, submit the password with a null value. For example:  "Password": {  "Value": {null}  }  To set the value to a string to be stored in the Keyfactor secrets table, include the password in quotes. For example:  "Password": {  "Value": "MyVerySecurePassword"  }
		SecretType- Guid	A string indicating the Keyfactor Command reference GUID for the type of credentials. This value is automatically set by Keyfactor Command.
		InstanceId	The Keyfactor Command reference ID for the secret provider. If you are using a secret provider with an integer ID, this will be used. This value is automatically set by Keyfactor Command.
		InstanceGui- d	The Keyfactor Command reference GUID for the secret provider. If you are using a secret provider with a GUID ID, this will be used. This value is automatically set by Keyfactor Command.
		Provider- Type Para-	An array containing the values for the PAM provider types specified by ProviderTypeParams. The provider type parameter values include:

Name	In	Description	cription			
		Name	Description			
		meterValue-	Name	Description		
			Id	The Keyfactor (	Command reference ID for the PAM parameter.	
			Value	CyberArk folde	or the parameter (e.g. the name of the r where the protected object that name or password resides).	
			Instancel- d		Command reference ID for the PAM are attaching to something with an will be used.	
			Instance- Guid		Command reference GUID for the PAM are attaching to something with a lill be used.	
			Provider	An array contain	ining information about the provider. details include:	
				Name	Description	
				Id	An integer indicating the Keyfactor Command reference ID for the PAM provider.	
				Name	A string indicating the internal name for the PAM provider.	
				Area	An integer indicating the area of Keyfactor Command the provider is used for. PAM providers generally have a value of 1, indicating they are used for certificate stores.	
				Provider- Type	An array containing details about the provider type for the provider, including:	

Name	In	Description				
		Name	Description			
			Name	Description		
				Name	Description	1
					Name	Description
					ld	A string indicating the Keyfactor Command reference GUID for the provider type.
					Name	A string that indicates the name of the provider type.
					Provider Type Params	An array of parameters that the provider type uses for data input in Keyfactor Command when creating new PAM provider and certificate store records.  See below instance of Provider-TypeParam for details.
				Provider- Type	An array con	taining the values for

Name In	Description			
	Name	Description		
		Name	Description	
			Name	Description
			Para- mValues	the provider types specified by ProviderTypeParams. See the previous level of <i>Provider-TypeParamValues</i> for details.
			SecuredAre-ald	An integer indicating the Keyfactor Command reference ID for the certificate store container the PAM provider is associated with, if any. You can create a single PAM provider for each provider type (e.g. CyberArk), however, if you have opted to organize your certificate stores into containers, you will need to create multiple providers to match your container organization structure. The container field in the PAM provider definition is not required, but if one is supplied when creating a PAM provider, the PAM provider can only be used with certificate stores in the matching container. Likewise, a PAM provider defined with no container would be available for selection when setting passwords for any certificate store that also did not specify a container. A PAM provider configured in this way could be used across a variety of certificate stores (e.g.

Name	In	Description			
		Name	Description		
			Name	Description	
			Provider- Type Param	data input in K PAM provider	rameters that the provider type uses for Keyfactor Command when creating new and certificate store records. PAM parameters include:
				Name	Description
				Id	An integer indicating the Keyfactor Command reference ID for the PAM provider type parameter.
				Name	A string indicating the internal name for the PAM provider type parameter.
				DisplayNa- me	A string indicating the display name for the PAM provider type parameter. For parameters with an InstanceLevel of <i>false</i> , this name appears on the PAM provider dialog for the parameter when a user creates a new PAM provider. For parameters with an InstanceLevel of <i>true</i> , this name appears on the Server dialog for the parameter when a user creates a new PAM provider.
				DataType	An integer indicating the data type for the parameter. Possible values are:  • 1 = String • 2 = Secret
				InstanceL- evel	A Boolean that sets whether the parameter is used to define the

Name	In	Description				
		Name	Description			
			Name	Description		
				Name	Description	
					a field that need	figuring a certificate PAM provider see GET PAM
				Provider- Type	An array contain provider type.	ning details for the
					Name	Descrip- tion
					Id	A string indicating the Keyfactor Command reference GUID for the PAM provider type parameter.
					Name	A string indicating the internal name for the PAM

Name	In	Description				
		Name	Description			
			Name	Description		
				Name	Description	
					Name	Descrip- tion
						provider type para- meter.
					Provider- TypeParams	Unused field
		ProviderId	An integer ind provider.	icating the Keyfa	ctor Command refere	ence ID for the PAM
		IsManaged	by a PAM prov	vider (true) or sto	he credentials for the red in the Keyfactor s by Keyfactor Comman	secrets table (false).

Table 194: PUT Certificate Stores Response Data

Name	Description
ld	A string indicating the GUID of the certificate store within Keyfactor Command. This ID is automatically set by Keyfactor Command.
ContainerId	An integer indicating the ID of the certificate store's associated certificate store container, if applicable (see <u>GET Certificate Store Containers on page 488</u> ).
ClientMachine	The string value of the client machine. The value for this will vary depending on the certificate store type. For example, for a Java keystore or an F5 device, it is the hostname of the machine on which the store is located, but for an Amazon Web Services store, it is the FQDN of the Keyfactor Command Windows Orchestrator. See <i>Certificate Store Operations: Adding or Modifying a Certificate Store</i> in the <i>Keyfactor Command Reference Guide</i> for more information.
Storepath	A string indicating the path to the certificate store on the target. The format for this path will vary depending on the certificate store type. For example, for a Java keystore, this will be a file path (e.g. /opt/myapp/store.jks), but for an F5 device, this will be a partition name on the device (e.g. Common). See <i>Certificate Store Operations: Adding or Modifying a Certificate Store</i> in the <i>Keyfactor Command Reference Guide</i> for more information.
CertStoreIn- ventoryJobId	A string indicating the GUID that identifies the inventory job for the certificate store in the Keyfactor Command database. This will be null if an inventory schedule is not set for the certificate store.
CertStoreType	An integer indicating the ID of the certificate store type, as defined in Keyfactor Command, for this certificate store. (0-Javakeystore,2-PEMFile, 3-F5SSLProfiles,4-IISRoots, 5-NetScaler, 6-IISPersonal, 7-F5WebServer, 8-IISRevoked, 9-F5WebServerREST, 10-F5SSLProfilesREST, 11-F5CABundlesREST, 100-AmazonWebServices, 101-FileTransferProtocol)
Approved	A Boolean that indicates whether a certificate store is approved (true) or not (false). If a certificate store is approved, it can be used and updated. A certificate store that has been discovered using the discover feature but not yet marked as approved will be false here.
CreatelfMissing	A Boolean that indicates whether a new certificate store should be created with the information provided (true) or not (false). This option is only valid for Java keystores and any custom certificate store types you have defined to support this functionality.
Properties	Some types of certificate stores have additional properties that are stored in this parameter. The data is stored in a series of, typically, key value pairs that define the property name and value (see <a href="Meta-Europeans-518">GET Certificate Store Types on page 518</a> for more information).  As of Keyfactor Command v10, this parameter is used to store certificate store server usernames, server passwords, and the UseSSL flag. Built-in certificate stores that typically require configuration of certificate store server parameters include NetScaler and F5 stores. The legacy

#### Name

#### Description

methods for managing certificate store server credentials have been deprecated but are retained for backwards compatiblity. For more information, see <a href="POST Certificate Stores Server">POST Certificate Stores Server</a> on page 441.

When reading this field, the values are returned as simple key value pairs, with the values being individual values. When writing, the values are specified as objects, though they are typically single values.

For example, on a GET request for a *PEM* store configured with a separate private key, the contents of this field might be:

```
"{
  \"privateKeyPath\":\"/opt/app/mystore.key\",
  \"separatePrivateKey\":\"true\"
}"
```

However, the syntax used when updating the properties sets the value as a key value pair using *value* as the key. For example, on a POST or PUT request for a *PEM* store configured with a separate private key, the contents of this field might be:

```
"{
  \"privateKeyPath\":{\"value\":\"/opt/app/mystore.key\"},
  \"separatePrivateKey\":{\"value\":\"true\"}
}"
```

An example server properties parameter POST for an FTP or NetScaler store would contain:

```
"{
    \"ServerUsername\":{\"value\":{\"SecretValue\":\"User_Name\"}},
    \"ServerPassword\":{\"value\":{\"SecretValue\":\"Password\"}},
    \"ServerUseSsl\":{\"value\":\"true\"}
}"
```

An example server properties parameter POST for an FTP or NetScaler store with the username and password stored as PAM secrets would contain (where the Provider value—1 in this example—is the Id value from GET PAM Providers on page 724):

```
"{
    \"ServerUsername\":{\"value\":{\"Provider\":\"1\",\"Parameters\":
{\"SecretId\":\"User_Name\"}}},
    \"ServerPassword\":{\"Provider\":\"1\",\"Parameters\":
{\"SecretId\":\"Password\"}}},
    \"ServerUseSsl\":{\"value\":\"true\"}
}"
```

Name	Description
	Note: There are three standard properties that are used for any built-in certificate store types that require server credentials (e.g. F5):  ServerUsername ServerPassword ServerUseSsI  These replace the separate certificate store server records that existed in previous versions of Keyfactor Command. For legacy support, if credentials are not provided through store properties during creation or editing of a certificate store, Keyfactor Command will attempt to find a certificate store server record and copy the credentials from it into the store properties for future use.  Tip: Built-in stores that make use of this field include: AWS stores use this field to store secured versions of the access key and secret. F5 REST stores (all types) use this field to store secured versions of the server authentication information (ServerUsername, ServerPassword, ServerUseSsI) and primary node information (PrimaryNode, PrimaryNodeCheckRetryWaitSecs, PrimaryNodeCheckRetryMax) and F5 version (F5Version).  F5 SOAP stores (all types) use this field to store secured versions of the server authentication information (ServerUsername, ServerPassword, ServerUseSsI).  FTP stores use this field to store secured versions of the server authentication information (ServerUsername, ServerPassword, ServerUseSsI).  Ils stores (all types) use this field to store the UseSSL flag and the port for WinRM communications.  Java keystores use this field to store type (ProviderType).  NetScaler stores use this field to store secured versions of the server authentication information (ServerUsername, ServerPassword, ServerUseSsI).
AgentId	A string indicating the Keyfactor Command GUID of the orchestrator for this store.
AgentAssigned	A Boolean that indicates whether there is an orchestrator assigned to this certificate store (true) or not (false).
ContainerName	A string indicating the name of the certificate store's associated container, if applicable.
InventorySchedule	The inventory schedule for this certificate store. The following schedule types are supported:

Name	Description					
	Name	Description				
	Off	Turn off a previo	Turn off a previously configured schedule.			
	Immediate	A Boolean that i (false).	indicates a job scheduled to run immediately (true) or not			
		N/Z	some instances, jobs initially scheduled as <i>Immediate</i> will on a GET as <i>null</i> .			
	Interval	specified param	It indicates a job scheduled to run every x minutes with the leter. Any interval that is selected in the UI will be converted in stored in the database.			
		Name	Description			
		Minutes	An integer indicating the number of minutes between each interval.			
	Daily	For example, every hour:				
		"Interval":     "Minutes				
		A dictionary that indicates a job scheduled to run every day at the same time with the parameter:				
		Name	Description			
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).			
		For example, da	nily at 11:30 pm:			
		"Daily": {     "Time": }	"2022-02-25T23:30:00Z"			

Name	Description						
	Name	Descript	ion				
	ExactlyOnce		A dictionary that indicates a job scheduled to run at the time specified with the parameter:				
		Name	Description				
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).				
		For exam	ple, exactly once at 11:45 am:				
			"ExactlyOnce": {     "Time": "2022-02-27T11:45:00Z" }				
		Tip: In some instances, jobs initially scheduled as <i>Immediate</i> will appear on a GET as <i>ExactlyOnce</i> .					
	ules, onl	y the schedu	Swagger Example Value may show examples of various other schedules shown here—that are available in the Management Portal for revalid for this endpoint.				
ReenrollmentStatus			her the certificate store can use the re-enrollment function with e re-enrollment job. The following reenrollment fields are				
	Name		Description				
	Data		A Boolean that indicates whether the certificate store can use the re-enrollment function (true) or not (false).				
	AgentId		A string indicating the Keyfactor Command GUID of the orchestrator that can re-enroll the certificate store.				
	Message		A string indicating the reason the certificate store cannot reenroll, if applicable.				
	JobProperties		An array of key/value pairs for the unique parameters defined				

Name	Description				
	Name	Description			
		for the certificate store type. The *key* is the name of the specific parameter from the certificate store type definition as returned in the JobProperties on the store type using the *GET CertificateStoreTypes* method and the *value* is the value that should be set for that parameter on a certificate in the certificate store. For example, for NetScaler, the key name that is optionally used to associate a certificate with a virtual server is *NetscalerVserver* and is returned by *GET CertificateStoreTypes* like so:  "JobProperties": ["NetscalerVserver"]  It can be seen in the Keyfactor Command Management Portal when editing the certificate store type in the field for *Management Job Custom Fields*.  The setting is referenced using the following format:  "JobProperties": [			
		This field is optional.			
	CustomAliasAllowed	An integer indicating the option for a custom alias for this certificate store.  • 0—forbidden  • 1—optional  • 2—required			
SetNewPass- wordAllowed	A Boolean that indicates wh	ether the store password can be changed (true) or not (false).			
Password	Note: Secret data is responses.	s stored in the secrets table or a PAM provider and is not returned in			

# 2.2.9.5 DELETE Certificate Stores ID

The DELETE /CertificateStores/{id} method is used to delete an existing certificate store with the specified GUID. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: CertificateStoreManagement: *Modify* 

Permissions for certificate stores can be set at either the global or certificate store container level. See *Container Permissions* in the *Keyfactor Command Reference Guide* for more information about global vs container permissions.

Table 195: DELETE Certificate Stores Input Parameters

Name	In	Description
id	Path	<b>Required</b> . A string indicating the GUID of the certificate store to delete.  Use the GET /CertificateStores method (see GET Certificate Stores on page 377) to retrieve a list of all the certificate stores to determine the certificate store GUID.

### 2.2.9.6 GET Certificate Stores ID

The GET /CertificateStores/{id} method is used to return details for the certificate store with the specified ID. This method returns HTTP 200 OK on a success with a message body containing certificate store details.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: CertificateStoreManagement: *Read* 

Permissions for certificate stores can be set at either the global or certificate store container level. See *Container Permissions* in the *Keyfactor Command Reference Guide* for more information about global vs container permissions.

Table 196: GET Certificate Stores {id} Input Parameters

Name	In	Description
id	Path	Required. A string indicating the GUID of the certificate store within Keyfactor Command.

Table 197: GET Certificate Stores {id} Response Data

Name	Description			
Id	A string indicating the GUID of the certificate store within Keyfactor Command. This ID is automatically set by Keyfactor Command.			
ContainerId	An integer indicating the ID of the certificate store's associated certificate store container, if applicable (see <a href="METCERTIFICATES">GET Certificate Store Containers on page 488</a> ).			
ClientMachine	The string value of the client machine. The value for this will vary depending on the certificate store type. For example, for a Java keystore or an F5 device, it is the hostname of the machine on which the store is located, but for an Amazon Web Services store, it is the FQDN of the Keyfactor Command Windows Orchestrator. See <i>Certificate Store Operations: Adding or Modifying a Certificate Store</i> in the <i>Keyfactor Command Reference Guide</i> for more information.			
Storepath	A string indicating the path to the certificate store on the target. The format for this path will vary depending on the certificate store type. For example, for a Java keystore, this will be a file path (e.g. /opt/myapp/store.jks), but for an F5 device, this will be a partition name on the device (e.g. Common). See <i>Certificate Store Operations: Adding or Modifying a Certificate Store</i> in the <i>Keyfactor Command Reference Guide</i> for more information.			
CertStoreIn- ventoryJobId	A string indicating the GUID that identifies the inventory job for the certificate store in the Keyfactor Command database. This will be null if an inventory schedule is not set for the certificate store.			
CertStoreType	An integer indicating the ID of the certificate store type, as defined in Keyfactor Command, for this certificate store. (0-Javakeystore,2-PEMFile, 3-F5SSLProfiles,4-IISRoots, 5-NetScaler, 6-IISPersonal, 7-F5WebServer, 8-IISRevoked, 9-F5WebServerREST, 10-F5SSLProfilesREST, 11-F5CABundlesREST, 100-AmazonWebServices, 101-FileTransferProtocol)			
Approved	A Boolean that indicates whether a certificate store is approved (true) or not (false). If a certificate store is approved, it can be used and updated. A certificate store that has been discovered using the discover feature but not yet marked as approved will be false here.			
CreatelfMissing	A Boolean that indicates whether a new certificate store should be created with the information provided (true) or not (false). This option is only valid for Java keystores and any custom certificate store types you have defined to support this functionality.			
Properties	Some types of certificate stores have additional properties that are stored in this parameter. The data is stored in a series of, typically, key value pairs that define the property name and value (see <a href="GET Certificate Store Types on page 518">GET Certificate Store Types on page 518</a> for more information).  As of Keyfactor Command v10, this parameter is used to store certificate store server usernames, server passwords, and the UseSSL flag. Built-in certificate stores that typically require configuration of certificate store server parameters include NetScaler and F5 stores. The legacy methods for managing certificate store server credentials have been deprecated but are retained for backwards compatibility. For more information, see <a href="POST Certificate Stores Server">POST Certificate Stores Server</a> on page 441.			

#### Name

#### Description

When reading this field, the values are returned as simple key value pairs, with the values being individual values. When writing, the values are specified as objects, though they are typically single values.

For example, on a GET request for a *PEM* store configured with a separate private key, the contents of this field might be:

```
"{
  \"privateKeyPath\":\"/opt/app/mystore.key\",
  \"separatePrivateKey\":\"true\"
}"
```

However, the syntax used when updating the properties sets the value as a key value pair using *value* as the key. For example, on a POST or PUT request for a *PEM* store configured with a separate private key, the contents of this field might be:

```
"{
  \"privateKeyPath\":{\"value\":\"/opt/app/mystore.key\"},
  \"separatePrivateKey\":{\"value\":\"true\"}
}"
```

An example server properties parameter POST for an FTP or NetScaler store would contain:

```
"{
    \"ServerUsername\":{\"value\":{\"SecretValue\":\"User_Name\"}},
    \"ServerPassword\":{\"value\":{\"SecretValue\":\"Password\"}},
    \"ServerUseSsl\":{\"value\":\"true\"}
}"
```

An example server properties parameter POST for an FTP or NetScaler store with the username and password stored as PAM secrets would contain (where the Provider value—1 in this example—is the Id value from GET PAM Providers on page 724):

```
"{
    \"ServerUsername\":{\"value\":{\"Provider\":\"1\",\"Parameters\":
{\"SecretId\":\"User_Name\"}}},
    \"ServerPassword\":{\"value\":{\"Provider\":\"1\",\"Parameters\":
{\"SecretId\":\"Password\"}}},
    \"ServerUseSs1\":{\"value\":\"true\"}
}"
```



**Note:** There are three standard properties that are used for any built-in certificate store types that require server credentials (e.g. F5):

ServerUsername

Name	Description			
	<ul> <li>ServerPassword</li> <li>ServerUseSsI</li> <li>These replace the separate certificate store server records that existed in previous versions of Keyfactor Command. For legacy support, if credentials are not provided through store properties during creation or editing of a certificate store, Keyfactor Command will attempt to find a certificate store server record and copy the credentials from it into the store properties for future use.</li> </ul>			
	<ul> <li>Tip: Built-in stores that make use of this field include:         <ul> <li>AWS stores use this field to store secured versions of the access key and secret.</li> <li>F5 REST stores (all types) use this field to store secured versions of the server authentication information (ServerUsername, ServerPassword, ServerUseSsI) and primary node information (PrimaryNode, PrimaryNodeCheckRetryWaitSecs, PrimaryNodeCheckRetryMax) and F5 version (F5Version).</li> <li>F5 SOAP stores (all types) use this field to store secured versions of the server authentication information (ServerUsername, ServerPassword, ServerUseSsI).</li> <li>FTP stores use this field to store secured versions of the server authentication information (ServerUsername, ServerPassword, ServerUseSsI).</li> <li>IIS stores (all types) use this field to store the UseSSL flag and the port for WinRM communications.</li> <li>Java keystores use this field to store type (ProviderType).</li> </ul> </li> <li>NetScaler stores use this field to store secured versions of the server authentication information (ServerUsername, ServerPassword, ServerUseSsI).</li> <li>PEM stores use this field to store the path to the private key file, if defined, and the Boolean value indicating whether a separate private key path is defined.</li> </ul>			
AgentId	A string indicating the Keyfactor Command GUID of the orchestrator for this store.			
AgentAssigned	A Boolean that indicates whether there is an orchestrator assigned to this certificate store (true) or not (false).			
ContainerName	A string indicating the name of the certificate store's associated container, if applicable.			
InventorySchedule	The inventory schedule for this certificate store. The following schedule types are supported:			
	Name Description			
	Off Turn off a previously configured schedule.			
	Immediate A Boolean that indicates a job scheduled to run immediately (true) or not			

Name	Description	scription			
	Name	Description			
		(false).			
		N/Z	some instances, jobs initially scheduled as <i>Immediate</i> will on a GET as <i>null</i> .		
	Interval	specified param	t indicates a job scheduled to run every x minutes with the eter. Any interval that is selected in the UI will be converted to tored in the database.		
		Name	Description		
		Minutes	An integer indicating the number of minutes between each interval.		
		For example, every hour:			
		"Interval": "Minutes }			
	Daily	A dictionary that with the parame	t indicates a job scheduled to run every day at the same time eter:		
		Name	Description		
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).		
		For example, da	ily at 11:30 pm:		
		"Daily": {     "Time": }	"2022-02-25T23:30:00Z"		

Name	Description				
	Name	Descript	ion		
	ExactlyOnce	A dictional	ary that indicates a job scheduled to run at the time specified with the er:		
		Name	Description		
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).		
		For exam	ple, exactly once at 11:45 am:		
		"ExactlyOnce": {     "Time": "2022-02-27T11:45:00Z" }			
		<b>Tip:</b> In some instances, jobs initially scheduled as <i>Immediate</i> will appear on a GET as <i>ExactlyOnce</i> .			
	ules, only	the schedu	Swagger Example Value may show examples of various other sched- les shown here—that are available in the Management Portal for this lid for this endpoint.		
Reen- rollmentStatus			ner the certificate store can use the re-enrollment function with accom- rollment job. The following reenrollment fields are supported:		
	Name		Description		
	Data		A Boolean that indicates whether the certificate store can use the re-enrollment function (true) or not (false).		
	AgentId		A string indicating the Keyfactor Command GUID of the orchestrator that can re-enroll the certificate store.		
	Message		A string indicating the reason the certificate store cannot re-enroll, if applicable.		
	JobProperties		An array of key/value pairs for the unique parameters defined for the certificate store type. The <i>key</i> is the name of the specific para- meter from the certificate store type definition as returned in the		

Name	Description			
	Name	Description		
		JobProperties on the store type using the GET CertificateStoreTypes method and the value is the value that should be set for that parameter on a certificate in the certificate store. For example, for NetScaler, the key name that is optionally used to associate a certificate with a virtual server is NetscalerVserver and is returned by GET CertificateStoreTypes like so:  "JobProperties": [ "NetscalerVserver" ]  It can be seen in the Keyfactor Command Management Portal when editing the certificate store type in the field for Management Job Custom Fields.  The setting is referenced using the following format:  "JobProperties": [ {"NetscalerVserver": "MyVirtualServerName"} ]  Note: The only built-in certificate store type that makes use of job properties that can be set on a certificate-bycertificate basis in the store is NetScaler. You may have custom certificate store types that make use of this functionality.		
		This field is optional.		
	CustomAliasAllowed	An integer indicating the option for a custom alias for this certificate store.		
		• 0—forbidden		
		• 1—optional		
		• 2—required		
SetNewPass- wordAllowed	A Boolean that indicates wh	nether the store password can be changed (true) or not (false).		
Password	use to access the certificate credential information Keyf former (this setting) is typic stores on NetScaler and F5  POST Certificate Stores Service Certificate stores that requires the company of the company of the certificate store passwords are passwords.	ire credentials support up to three possible credential options:		

Name	Description					
	<ul> <li>Store the credential information in the Keyfactor secrets table.</li> <li>A Keyfactor secret is a user-defined password that is encrypted and stored securely in the Keyfactor Command database.</li> </ul>					
	<ul> <li>Load the credential information from a PAM provider.</li> <li>See Privileged Access Management (PAM) in the Keyfactor Command Reference Guide and PAM Providers on page 709 for more information.</li> </ul>					
	The possible values are:					
	Name	Description				

Name	Description
Value	A string—submitted as an object—indicating a password to be stored as a Keyfactor secret.
	Tip: To set the no password option on a store, submit the password with a null value. For example:  "Password": {  "Value": {null}  }  To set the value to a string to be stored in the Keyfactor secrets table, include the password in quotes. For example:  "Password": {  "Value": "MyVerySecurePassword"  }
SecretTypeG- uid	A string indicating the Keyfactor Command reference GUID for the type of credentials. This value is automatically set by Keyfactor Command.
InstanceId	The Keyfactor Command reference ID for the secret provider. If you are using a secret provider with an integer ID, this will be used. This value is automatically set by Keyfactor Command.
InstanceGuid	The Keyfactor Command reference GUID for the secret provider. If you are using a secret provider with a GUID ID, this will be used. This value is automatically set by Keyfactor Command.
ProviderType Para- meterValues	An array containing the values for the PAM provider types specified by ProviderTypeParams. The provider type parameter values include:

Name	Description				
	Name	Description			
		Name	Description		
		Id	The Keyfactor Cor provider type par	mmand reference ID for the PAM ameter.	
		Value		the parameter (e.g. the name of the where the protected object that stores the sword resides).	
		InstanceId		mmand reference ID for the PAM re attaching to something with an integer ed.	
		InstanceG- uid		The Keyfactor Command reference GUID for the PAM provider. If you are attaching to something with a GUID ID, this will be used.	
		Provider	An array containing information about the provider. PAM provider details include:		
			Name	Description	
			Id	An integer indicating the Keyfactor Command reference ID for the PAM provider.	
			Name	A string indicating the internal name for the PAM provider.	
			Area	An integer indicating the area of Keyfactor Command the provider is used for. PAM providers generally have a value of 1, indicating they are used for certificate stores.	
			ProviderType	An array containing details about the provider type for the provider, including:	

Name	Description				
	Name	Description			
		Name	Description		
			Name	Description	
				Name	Description
				Id	A string indicating the Keyfactor Command reference GUID for the provider type.
				Name	A string that indicates the name of the provider type.
				Provider Type Params	An array of parameters that the provider type uses for data input in Keyfactor Command when creating new PAM provider and certificate store records.  See below instance of Provider-TypeParam for details.
			ProviderType ParamValues	the provider ProviderType previous leve	taining the values for types specified by Params. See the el of <i>Provider-</i> alues for details.

Name	Description			
	Name	Description		
		Name	Description	
			Name	Description
			SecuredAreald	An integer indicating the Keyfactor Command reference ID for the certificate store container the PAM provider is associated with, if any.  You can create a single PAM provider for each provider type (e.g. CyberArk), however, if you have opted to organize your certificate stores into containers, you will need to create multiple providers to match your container organization structure. The container field in the PAM provider definition is not required, but if one is supplied when creating a PAM provider, the PAM provider can only be used with certificate stores in the matching container. Likewise, a PAM provider defined with no container would be available for selection when setting passwords for any certificate store that also did not specify a container. A PAM provider configured in this way could be used across a variety of certificate stores (e.g. both JKS and F5) as long as they were not in containers.
		Provider- Type Param	input in Keyfactor	neters that the provider type uses for data Command when creating new PAM ificate store records. PAM provider type de:

Name	Description			
	Name	Description		
		Name	Description	
			Name	Description
			Id	An integer indicating the Keyfactor Command reference ID for the PAM provider type parameter.
			Name	A string indicating the internal name for the PAM provider type parameter.
			DisplayNa- me	A string indicating the display name for the PAM provider type parameter. For parameters with an InstanceLevel of false, this name appears on the PAM provider dialog for the parameter when a user creates a new PAM provider. For parameters with an InstanceLevel of true, this name appears on the Server dialog for the parameter when a user creates a new PAM provider.
			DataType	An integer indicating the data type for the parameter. Possible values are:  • 1 = String  • 2 = Secret
			InstanceLe- vel	A Boolean that sets whether the parameter is used to define the underlying PAM provider (false) or a field that needs to be set to a value when configuring a certificate store to use the PAM provider (true).  For an example, see GET PAM
			Provider-	Providers on page 724.  An array containing details for the

Name	Description				
	Name	Description			
		Name	Description		
			Name	Description	
			Туре	provider type.	
				Name	Descrip- tion
				Id	A string indicating the Keyfactor Command reference GUID for the PAM provider type para- meter.
				Name	A string indicating the internal name for the PAM provider type parameter.
				Provider- TypeParams	Unused field
	ProviderId	An integer indi provider.	cating the Keyfacto	or Command reference	ID for the PAM
	IsManaged	PAM provider		e credentials for the sto the Keyfactor secrets to Command.	

Name	Description		
	Note: Secret data is stored in the secrets table or a PAM provider and is not returned in responses.		

# 2.2.9.7 GET Certificate Stores ID Inventory

The GET /CertificateStores/{id}/Inventory method is used to return a list of all the certificates found in the selected certificate store based on an inventory done using Keyfactor Command an approved orchestrator. The results include both end entity certificates and chain certificates found in the store. This method allows URL parameters to specify paging and sorting. This method returns HTTP 200 OK on a success with details about the certificates in the store.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: CertificateStoreManagement: *Read* 

Permissions for certificate stores can be set at either the global or certificate store container level. See *Container Permissions* in the *Keyfactor Command Reference Guide* for more information about global vs container permissions.

Table 198: GET Certificate Stores {id} Inventory Input Parameters

Name	In	Description
id	Path	<b>Required</b> . A string indicating the GUID of the certificate store within Keyfactor Command.
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>Name</i> .
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.

Table 199: GET Certificate Stores {id} Inventory Response Data

Name	Description			
Name	A string indicating the alias for the certificate in the certificate store. The format for this varies depending on the certificate store type and whether the <i>Overwrite</i> flag is selected. See the <a href="PFX Enrollment">PFX Enrollment</a> section of the <i>Keyfactor Command Reference Guide</i> for more information.			
Certificates	An array of certificates (end entity and chain) found in the certificate store. Certificate details include:			
	Name	Description		
	Id	An integer indicating the Keyfactor Command reference ID of the certificate.		
	IssuedDN	A string indicating the distinguished name of the certificate.		
	SerialNumber	A string indicating the serial number of the certificate.		
	NotBefore	The date, in UTC, on which the certificate was issued by the certificate authority.		
	NotAfter	The date, in UTC, on which the certificate expires.		
	SigningAlgorithm	A string indicating the algorithm used to sign the certificate.		
	IssuerDN	A string indicating the distinguished name of the issuer.		
	Thumbprint	A string indicating the thumbprint of the certificate.		
	CertStoreInventoryItemId	An integer indicating the Keyfactor Command referenced ID of the certificate in the certificate store.		
CertStoreInventoryItemId	An integer indicating the Keyfactor Command reference ID of the certificate in the certificate store.			
Parameters	An array of entry parameters associated with the certificate in the certificate store. Expected entry parameters will vary depending on the configuration of the certificate store type. See <a href="POST Certificate Store Types on page 523">POST Certificate Store Types on page 523</a> for more information about entry parameters.			

### 2.2.9.8 GET Certificate Stores Server

The GET /CertificateStores/Server method is used to retrieve all servers for certificate stores. Only select types of certificate stores have an associated server. These include F5, FTP, NetScaler, and any custom method you've defined to support this. This method returns HTTP 200 OK on a success with details for each server.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: CertificateStoreManagement: *Read* 

Permissions for certificate stores can be set at either the global or certificate store container level. See *Container Permissions* in the *Keyfactor Command Reference Guide* for more information about global vs container permissions.



**Note:** This method has been deprecated and will be removed from the Keyfactor API in release 12. Certificate store server information is now found in the certificate store (see <u>GET Certificate Stores on page 377</u>).

Table 200: GET Certificate Stores Server Input Parameters

Name	In	Description
queryString	Query	A string containing a query to limit the results (e.g. field1 -eq value1 AND field2 -gt value2). The default is to return all records. Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns for the same feature. For querying guidelines, refer to the Keyfactor Command Reference Guide: Using the Certificate Store Search Feature section. The query fields supported for this endpoint are:  • Id  • Name  • ServerType
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>Id</i> .
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.

Table 201: GET Certificate Stores Server Response Data

Name	Description		
Id	The ID of the server.		
Username	The username used to connect	to the certificate store.	
	Note: Secret data is stored in the secrets table or a PAM provider and is not ret responses.		
Password	The password used to connect	to the certificate store.	
	Note: Secret data is stored in the secrets table or a PAM provider and is not returned in responses.		
UseSSL	A Boolean that indicates whether Keyfactor Command will use SSL to communicate with the server (true) or not (false).		
ServerType	An integer indicating the type of server. Possible values include (plus any custom values):		
	Value	Description	
	0	F5 Web Server & F5 SSL Profiles	
	1	NetScaler	
	2	FTP	
	3	F5 Web Server REST	
	4	F5 SSL Profiles REST	
	5	F5 CA Bundles REST	
Name	The host name of the server.		

## 2.2.9.9 POST Certificate Stores Server

The POST /CertificateStores/Server method is used to create a new server record for a certificate store in Keyfactor Command. This method returns HTTP 200 OK on a success with details of the newly created server record.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: CertificateStoreManagement: *Modify* 



Permissions for certificate stores can be set at either the global or certificate store container level. Creating new certificate store server records requires permissions at the global level. See <u>Container Permissions</u> in the *Keyfactor Command Reference Guide* for more information about global vs container permissions.



**Note:** This method has been deprecated and will be removed from the Keyfactor API in a future release. This method is retained until that time for backwards compatibility. Continuing to use this endpoint with the latest Keyfactor Command functionality could cause serious data issues. Certificate store server information is now found in the certificate store (see <u>POST Certificate Stores on page 384</u>). The Management Portal has additional functionality, such as being able to set different credentials for different stores on the same server, which use the new API endpoint.



**Tip:** If a certificate store that requires a server is missing a server definition within the store record, the certificate store server created with this method will be used. If no credentials are supplied in the request and no certificate store server exists, an error is returned and the request fails.

Table 202: POST Certificate Stores Server Input Parameters

Name	In	Description		
Username Body	Body	Required. The use include:	ername used to connect to the certificate store. Username parameters	
		Name	Description	
		SecretValue	A string containing the username.  This value only needs to be supplied if you're storing your username in the Keyfactor Command database.	
		Provider	An integer that identifies the PAM provider used to store the username. Use the GET /PamProviders method (see GET PAM Providers on page 724) to retrieve a list of your defined PAM providers to determine the PAM provider ID to use. See PAM Provider Configuration in Keyfactor Command in the Keyfactor Command Reference Guide for more information.  This value only needs to be supplied if you're storing your username using a PAM provider.	
		Parameters	The parameters required by your PAM provider, containing the information that identifies the location of the username in the PAM solution. Use the <i>GET /PamProviders</i> method (see <u>GET PAM Providers on page 724</u> ) to retrieve a list of the parameters used by your PAM provider. Only parameters where <i>InstanceLevel</i> is equal to <i>true</i> need to be supplied in the request.  For example, for Delinea (formerly Thycotic), this might be:	
			<pre>"Username": {     "Provider": 2,     "Parameters": {         "SecretId": 4     } },</pre>	
			For CyberArk, this might be:	
			<pre>"Username": {     "Provider": 5,     "Parameters": {         "Folder": "Root",         "Object": "F5Username"     } },</pre>	

Name	In	Description	Description		
Password	Body	<b>Required</b> . The password used to connect to the certificate store. Password parameters include:			
		Name	Description		
		SecretValue	A string containing the password. This value only needs to be supplied if you're storing your password in the Keyfactor Command database.		
		Provider	An integer that identifies the PAM provider used to store the password. Use the GET/PamProviders method (see GET PAM Providers on page 724) to retrieve a list of your defined PAM providers to determine the PAM provider ID to use.		
		Parameters	The parameters required by your PAM provider, containing the information that identifies the location of the password in the PAM solution. Use the GET /PamProviders method (see GET PAM Providers on page 724) to retrieve a list of the parameters used by your PAM provider. Only parameters where InstanceLevel is equal to true need to be supplied in the request.  For example, for Delinea, this might be:		
			<pre>"Password": {     "Provider": 2,         "Parameters": {         "SecretId": 5      } },</pre>		
			For CyberArk, this might be:		
			<pre>"Password": {     "Provider": 5,     "Parameters": {         "Folder": "Root",         "Object": "F5Password"     } },</pre>		
UseSSL	Body	A Boolean that indicates whether Keyfactor Command will use SSL to communicate with the server (true) or not (false). The default is <i>false</i> .			
ServerType	Body	An integer indicating	g the type of server. Possible values include (plus any custom values):		

Name	In	Description	
		Value	Description
		0	F5 Web Server & F5 SSL Profiles
		1	NetScaler
		2	FTP
		3	F5 Web Server REST
		4	F5 SSL Profiles REST
		5	F5 CA Bundles REST
		to locate the server types fo	reTypes method (see GET Certificate Store Types on page 518) or your custom certificate store types. The ServerRegistration nod maps to the ServerType.
Name	Body	Required. The host name of the server.	
Container	Body	An integer that identifies the certificate store container into which the certificate store should be placed for organizational and management purposes. This value must be specified if you are using PAM to store your username and/or password and your PAM provider has been configured to be linked to a specific certificate store container.	

Table 203: POST Certificate Stores Server Response Data

Name	Description		
Id	The ID of the server.		
UseSSL	A Boolean that indicates whether Keyfactor Command will use SSL to communicate with the server (true) or not (false).		
ServerType	An integer indicating the type o	f server. Possible values include (plus any custom values):	
	Value	Description	
	0	F5 Web Server & F5 SSL Profiles	
	1	NetScaler	
	2	FTP	
	3	F5 Web Server REST	
	4	F5 SSL Profiles REST	
	5	F5 CA Bundles REST	
Name	The host name of the server.		

### 2.2.9.10 PUT Certificate Stores Server

The PUT /CertificateStores/Server method is used to update the server record for a certificate store in Keyfactor Command. This method returns HTTP 200 OK on a success with details of the server record.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: CertificateStoreManagement: *Modify* 

Permissions for certificate stores can be set at either the global or certificate store container level. Updating certificate store server records requires permissions at the global level. See <a href="Container Permissions">Container Permissions</a> in the <a href="Keyfactor Command Reference Guide">Keyfactor Command Reference Guide</a> for more information about global vs container permissions.



**Note:** This method has been deprecated and will be removed from the Keyfactor API in a future release. This method is retained until that time for backwards compatibility. Continuing to use this endpoint with the latest Keyfactor Command functionality could cause serious data issues. The Management Portal has additional functionality, such as being able to set different credentials for different stores on the same server, which use the new <a href="PUT Certificate Stores on page 404">PUT Certificate Stores on page 404</a> API endpoint. Using this deprecated API endpoint could potentially, for instance, overwrite all cert stores on the server.



Warning: Any previously populated fields that are not submitted with their full existing data using this method will be cleared of their existing data. When using this method, you should first do a GET to retrieve all the values for the record you want to update, enter corrected data into the field(s) you want to update, and then submit all the fields using PUT, including the fields that contain values but which you are not changing.

Table 204: PUT Certificate Stores Server Input Parameters

Name	In	Description			
Id	Body	The ID of the server.	The ID of the server.		
Username	Body	<b>Required</b> . The username used to connect to the certificate store. Username parameters			
		Name	Description		
		SecretValue	A string containing the username.  This value only needs to be supplied if you're storing your username in the Keyfactor Command database.		
		Parameters	An integer that identifies the PAM provider used to store the username. Use the GET /PamProviders method (see GET PAM Providers on page 724) to retrieve a list of your defined PAM providers to determine the PAM provider ID to use. See PAM Provider Configuration in Keyfactor Command in the Keyfactor Command Reference Guide for more information.  This value only needs to be supplied if you're storing your username using a PAM provider.		
			The parameters required by your PAM provider, containing the information that identifies the location of the username in the PAM solution. Use the GET /PamProviders method (see GET PAM Providers on page 724) to retrieve a list of the parameters used by your PAM provider. Only parameters where InstanceLevel is equal to true need to be supplied in the request.  For example, for Delinea (formerly Thycotic), this might be:  "Username": {     "Provider": 2,     "Parameters": {         "SecretId": 4       }     } },		
			For CyberArk, this might be:		
			"Username": {     "Provider": 5,     "Parameters": {         "Folder": "Root",         "Object": "F5Username"     } },		

Name	In	Description				
Password	Body	<b>Required</b> . The password used to connect to the certificate store. Password parameters include:				
		Name	Description			
		SecretValue	A string containing the password. This value only needs to be supplied if you're storing your password in the Keyfactor Command database.			
		Provider	An integer that identifies the PAM provider used to store the password. Use the <i>GET/PamProviders</i> method (see <u>GET PAM Providers</u> on page 724) to retrieve a list of your defined PAM providers to determine the PAM provider ID to use.			
		Parameters	The parameters required by your PAM provider, containing the information that identifies the location of the password in the PAM solution. Use the GET /PamProviders method (see GET PAM Providers on page 724) to retrieve a list of the parameters used by your PAM provider. Only parameters where InstanceLevel is equal to true need to be supplied in the request.  For example, for Delinea, this might be:			
			<pre>"Password": {     "Provider": 2,         "Parameters": {         "SecretId": 5     } },</pre>			
			For CyberArk, this might be:			
			<pre>"Password": {     "Provider": 5,     "Parameters": {         "Folder": "Root",         "Object": "F5Password"     } },</pre>			
UseSSL	Body	A Boolean that indicates whether Keyfactor Command will use SSL to communicate with the server (true) or not (false). The default is <i>false</i> .				
Name	Body	Required. The host name of the server.				

Name	In	Description
Container	Body	An integer that identifies the certificate store container into which the certificate store should be placed for organizational and management purposes. This value must be specified if you are using PAM to store your username and/or password and your PAM provider has been configured to be linked to a specific certificate store container.

Table 205: PUT Certificate Stores Server Response Data

Name	Description		
Id	The ID of the server.		
UseSSL	A Boolean that indicates whether Keyfactor Command will use SSL to communicate with the server (true) or not (false).		
ServerType	An integer indicating the type o	f server. Possible values include (plus any custom values):	
	Value	Description	
	0	F5 Web Server & F5 SSL Profiles	
	1 NetScaler		
	2	FTP	
	3	F5 Web Server REST	
	4	F5 SSL Profiles REST	
	5 F5 CA Bundles REST		
Name	The host name of the server.		

# 2.2.9.11 PUT Certificate Stores Password

The PUT /CertificateStores/Password method is used to update a password for a certificate store that supports this functionality. This updates the password stored in Keyfactor Command for the certificate store but does not update the certificate store itself. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: CertificateStoreManagement: *Modify* 



Table 206: PUT Certificate Stores Password Input Parameters

Name	Туре	Description			
CertStoreID	Body	<b>Required</b> . A string indicating the GUID of the certificate store. Use the <i>GET CertificateStores</i> method (see <u>GET Certificate Stores on page 377</u> ) to retrieve a list of all your certificate stores to determine the GUID of the store.			
NewPassword	Body	certificate store. It o	nat sets the password used by Keyfactor Command to access the does not impact the certificate store itself, just Keyfactor on of it. Password settings include:		
		Name	Description		
		SecretValue	A string containing the password. This value only needs to be supplied if you're storing your password in the Keyfactor Command database.		
		Provider	An integer that identifies the PAM provider used to store the password. Use the GET /PamProviders method (see GET PAM Providers on page 724) to retrieve a list of your defined PAM providers to determine the PAM provider ID to use.  This value only needs to be supplied if you're storing your password using a PAM provider.		
		Parameters	The parameters required by your PAM provider, containing the information that identifies the location of the password in the PAM solution. Use the GET /PamProviders method (see GET PAM Providers on page 724) to retrieve a list of the parameters used by your PAM provider. Only parameters where InstanceLevel is equal to true need to be supplied in the request.  For example, for Delinea (formerly Thycotic), this might be:  "NewPassword": {  "Provider": 2,  "Parameters": {  "SecretId": 5  }  },  For CyberArk, this might be:  "NewPassword": {  "Provider": 5,  "Parameters": {  "Folder": "Root",  "Object": "F5Password"		

Name	Туре	Description		
			Description	
			} },	
		For a password store	ed in the Keyfactor Command database, this might be:	
		"NewPassword": "SecretValue }	{ =": "P@ssw0rd"	

## 2.2.9.12 PUT Certificate Stores Discovery Job

The PUT /CertificateStores/DiscoveryJob method is used to schedule a discovery job for certificate stores. The certificate store discovery feature is used to scan machines and devices for existing certificates and certificate stores, which can then be configured for management in Keyfactor Command. Certificate store discovery is supported for:

- PEM and Java certificate stores discovered by the Keyfactor Java Agent. Only stores to which the service account running the Keyfactor Java Agent has at least read permissions will be returned on a discover job.
- F5 bundle and SSL certificates discovered by the Keyfactor Windows Orchestrator on F5 devices using the F5 REST API (v14 and up).
- F5 bundle and SSL certificates discovered by the Keyfactor Universal Orchestrator with a custom extension to support F5. For more information about the Keyfactor Universal Orchestrator and custom extensions, see the <a href="Installing Orchestrators">Installing Orchestrators</a> guide.
- Any custom certificate store types configured to support this function.

This endpoint returns 204 with no content upon success. The method schedules the discovery job through the orchestrator. The results of the discovery job are determined separately (see <a href="POST Certificate Stores Approve on page 466">POST Certificate Stores Approve on page 466</a>).



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: CertificateStoreManagement: *Modify* 

Table 207: PUT Certificate Stores Discovery Job Input Parameters

Name	In	Description	
ClientMachine	Body	<b>Required</b> . A string indicating the name in Keyfactor Command of the client machine that will do the discovery. This is not necessarily the actual DNS name of the server; the orchestrator may have been installed using an alternative as a reference name.	
AgentId	Body	<b>Required</b> . A string indicating the Keyfactor Command reference GUID of the orchestrator for this store.	
Туре	Body	An integer indicating the ID of the certificate store type, as defined in Keyfactor Command, for this certificate store. (0-Javakeystore,2-PEMFile, 3-F5SSLProfiles,4-IISRoots, 5-NetScaler, 6-IISPersonal, 7-F5WebServer, 8-IISRevoked, 9-F5WebServerREST, 10-F5SSLProfilesREST, 11-F5CABundlesREST, 100-AmazonWebServices, 101-FileTransferProtocol) The default is 0 for a JKS discovery.	
JobExecutionTimestamp	Body	The date and time at which the discovery job should run. If no date is provided, the job will be scheduled to run immediately. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
Dirs	Body	Required. A string containing the directory or directories to search during the discovery job. Multiple directories should be separated by commas.  Java  For Java discovery, enter at a minimum either "/" for a Linux server or "c:\" for a Windows server.  PEM  For PEM discovery, enter at a minimum either "/" for a Linux server or "c:\" for a Windows server.  F5  For F5 discovery, enter "/".	
IgnoredDirs	Body	A string containing the directories that should not be included in the search. Multiple directories should be separated by commas.	
Extensions	Body	A string containing the file extensions for which to search. For example, search for files with the extension "jks" in order to exclude files with other extensions such as "txt". The dot should not be included when specifying extensions.	

Name	In	Description	
NamePatterns	Body	A string against which to compare the file names of certificate store files and return only those that contain the specified string (e.g. "myjks").	
SymLinks	Body	A Boolean that sets whether the job should follow symbolic links on Linux and UNIX operating systems and report both the actual location of a found certificate store file in addition to the symbolic link pointing to the file. This option is ignored on Windows.	
Compatibility	Body	A Boolean that sets whether the job will run using the compatibility mode introduced in Java version 1.8 to locate both JKS and PKCS12 type files (true) or not (false). This option applies only to Java keystore discover jobs.	

Name	In	Description		
ServerUsername	Body	<b>Required</b> *. The username used to connect to the certificate store server.		
		Name	Description	
			SecretValue	A string containing the username.  This value only needs to be supplied if you're storing your username in the Keyfactor Command database.
		Provider	An integer that identifies the PAM provider used to store the username. Use the GET /PamProviders method (see GET PAM Providers on page 724) to retrieve a list of your defined PAM providers to determine the PAM provider ID to use. See the PAM Provider Configuration in Keyfactor Command section of the Keyfactor Command Reference Guide for more information.  This value only needs to be supplied if you're storing your username using a PAM provider.	
		Parameters	The parameters required by your PAM provider, containing the information that identifies the location of the username in the PAM solution. Use the GET /PamProviders method (see GET PAM Providers on page 724) to retrieve a list of the parameters used by your PAM provider. Only parameters where InstanceLevel is equal to true need to be supplied in the request.  For example, for Delinea (formerly Thycotic), this might be:  "ServerUsername": {  "Provider": 2,  "Parameters": {  "SecretId": 4  }  },  For CyberArk, this might be:  "ServerUsername": {  "Provider": 5,  "Parameters": {  "Folder": "Root",  "Object": "F5Username"  }	

Name	In	Description	
		Name	Description
		SecretValue	A string containing the username.  This value only needs to be supplied if you're storing your username in the Keyfactor Command database.
		Provider	An integer that identifies the PAM provider used to store the username. Use the GET /PamProviders method (see GET PAM Providers on page 724) to retrieve a list of your defined PAM providers to determine the PAM provider ID to use. See the PAM Provider Configuration in Keyfactor Command section of the Keyfactor Command Reference Guide for more information.  This value only needs to be supplied if you're storing your username using a PAM provider.
		Parameters	The parameters required by your PAM provider, containing the information that identifies the location of the username in the PAM solution. Use the GET /PamProviders method (see GET PAM Providers on page 724) to retrieve a list of the parameters used by your PAM provider. Only parameters where InstanceLevel is equal to true need to be supplied in the request.  For example, for Delinea (formerly Thycotic), this might be:
			"ServerUsername": {     "Provider": 2,     "Parameters": {         "SecretId": 4      } },
			For CyberArk, this might be:  "ServerUsername": {  "Provider": 5,  "Parameters": {  "Folder": "Root",  "Object": "F5Username"  } },

Name	In	Description			
		Note: Secret data is stored in the secrets table or a PAM provider and is not returned in responses.			
		authentication at th	d only for select certificate store types that require e server level. These include F5, FTP, NetScaler, and any 've defined to support this.		
ServerPassword	Body		<b>Required</b> *. The password used to connect to the certificate store server. Password parameters include:		
		Name	Description		
		SecretValue	A string containing the password. This value only needs to be supplied if you're storing your password in the Keyfactor Command database.		
		Provider	An integer that identifies the PAM provider used to store the password. Use the <i>GET /PamProviders</i> method (see <u>GET PAM Providers on page 724</u> ) to retrieve a list of your defined PAM providers to determine the PAM provider ID to use.		
		Parameters	The parameters required by your PAM provider, containing the information that identifies the location of the password in the PAM solution. Use the GET /PamProviders method (see GET PAM Providers on page 724) to retrieve a list of the parameters used by your PAM provider. Only parameters where InstanceLevel is equal to true need to be supplied in the request.  For example, for Delinea, this might be:  "Password": {  "Provider": 2,  "Parameters": {  "SecretId": 5  }  },  For CyberArk, this might be:  "Password": {  "Provider": 5,  "Parameters": {		
			InstanceLevel is equal to true need to be support the request.  For example, for Delinea, this might be:  "Password": {  "Provider": 2,  "Parameters": {  "SecretId": 5  }  },  For CyberArk, this might be:  "Password": {		

Name	In	Description	
		Name	Description
		Note: Secre	"Object": "F5Password" } }, t data is stored in the secrets table or a PAM provider
			turned in responses.
		authentication at the	only for select certificate store types that require e server level. These include F5, FTP, NetScaler, and any ve defined to support this.
ServerUseSsI	Body	A Boolean that indicates whether Keyfactor Command will use SSL to connicate with the certificate store server (true) or not (false). The default is false.	

# 2.2.9.13 PUT Certificate Stores Assign Container

The PUT /CertificateStores/AssignContainer method is used to assign one or more certificate stores to a container. This method returns HTTP 200 OK on a success with the certificate stores that were just assigned to a container.

If you are creating a new container and assigning stores to it in one action, you should include the following fields:

- NewContainerName
- NewContainerType
- Keystorelds

If you are assigning stores to an already existing container, you should include the following fields:

- CertStoreContainerId
- Keystorelds



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: CertificateStoreManagement: *Modify* 

Table 208: PUT Certificate Stores Assign Container Input Parameters

Name	In	Description
CertStoreContainerId	Body	Required*. An integer that identifies the container into which you want to place the certificate store or stores.  One of the following is required:  • CertStoreContainerId  • NewContainerName and NewContainerType
Keystorelds	Body	<b>Required</b> . An array of certificate store GUIDs for the stores you want to place into the container.
NewContainerName	Body	Required*. A string that sets the name of the container if you would like to create a new container while assigning store(s) to it.  One of the following is required:  • CertStoreContainerId  • NewContainerName and NewContainerType
NewContainerType	Body	Required*. An integer for the container type if you would like to create a new container while assigning store(s) to it. Container types match certificate store types.  Use the GET / CertificateStoreTypes method with a query (e.g. storetype -eq 7) or GET / CertificateStoreTypes/{id} method to determine what a particular certificate store type ID maps to. For example, type 2 maps to PEM File and type 10 maps to F5 SSL Profiles REST.  One of the following is required:  • CertStoreContainerId  • NewContainerName and NewContainerType

Table 209: PUT Certificate Stores Assign Container Response Data

Name	Description
Id	A string indicating the GUID of the certificate store within Keyfactor Command. This ID is automatically set by Keyfactor Command.
ContainerId	An integer indicating the ID of the certificate store's associated certificate store container, if applicable (see <u>GET Certificate Store Containers on page 488</u> ).
ClientMachine	The string value of the client machine. The value for this will vary depending on the certificate store type. For example, for a Java keystore or an F5 device, it is the hostname of the machine on which the store is located, but for an Amazon Web Services store, it is the FQDN of the Keyfactor Command Windows Orchestrator. See <i>Certificate Store Operations: Adding or Modifying a Certificate Store</i> in the <i>Keyfactor Command Reference Guide</i> for more information.
Storepath	A string indicating the path to the certificate store on the target. The format for this path will vary depending on the certificate store type. For example, for a Java keystore, this will be a file path (e.g. /opt/myapp/store.jks), but for an F5 device, this will be a partition name on the device (e.g. Common). See <i>Certificate Store Operations: Adding or Modifying a Certificate Store</i> in the <i>Keyfactor Command Reference Guide</i> for more information.
CertStoreIn- ventoryJobId	A string indicating the GUID that identifies the inventory job for the certificate store in the Keyfactor Command database. This will be null if an inventory schedule is not set for the certificate store.
CertStoreType	An integer indicating the ID of the certificate store type, as defined in Keyfactor Command, for this certificate store. (0-Javakeystore,2-PEMFile, 3-F5SSLProfiles,4-IISRoots, 5-NetScaler, 6-IISPersonal, 7-F5WebServer, 8-IISRevoked, 9-F5WebServerREST, 10-F5SSLProfilesREST, 11-F5CABundlesREST, 100-AmazonWebServices, 101-FileTransferProtocol)
Approved	A Boolean that indicates whether a certificate store is approved (true) or not (false). If a certificate store is approved, it can be used and updated. A certificate store that has been discovered using the discover feature but not yet marked as approved will be false here.
CreatelfMissing	A Boolean that indicates whether a new certificate store should be created with the information provided (true) or not (false). This option is only valid for Java keystores and any custom certificate store types you have defined to support this functionality.
Properties	Some types of certificate stores have additional properties that are stored in this parameter. The data is stored in a series of, typically, key value pairs that define the property name and value (see <a href="GET Certificate Store Types on page 518">GET Certificate Store Types on page 518</a> for more information).  As of Keyfactor Command v10, this parameter is used to store certificate store server user-
	names, server passwords, and the UseSSL flag. Built-in certificate stores that typically require configuration of certificate store server parameters include NetScaler and F5 stores. The legacy

#### Name

#### Description

methods for managing certificate store server credentials have been deprecated but are retained for backwards compatiblity. For more information, see <a href="POST Certificate Stores Server">POST Certificate Stores Server</a> on page 441.

When reading this field, the values are returned as simple key value pairs, with the values being individual values. When writing, the values are specified as objects, though they are typically single values.

For example, on a GET request for a *PEM* store configured with a separate private key, the contents of this field might be:

```
"{
  \"privateKeyPath\":\"/opt/app/mystore.key\",
  \"separatePrivateKey\":\"true\"
}"
```

However, the syntax used when updating the properties sets the value as a key value pair using *value* as the key. For example, on a POST or PUT request for a *PEM* store configured with a separate private key, the contents of this field might be:

```
"{
  \"privateKeyPath\":{\"value\":\"/opt/app/mystore.key\"},
  \"separatePrivateKey\":{\"value\":\"true\"}
}"
```

An example server properties parameter POST for an FTP or NetScaler store would contain:

```
"{
    \"ServerUsername\":{\"value\":{\"SecretValue\":\"User_Name\"}},
    \"ServerPassword\":{\"value\":{\"SecretValue\":\"Password\"}},
    \"ServerUseSsl\":{\"value\":\"true\"}
}"
```

An example server properties parameter POST for an FTP or NetScaler store with the username and password stored as PAM secrets would contain (where the Provider value—1 in this example—is the Id value from GET PAM Providers on page 724):

```
"{
    \"ServerUsername\":{\"value\":{\"Provider\":\"1\",\"Parameters\":
{\"SecretId\":\"User_Name\"}}},
    \"ServerPassword\":{\"value\":{\"Provider\":\"1\",\"Parameters\":
{\"SecretId\":\"Password\"}}},
    \"ServerUseSs1\":{\"value\":\"true\"}
}"
```

Name	Description
	Note: There are three standard properties that are used for any built-in certificate store types that require server credentials (e.g. F5):  ServerUsername ServerPassword ServerUseSsI  These replace the separate certificate store server records that existed in previous versions of Keyfactor Command. For legacy support, if credentials are not provided through store properties during creation or editing of a certificate store, Keyfactor Command will attempt to find a certificate store server record and copy the credentials from it into the store properties for future use.  Tip: Built-in stores that make use of this field include: AWS stores use this field to store secured versions of the access key and secret. F5 REST stores (all types) use this field to store secured versions of the server authentication information (ServerUsername, ServerPassword, ServerUseSsI) and primary node information (PrimaryNode, PrimaryNodeCheckRetryWaitSecs, PrimaryNodeCheckRetryMax) and F5 version (F5Version). F5 SOAP stores (all types) use this field to store secured versions of the server authentication information (ServerUsername, ServerPassword, ServerUseSsI). FTP stores use this field to store secured versions of the server authentication information (ServerUsername, ServerPassword, ServerUseSsI).  IIS stores (all types) use this field to store the UseSSL flag and the port for WinRM communications. Java keystores use this field to store type (ProviderType). NetScaler stores use this field to store secured versions of the server authentication information (ServerUsername, ServerPassword, ServerUseSsI).
AgentId	A string indicating the Keyfactor Command GUID of the orchestrator for this store.
AgentAssigned	A Boolean that indicates whether there is an orchestrator assigned to this certificate store (true) or not (false).
ContainerName	A string indicating the name of the certificate store's associated container, if applicable.
InventorySchedule	The inventory schedule for this certificate store. The following schedule types are supported:

Name	Description					
	Name	Description				
	Off	Turn off a previo	ously configured schedule.			
	Immediate	A Boolean that i (false).	indicates a job scheduled to run immediately (true) or not			
		N/Z	some instances, jobs initially scheduled as <i>Immediate</i> will on a GET as <i>null</i> .			
	Interval	specified param	It indicates a job scheduled to run every x minutes with the leter. Any interval that is selected in the UI will be converted in stored in the database.			
		Name	Description			
		Minutes	An integer indicating the number of minutes between each interval.			
		For example, every hour:				
		"Interval":     "Minutes				
	Daily	A dictionary that indicates a job scheduled to run every day at the same time with the parameter:				
		Name	Description			
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).			
		For example, da	nily at 11:30 pm:			
		"Daily": {     "Time": }	"2022-02-25T23:30:00Z"			

Name	Description				
	Name	Description			
	ExactlyOnce		A dictionary that indicates a job scheduled to run at the time specified with the parameter:		
		Name	Description		
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).		
		For exam	ple, exactly once at 11:45 am:		
			lyOnce": { ne": "2022-02-27T11:45:00Z"		
		N/	ip: In some instances, jobs initially scheduled as <i>Immediate</i> will ppear on a GET as <i>ExactlyOnce</i> .		
	ules, onl	y the schedu	Swagger Example Value may show examples of various other schedules shown here—that are available in the Management Portal for re valid for this endpoint.		
ReenrollmentStatus			her the certificate store can use the re-enrollment function with se re-enrollment job. The following reenrollment fields are		
	Name		Description		
	Data		A Boolean that indicates whether the certificate store can use the re-enrollment function (true) or not (false).		
	AgentId		A string indicating the Keyfactor Command GUID of the orchestrator that can re-enroll the certificate store.		
	Message		A string indicating the reason the certificate store cannot reenroll, if applicable.		
	JobProperties		An array of key/value pairs for the unique parameters defined		

Name	Description	
	Name	Description
		for the certificate store type. The *key* is the name of the specific parameter from the certificate store type definition as returned in the JobProperties on the store type using the *GET CertificateStoreTypes* method and the *value* is the value that should be set for that parameter on a certificate in the certificate store. For example, for NetScaler, the key name that is optionally used to associate a certificate with a virtual server is *NetscalerVserver* and is returned by *GET CertificateStoreTypes* like so:  "JobProperties": ["NetscalerVserver"]  It can be seen in the Keyfactor Command Management Portal when editing the certificate store type in the field for *Management Job Custom Fields*.  The setting is referenced using the following format:  "JobProperties": [
		This field is optional.
	CustomAliasAllowed	An integer indicating the option for a custom alias for this certificate store.  • 0—forbidden  • 1—optional  • 2—required
SetNewPass- wordAllowed	A Boolean that indicates wh	ether the store password can be changed (true) or not (false).
Password	Note: Secret data is responses.	s stored in the secrets table or a PAM provider and is not returned in

# 2.2.9.14 POST Certificate Stores Approve

The POST /CertificateStores/Approve method is used to approve one or more certificate stores currently in the pending state—having been discovered using the certificate store discover option (see <u>PUT Certificate Stores</u>

<u>Discovery Job on page 453</u>). If more than one certificate store is included in the array, all stores must be of the same store type (e.g. Java keystore). This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: CertificateStoreManagement: *Modify* 

Table 210: POST Certificate Stores Approve Input Parameters

Name	In	Description
Id	Bod- y	Required. The GUID of the pending certificate store.  Use the GET /CertificateStores method (see GET Certificate Stores on page 377) with a query of "Approved -eq false" to retrieve a list of all your unapproved certificate stores to determine the GUID of the store.
Contain- erld	Bod- y	An integer that identifies the container in which the certificate store should be placed on approval.  Use the GET /CertificateStores/Containers method (see GET Certificate Store Containers on page 488) to retrieve a list of your defined certificate store containers to determine the container ID to use.
CertStore- Type	Bod- y	<b>Required</b> . An integer indicating the ID of the certificate store type, as defined in Keyfactor Command, for this certificate store. (0-Javakeystore, 2-PEMFile, 3-F5SSLProfiles, 4-IISRoots, 5-NetScaler, 6-IISPersonal, 7-F5WebServer, 8-IISRevoked, 9-F5WebServerREST, 10-F5SSLProfilesREST, 11-F5CABundlesREST, 100-AmazonWebServices, 101-FileTransferProtocol)
Properties	Bod-y	Required*. Some types of certificate stores have additional properties that are stored in this parameter. The data is stored in a series of, typically, key value pairs that define the property name and value (see GET Certificate Store Types on page 518 for more information).  When reading this field, the values are returned as simple key value pairs, with the values being individual values. When writing, the values are specified as objects, though they are typically single values.  For example, on a GET request for a PEM store configured with a separate private key, the contents of this field might be:  "{
Password	Bod- y	Required. An array indicating the source for and details of the credential information Keyfactor Command will use to access the certificates in a specific certificate store (the store password). This is different from credential information Keyfactor Command uses to access a certificate store server as a whole. The former (this setting) is typically used for Java keystores; the latter is typically used for certificates stores on NetScaler and F5 devices and set at the server level, not the certificate store level (see POST Certificate Stores Server on page 441).  Certificate stores that require credentials support up to three possible credential options:

Name	In	Description					
		<ul> <li>Use no store password.         This option is supported for Java keystores that would normally require a passw be configured with the no password option (see <i>Value</i>, below).     </li> <li>Store the credential information in the Keyfactor secrets table.         A Keyfactor secret is a user-defined password that is encrypted and stored secur Keyfactor Command database.     </li> <li>Load the credential information from a PAM provider.         See <u>PAM Providers on page 709</u> and the <u>Privileged Access Management (PAM) secure Command Reference Guide for more information.     </u></li> </ul>					
		Name	Description				
		Value	A string—submitted as an object—indicating a password to be stored as a Keyfactor secret.  Tip: To set the no password option on a store, submit the password with a null value. For example:  "Password": {  "Value": {null}  }  To set the value to a string to be stored in the Keyfactor secrets table, include the password in quotes. For example:  "Password": {  "Value": "MyVerySecurePassword"  }				
		SecretTypeGuid	A string indicating the Keyfactor Command reference GUID for the type of credentials. This value is automatically set by Keyfactor Command.				
		InstanceId	The Keyfactor Command reference ID for the secret provider. If you are using a secret provider with an integer ID, this will be used. This value is automatically set by Keyfactor Command.				
		InstanceGuid	The Keyfactor Command reference GUID for the secret provider. If you are using a secret provider with a GUID ID, this will be used. This value is automatically set by Keyfactor Command.				
		Provider- TypePara- meterValues	An array containing the values for the provider types specified by ProviderTypeParams. PAM provider type parameter values include:				

Name	In	Description				
		Name	Description			
			Name	Description		
			Id	The Keyfactor C	ommand reference ID for the PAM arameter.	
		Value	CyberArk folder	or the parameter (e.g. the name of the where the protected object that name or password resides).		
			Instancel- d		ommand reference ID for the PAM are attaching to something with an will be used.	
			Instance- Guid		ommand reference GUID for the PAM are attaching to something with a II be used.	
			Provider	An array containing information about the provider.  PAM provider details include:		
				Name	Description	
				Id	An integer indicating the Keyfactor Command reference ID for the PAM provider.	
				Name	A string indicating the internal name for the PAM provider.	
				Area	An integer indicating the area of Keyfactor Command the provider is used for. PAM providers generally have a value of 1, indicating they are used for certificate stores.	
				Provider- Type	An array containing details about the provider type for the provider, including:	

Name	In	Description				
		Name	Description	1		
			Name	Description		
				Name	Description	n
					Name	Description
					Id	A string indicating the Keyfactor Command reference GUID for the provider type.
					Name	A string that indicates the name of the provider type.
					Provide- r Type Params	An array of parameters that the provider type uses for data input in Keyfactor Command when creating new PAM provider and certificate store records.  See below instance of Provider-TypeParam for details.
				Provider- Type	An array cor	ntaining the values

Name In	Description			
	Name	Description		
		Name	Description	
			Name	Description
			Para- mValues	for the provider types specified by ProviderTypeParams. See the previous level of <i>Provider-TypeParamValues</i> for details.
			SecuredAreald	An integer indicating the Keyfactor Command reference ID for the certificate store container the PAM provider is associated with, if any. You can create a single PAM provider for each provider type (e.g. CyberArk), however, if you have opted to organize your certi- ficate stores into containers, you will need to create multiple providers to match your container organization structure. The container field in the PAM provider definition is not required, but if one is supplied when creating a PAM provider, the PAM provider can only be used with certificate stores in the matching container. Likewise, a PAM provider defined with no container would be available for selection when setting pass- words for any certificate store that also did not specify a container. A PAM provider configured in this way could be used across a variety of certi- ficate stores (e.g. both JKS and

Name	In	Description			
		Name	Description		
			Name	Description	
				Name	Description
					F5) as long as they were not in containers.
			Provider- Type Param	for data input new PAM prov	rameters that the provider type uses in Keyfactor Command when creating vider and certificate store records. type parameters include:
				Name	Description
				Id	An integer indicating the Keyfactor Command reference ID for the PAM provider type parameter.
				Name	A string indicating the internal name for the PAM provider type parameter.
				DisplayNa- me	A string indicating the display name for the PAM provider type parameter. For parameters with an InstanceLevel of <i>false</i> , this name appears on the PAM provider dialog for the parameter when a user creates a new PAM provider. For parameters with an InstanceLevel of <i>true</i> , this name appears on the Server dialog for the parameter when a user creates a new PAM provider.
				DataType	An integer indicating the data type for the parameter. Possible values are:

Name	In	Description				
		Name	Description  Name Description			
			Nume	Name	Description	
					<ul><li>1 = String</li><li>2 = Secret</li></ul>	
				InstanceL- evel	parameter is us	figuring a certi- ise the PAM , see <u>GET PAM</u>
				Provider- Type	An array contain provider type.	ning details for the
					Name	Descrip- tion
					Id	A string indicating the Keyfactor Command reference GUID for the PAM provider type parameter.
					Name	A string

Name	In	Description					
		Name	Description				
			Name	Description	Description		
				Name			
					Name	Descrip- tion	
						indicating the internal name for the PAM provider type para- meter.	
					Provider- TypeParams	Unused field	
		Provider	An integer ind	licating the Keyfa	ctor Command refer	ence ID for the PAM	
IsManaged  A Boolean indicating whether the creden by a PAM provider (true) or stored in the This value is automatically set by Keyfact			red in the Keyfactor	secrets table (false).			
		This field is <b>required</b> for J	Java keystores.				

## 2.2.9.15 POST Certificate Stores Schedule

The POST /CertificateStores/Schedule method is used to create and assign a schedule to one or more certificate stores in Keyfactor Command. The POST request must contain an array of certificate store GUIDs and the properties that make up the schedule to attach to the store(s). This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: CertificateStoreManagement: *Schedule* 

Table 211: POST Certificate Stores Schedule Input Parameters

Name	In	Description		
Storelds	Body	<b>Required</b> . An array of strings providing the certificate store GUIDs to schedule.		
Schedule	Body	Required. The inventory schedule for the certificate store(s). Supported schedules are:		
		Name	Description	
		Off	Turn off a previously configured schedule.	
		Immediate	A Boolean that indicates a job scheduled to run immediately (true) or not (false).	
			Tip: In some instances, jobs initially scheduled as <i>Immediate</i> will appear on a GET as <i>null</i> .	
		Interval	A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database.	
			Name Description	
			Minutes An integer indicating the number of minutes between each interval.	
			For example, every hour:	
			"Interval": {     "Minutes": 60 }	
		Daily	A dictionary that indicates a job scheduled to run every day at the same time with the parameter:	
			Name Description	
			Time  The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
			For example, daily at 11:30 pm:	

Name	In	Description			
		Name	Description		
			"Daily": {     "Time": "2022-02-25T23:30:00Z" }		
	ExactlyOnce A dictionary that indicates a job scheduled to run at the t the parameter:				
			Name Description		
			Time  The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).		
			For example, exactly once at 11:45 am:		
"ExactlyOnce": {     "Time": "2022-02-27T11:45:00Z" }		"Time": "2022-02-27T11:45:00Z"			
			Tip: In some instances, jobs initially scheduled as <i>Immediate</i> will appear on a GET as <i>ExactlyOnce</i> .		
		ules, only	te: Although the Swagger Example Value may show examples of various other scheons, only the schedules shown here—that are available in the Management Portal for succionality—are valid for this endpoint.		

## 2.2.9.16 POST Certificate Stores Reenrollment

The POST /CertificateStores/Reenrollment method is used to schedule an existing certificate store for reenrollment. The reenrollment method is available for:

- PEM certificate stores managed by the Native Agent.
- PEM and Java certificate stores managed by Java and Android Agents.
- Any custom certificate store types created to support this functionality.

This endpoint returns 204 with no content upon success. Use the GET /OrchestratorJobs/JobHistory method to check on the progress of the job after submission (see GET Orchestrator Jobs Job History on page 687).



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature:

CertificateEnrollment: EnrollCSR
CertificateStoreManagement: Modify

Permissions for certificate stores can be set at either the global or certificate store container level. See *Container Permissions* in the *Keyfactor Command Reference Guide* for more information about global vs container permissions.

In addition, the either the user scheduling the reenrollment job or the user configured to provide authentication to the CA (see <u>Authorization Methods Tab</u> in the *Keyfactor Command Reference Guide*) must have enrollment permissions configured on the CA and template.

Table 212: POST Certificates Stores Reenrollment Input Parameters

Name	In	Description	
KeystoreId	Body	<b>Required</b> . The GUID of the certificate store to schedule for reenrollment. Use the $GET$ /CertificateStores method (see $GET$ Certificate Stores on page 377) to retrieve a list of your certificate stores to determine the GUID of the store.	
SubjectName	Body	Required. A string containing the reenrollment subject name using X.500 format. For example:  "SubjectName": "CN=websrvr14.keyexample.com,OU=IT,O=\"Key Example, Inc.\",L=Independence,ST=OH,C=US"	
AgentGuid	Body	Required. The GUID of the orchestrator that is registered with the certificate store.  Use the GET /CertificateStores method (see GET Certificate Stores on page 377) to retrieve a list of your certificate stores to determine the GUID of the orchestrator associated with the store.	
Alias	Body	Required. The alias of the certificate in the certificate store.	
JobProperties	Body	An array of key/value pairs for the unique parameters defined for the certificate store type. The key is the name of the specific parameter from the certificate store type definition as returned in the JobProperties on the store type using the GET CertificateStoreTypes method and the value is the value that should be set for that parameter on a certificate in the certificate store. For example, for NetScaler, the key name that is optionally used to associate a certificate with a virtual server is NetscalerVserver and is returned by GET CertificateStoreTypes like so:  "JobProperties": [ "NetscalerVserver" ]  It can be seen in the Keyfactor Command Management Portal when editing the certificate store type in the field for Management Job Custom Fields.  The setting is referenced using the following format:  "JobProperties": [ {"NetscalerVserver":"MyVirtualServerName"} ]  Note: The only built-in certificate store type that makes use of job properties that can be set on a certificate-by-certificate basis in the store is NetScaler, which does not support reenrollment. You may have custom certificate store types that make use of this functionality.	
CertificateAuthority	Body	A string indicating the certificate authority to which to direct the enrollment request. If this parameter is not provided, the value set in the <i>Certificate Authority For Submitted CSRs</i> application setting will be used (see <a href="#">Application Settings: Agents Tab</a> in the <i>Keyfactor Command Reference Guide</i> ).	
CertificateTemplate	Body	A string indicating the certificate template to use for the enrollment request. If this parameter is not provided, the value set in the <i>Template For Submitted CSRs</i>	

Name	In	Description
		application setting will be used (see <u>Application Settings: Agents Tab</u> in the Keyfactor Command Reference Guide).

### 2.2.9.17 POST Certificate Stores Certificates Add

The POST /CertificateStores/Certificates/Add method is used to add a certificate to one or more certificate stores. The POST request must contain a certificate ID and an array of certificate store GUIDs that identify the stores to which the certificate should be added. This method returns HTTP 200 OK on a success with an array of GUIDs for the add jobs. Use the GET /OrchestratorJobs/JobHistory method to check on the progress of the job after submission (see GET Orchestrator Jobs Job History on page 687).



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature:

Certificates: Read

CertificateStoreManagement: Schedule

Permissions for certificates and certificate stores can be set at either the global or certificate collection and certificate store container level. See *Certificate Permissions* and *Container Permissions* in the *Keyfactor Command Reference Guide* for more information about global vs collection and container permissions.

Table 213: POST Certificate Stores Certificates Add Input Parameters

Name	In	Description							
CertificateId	Body	<b>Required</b> . An integer containing the Keyfactor Command reference ID of the certificate to be added to the certificate store(s).							
CertificateStores	Body	<b>Required</b> . An array of certificate store GUIDs to identify the certificate stores to which the certificate should be added and provide appropriate reference information for the certificate in the store. Parameters include:							
		Name	Description						
		CertificateStoreIds	<b>Required</b> . A string containing the GUID for the certificate store to which the certificate should be added.						
		Alias	Required*. A string providing an alias to be used for the certificate upon entry into the certificate store. The function of the alias varies depending on the certificate store type. For example, for an F5 device, it serves as the file name used to store the file in the device file system, minus the extension (e.g. use alias MyFile for a file named MyFile.pfx) while for a Java keystore, it is stored in the keystore associated with the certificate. Some certificate store types don't require an alias and some do. See the Add Certificate section of the Keyfactor Command Reference Guide for more information. This field may be required depending on the store type selected.						
			JobFields	An array of key/value pairs that sets extra values for the job fields that will be associated with the add job. This option is typically used with custom Any Agent implementations.					
									Overwrite
		EntryPassword	The password to set on the entry within the certificate store, if applicable. Only select certificate stores support entry passwords (e.g. Java keystores). Entry password						

Name	In	Description				
		Name	Description	Description  values include:		
			values include:			
			Name	Description		
			SecretValue	A string containing the password. This value only needs to be supplied if you're storing your password in the Keyfactor Command database.		
			Provider	An integer that identifies the PAM provider used to store the password. Use the GET /PamProviders method (see GET PAM Providers on page 724) to retrieve a list of your defined PAM providers to determine the PAM provider ID to use.		
			Parameters	The parameters required by your PAM provider, containing the information that identifies the location of the password in the PAM solution. Use the GET /PamProviders method (see GET PAM Providers on page 724) to retrieve a list of the parameters used by your PAM provider. Only parameters where InstanceLevel is equal to true need to be supplied in the request.  For example, for Delinea (formerly Thycotic), this might be:  "EntryPassword": {  "Provider": 2,  "Parameters": {  "SecretId": 5		

Name	In	Description			
		Name	Description		
			Name	Description	
				<pre>}, For CyberArk, this might be:  "EntryPassword": {     "Provider": 5,     "Parameters": {         "Folder":     "Root",         "Object":     "F5Password"     } },</pre>	
	PfxPassword	ficate with its priva	ne password to use when saving a certi- te key in the certificate store. This is re's a private key being added along		
		IncludePrivateKey	the certificate in the	whether to include the private key of e certificate store if private keys are en certificate store (true) or not is false.	
		For example, to add to on writing an existing certific		nd one NetScaler store without over-	
		"CertificateS  "IncludePriva }, {  "Alias": "C21	ertificate.pfx", toreId": "fde12aa7 teKey": true 07973A928859C21330 toreId": "322e12ea	-6643-43db-88e8-5c91c5ce78b3", E566B299CD4A0705AE8", -43b2-4aab-80ae-c4ad4569b4e7",	
Schedule	Body	Required. The inventory s	chedule for the add jo	bb. Possible schedule values include:	

Name	In	Description				
		Name	Description			
		Off	Turn off a previ	ously configured schedule.		
		Immediate	A Boolean that (true) or not (fa	indicates a job scheduled to run immediately alse).		
				some instances, jobs initially scheduled as iate will appear on a GET as null.		
		ExactlyOnce	A dictionary that specified with t	at indicates a job scheduled to run at the time he parameter:		
			Name	Description		
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).		
			<pre>For example, exactly once at 11:45 am: "ExactlyOnce": {     "Time": "2022-02-27T11:45:00Z" }</pre>			
			N/	some instances, jobs initially scheduled as iate will appear on a GET as ExactlyOnce.		
		other schedu	ules, only the sche	Example Value may show examples of various edules shown here—that are available in the unctionality—are valid for this endpoint.		
CollectionId	Body	user executing the re ID is not supplied, th Supplying a certificat tion-level permission	equest has sufficience user must have the collection ID all the stocker with the action making to determine with the action in t	ficate collection identifier to validate that the ent permissions to do so. If a certificate collection global permissions to complete the action. ows for a check of the user's certificate collechether the user has sufficient permissions at a base. See Certificate Permissions in the Keyfactor information.		

#### 2.2.9.18 POST Certificate Stores Certificates Remove

The POST /CertificateStores/Certificates/Remove method is used to remove a certificate from one or more certificate stores. The POST request must contain an array of certificate store GUIDs and the certificate properties that identify the certificate to remove. This method returns HTTP 200 OK on a success with an array of GUIDs for the removal jobs. Use the GET /OrchestratorJobs/JobHistory method to check on the progress of the job after submission (see GET Orchestrator Jobs Job History on page 687).



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature:

Certificates: Read

CertificateStoreManagement: Schedule

Permissions for certificates and certificate stores can be set at either the global or certificate collection and certificate store container level. See *Certificate Permissions* and *Container Permissions* in the *Keyfactor Command Reference Guide* for more information about global vs collection and container permissions.

Table 214: POST Certificate Stores Certificates Remove Input Parameters

Name	In	Description				
CertificateStores	es Body	<b>Required</b> . An array of certificate store GUIDs and related information to identify the certificate to remove from the certificate store(s). Certificate store detail includes:				
		Name	Description			
		Alias	Required. A string containing the unique identifier for the certificate in the certificate store. Each type of certificate store has a different format for this alias. Use the GET /Certificates/{id} method (see GET Certificates ID on page 221) to retrieve the certificate store IDs in which the certificate is stored (CertStoreId) and the aliases under which the certificate is stored in these stores. This information is also available in the certificate details in the Management Portal.			
		CertificateStoreIds	<b>Required.</b> A string containing the GUID for the certificate store from which the certificate should be removed.			
				JobFields	An array of key/value pairs that sets extra values for the job fields that will be associated with the removal job. This option is typically used with custom Any Agent implementations.	
					For example, to remo	ve from one IIS personal store and one NetScaler store:
						"Certifica }, { "Alias": "
Schedule	Body	Required. The inventory schedule for the removal job. Supported schedules are:				
		Name	Description			
		Off	Turn off a previously configured schedule.			

Name	In	Description		
		Name	Description	
		Immediate	A Boolean that (true) or not (fa	indicates a job scheduled to run immediately alse).
			N/	some instances, jobs initially scheduled as liate will appear on a GET as null.
		ExactlyOnce		at indicates a job scheduled to run at the with the parameter:
			Name	Description
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
			For example, e	xactly once at 11:45 am:
			"ExactlyOn     "Time": }	ce": {    "2022-02-27T11:45:00Z"
			N/	some instances, jobs initially scheduled as liate will appear on a GET as ExactlyOnce.
		other schedu	ules, only the sch	Example Value may show examples of various edules shown here—that are available in the unctionality—are valid for this endpoint.
CollectionId	Body	user executing the retion ID is not supplie Supplying a certification-level permission	equest has suffici- id, the user must te collection ID al his to determine w implete the action	ificate collection identifier to validate that the ent permissions to do so. If a certificate collechave global permissions to complete the action. lows for a check of the user's certificate collecthether the user has sufficient permissions at a m. See <i>Certificate Permissions</i> in the <i>Keyfactor</i> information.

### 2.2.10 Certificate Store Containers

The CertificateStoreContainers component of the Keyfactor API provides a set of methods to support management of certificate store containers.

Table 215: Certificate Store Containers Endpoints

Endpoint	Method	Description	Link
/	GET	Returns a list of certificate store containers.	GET Certificate Store Containers below
/	POST	Adds a certificate store container.	POST Certificate Store Containers on page 491
/{id}	DELETE	Deletes a certificate store container.	DELETE Certificate Store Containers  ID on page 499
/{id}	GET	Returns details for the specified certificate store container.	GET Certificate Store Containers ID on page 499
/{id}	PUT	Edits a certificate store container.	PUT Certificate Store Containers on page 495

### 2.2.10.1 GET Certificate Store Containers

The GET /CertificateStoreContainers method is used to retrieve all certificate store containers. This method returns HTTP 200 OK on a success with container details.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: CertificateStoreManagement: *Read* 

Permissions for certificate stores can be set at either the global or certificate store container level. See *Container Permissions* in the *Keyfactor Command Reference Guide* for more information about global vs container permissions.

Table 216: GET Certificate Store Containers Input Parameters

Name	In	Description
queryString	Query	A string containing a query to limit the results (e.g. field1 -eq value1 AND field2 -gt value2). The default is to return all records. Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns for the same feature. For querying guidelines, refer to the Keyfactor Command Reference Guide: Using the Containers Search Feature. The query fields supported for this endpoint are:  • CertStoreType (0-Javakeystore,2-PEMFile, 3-F5SSLProfiles,4-IISRoots, 5-NetScaler, 6-IISPersonal, 7-F5WebServer, 8-IISRevoked, 9-F5WebServerREST, 10-F5SSLProfilesREST, 11-F5CABundlesREST, 100-AmazonWebServices, 101-FileTransferProtocol)  • HasSchedule (True, False)  • Id  • Name(Short Name)
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>Name</i> .
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.

Table 217: GET Certificate Stores Containers Response Data

Name	Description		
Id	An integer ind	licating the ID of th	ne container.
Name	A string indica	ting the name of t	the container.
Over- writeSchedules	A Boolean indicating whether the schedule set on the container will overwrite schedules set individually on the certificate stores (true) or not (false).		
Schedule	A string conta	ining the inventor	y schedule set for the container. Supported schedules are:
	Name	Description	
	Off	Turn off a previo	ously configured schedule.
	Interval	specified param	t indicates a job scheduled to run every x minutes with the eter. Any interval that is selected in the UI will be converted to tored in the database.
		Name	Description
		Minutes	An integer indicating the number of minutes between each interval.
		For example, ev	ery hour:
		"Interval": "Minutes }	
	Daily		t indicates a job scheduled to run every day at the same time eter:
		Name	Description
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
		For example, da	ily at 11:30 pm:

Name	Description	Description		
	Name	Description		
		"Daily": {     "Time": "2022-02-25T23:30:00Z" }		
	ules, c	Although the Swagger Example Value may show examples of various other schedonly the schedules shown here—that are available in the Management Portal for this onality—are valid for this endpoint.		
CertStoreType	An integer indicating the ID of the certificate store type, as defined in Keyfactor Command, for this certificate store. (0-Javakeystore,2-PEMFile, 3-F5SSLProfiles,4-IISRoots, 5-NetScaler, 6-IISPersonal, 7-F5WebServer, 8-IISRevoked, 9-F5WebServerREST, 10-F5SSLProfilesREST, 11-F5CABundlesREST, 100-AmazonWebServices, 101-FileTransferProtocol)			
StoreCount	An integer indicating the number of stores of the type referenced by CertStoreType in the container.			

### 2.2.10.2 POST Certificate Store Containers

The POST /CertificateStoreContainers method is used to add a new certificate store container. This method returns HTTP 200 OK on a success with container details.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: CertificateStoreManagement: *Modify* 

Permissions for certificate stores can be set at either the global or certificate store container level. See *Container Permissions* in the *Keyfactor Command Reference Guide* for more information about global vs container permissions.

Table 218: POST Certificate Stores Containers Input Parameters

Name	In	Description		
Name	Body	Required. A s	tring indicating the name	of the container.
Schedule	Body	A string containing the inventory schedule set for the container. Supported schedules are:		dule set for the container. Supported schedules are:
		Name	Description	
		Off	Turn off a previously co	onfigured schedule.
		Interval		tes a job scheduled to run every x minutes with the ny interval that is selected in the UI will be converted d in the database.
			Name Des	cription
				nteger indicating the number of minutes between interval.
			For example, every hou	ır:
			"Interval": {     "Minutes": 60 }	
		Daily	A dictionary that indica with the parameter:	tes a job scheduled to run every day at the same time
			Name Desc	cription
			shou YYYY	date and time to next run the job. The date and time ld be given using the ISO 8601 UTC time format
			For example, daily at 13	1:30 pm:
			"Daily": {     "Time": "2022- }	02-25T23:30:00Z"
				Example Value may show examples of various other shown here—that are available in the Management

Name	In	Description
		Portal for this functionality—are valid for this endpoint.
CertStoreTyp- e	Body	An integer indicating the ID of the certificate store type, as defined in Keyfactor Command, for this certificate store. (0-Javakeystore,2-PEMFile, 3-F5SSLProfiles,4-IISRoots, 5-NetScaler, 6-IISPersonal, 7-F5WebServer, 8-IISRevoked, 9-F5WebServerREST, 10-F5SSLProfilesREST, 11-F5CABundlesREST, 100-AmazonWebServices, 101-FileTransferProtocol) The default is 0 for a JKS keystore.

Table 219: POST Certificate Stores Containers Response Data

Name	Description			
Id	An integer ind	An integer indicating the ID of the container.		
Name	A string indicating the name of the container.			
Schedule	A string containing the inventory schedule set for the container. Supported schedules are:			
	Name	Description		
	Off	Turn off a previo	ously configured schedule.	
	Interval		t indicates a job scheduled to run every x minutes with the specified interval that is selected in the UI will be converted to minutes when tabase.	
		Name	Description	
		Minutes	An integer indicating the number of minutes between each interval.	
		For example, every hour:		
		"Interval": "Minutes }		
	Daily	A dictionary that the parameter:	t indicates a job scheduled to run every day at the same time with	
		Name	Description	
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
		For example, da	ily at 11:30 pm:	
		"Daily": {     "Time": }	"2022-02-25T23:30:00Z"	

Name	Description
	Note: Although the Swagger <i>Example Value</i> may show examples of various other schedules, only the schedules shown here—that are available in the Management Portal for this functionality—are valid for this endpoint.
CertStoreType	An integer indicating the ID of the certificate store type, as defined in Keyfactor Command, for this certificate store. (0-Javakeystore,2-PEMFile, 3-F5SSLProfiles,4-IISRoots, 5-NetScaler, 6-IISPersonal, 7-F5WebServer, 8-IISRevoked, 9-F5WebServerREST, 10-F5SSLProfilesREST, 11-F5CABundlesREST, 100-AmazonWebServices, 101-FileTransferProtocol)

### 2.2.10.3 PUT Certificate Store Containers

The PUT /CertificateStoreContainers method is used to edit the specified certificate store container. This method returns HTTP 200 OK on a success with container details.



**Tip:** The following permissions (see Security Overview) are required to use this feature: CertificateStoreManagement: Modify

Permissions for certificate stores can be set at either the global or certificate store container level. See Container Permissions in the Keyfactor Command Reference Guide for more information about global vs container permissions.



Warning: Any previously populated fields that are not submitted with their full existing data using this method will be cleared of their existing data. When using this method, you should first do a GET to retrieve all the values for the record you want to update, enter corrected data into the field(s) you want to update, and then submit all the fields using PUT, including the fields that contain values but which you are not changing.

Table 220: PUT Certificate Store Containers Input Parameters

Name	In	Description			
Id	Path	Required. An integer indicating the ID of the container.			
Name	Body	Required. A s	string indicating the name of the container.		
Schedule	Body	A string containing the inventory schedule set for the container. Supported schedules are:			
		Name	Description		
		Off	Turn off a previously configured schedule.		
		Interval	A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database.		
			Name Description		
			Minutes An integer indicating the number of minutes between each interval.		
			For example, every hour:		
			"Interval": {     "Minutes": 60 }		
		Daily	A dictionary that indicates a job scheduled to run every day at the same time with the parameter:		
			Name Description		
			Time  The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).		
			For example, daily at 11:30 pm:		
			"Daily": {     "Time": "2022-02-25T23:30:00Z" }		

Name	In	Description
		Note: Although the Swagger Example Value may show examples of various other schedules, only the schedules shown here—that are available in the Management Portal for this functionality—are valid for this endpoint.
CertStoreTyp- e	Body	An integer indicating the ID of the certificate store type, as defined in Keyfactor Command, for this certificate store. (0-Javakeystore,2-PEMFile, 3-F5SSLProfiles,4-IISRoots, 5-NetScaler, 6-IISPersonal, 7-F5WebServer, 8-IISRevoked, 9-F5WebServerREST, 10-F5SSLProfilesREST, 11-F5CABundlesREST, 100-AmazonWebServices, 101-FileTransferProtocol) The default is 0 for a JKS keystore.

Table 221: PUT Certificate Store Containers Response Data

Name	Description			
Id	An integer indicating the ID of the container.			
Name	A string indica	ting the name of th	ne container.	
Schedule	A string containing the inventory schedule set for the container. Supported schedules are:			
	Name	Description		
	Off	Turn off a previously configured schedule.		
	Interval	A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database.		
		Name	Description	
		Minutes	An integer indicating the number of minutes between each interval.	
		For example, every hour:		
		"Interval": {     "Minutes": 60 }		
	Daily	A dictionary that the parameter:	t indicates a job scheduled to run every day at the same time with	
		Name	Description	
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
		For example, daily at 11:30 pm:		
		"Daily": {     "Time": }	"2022-02-25T23:30:00Z"	

Name	Description
	Note: Although the Swagger <i>Example Value</i> may show examples of various other schedules, only the schedules shown here—that are available in the Management Portal for this functionality—are valid for this endpoint.
CertStoreType	An integer indicating the ID of the certificate store type, as defined in Keyfactor Command, for this certificate store. (0-Javakeystore,2-PEMFile, 3-F5SSLProfiles,4-IISRoots, 5-NetScaler, 6-IISPersonal, 7-F5WebServer, 8-IISRevoked, 9-F5WebServerREST, 10-F5SSLProfilesREST, 11-F5CABundlesREST, 100-AmazonWebServices, 101-FileTransferProtocol)

#### 2.2.10.4 DELETE Certificate Store Containers ID

The DELETE /CertificateStoreContainers/{id} method is used to delete the certificate store container with the specified ID. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: CertificateStoreManagement: *Modify* 

Permissions for certificate stores can be set at either the global or certificate store container level. See *Container Permissions* in the *Keyfactor Command Reference Guide* for more information about global vs container permissions.

Table 222: DELETE Certificate Store Containers {id} Input Parameters

Name	In	Description
id	Path	Required. A string containing the ID of the certificate store container to delete.  Use the GET /CertificateStoreContainers method (see GET Certificate Store Containers on page 488) to retrieve a list of all the certificate store containers to determine the certificate store container ID.

### 2.2.10.5 GET Certificate Store Containers ID

The GET /CertificateStoreContainers/{id} method is used to retrieve the certificate store container with the specified ID. This method returns HTTP 200 OK on a success with container details.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: CertificateStoreManagement: *Read* 

Permissions for certificate stores can be set at either the global or certificate store container level. See *Container Permissions* in the *Keyfactor Command Reference Guide* for more information about global vs container permissions.

Table 223: GET Certificate Store Containers {id} Input Parameters

Name	In	Description
id	Path	Required. A string containing the ID of the certificate store container.  Use the GET /CertificateStoreContainers method (see GET Certificate Store Containers on page 488) to retrieve a list of all the certificate store containers to determine the certificate store container ID.

Table 224: GET Certificate Stores Containers {id} Response Data

Name	Description			
Id	An integer indicating the ID of the container.			
Name	A string indica	ating the name of t	he container.	
Schedule	A string conta	ining the inventory	schedule set for the container. Supported schedules are:	
	Name	Description		
	Off	Turn off a previously configured schedule.		
	Interval	A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database.		
		Name	Description	
		Minutes	An integer indicating the number of minutes between each interval.	
		For example, every hour:		
		"Interval": "Minutes }		
	Daily	A dictionary that the parameter:	t indicates a job scheduled to run every day at the same time with	
		Name	Description	
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
		For example, daily at 11:30 pm:		
		"Daily": {     "Time": "2022-02-25T23:30:00Z" }		

Name	Description		
	Note: Although the Swagger Example Value may show examples of various other schedules, only the schedules shown here—that are available in the Management Portal for this functionality—are valid for this endpoint.		
CertStoreType	An integer indicating the ID of the certificate store type, as defined in Keyfactor Command, for this certificate store. (0-Javakeystore,2-PEMFile, 3-F5SSLProfiles,4-IISRoots, 5-NetScaler, 6-IISPersonal, 7-F5WebServer, 8-IISRevoked, 9-F5WebServerREST, 10-F5SSLProfilesREST, 11-F5CABundlesREST, 100-AmazonWebServices, 101-FileTransferProtocol)		
CertificateStores	An array of certificate store data f	for the certificate stores within this container. Certificate store	
	Name	Description	
	Id	A string indicating the GUID of the certificate store within Keyfactor Command.	
	DisplayName	A string indicating the display name of the certificate store.	
	ContainerId	An integer indicating the ID of the certificate store's associated certificate store container.	
	ClientMachine	The string value of the client machine. The value for this will vary depending on the certificate store type. For example, for a Java keystore or an F5 device, it is the hostname of the machine on which the store is located, but for an Amazon Web Services store, it is the FQDN of the Keyfactor Command Windows Orchestrator. See Certificate Store Operations: Adding or Modifying a Certificate Store in the Keyfactor Command Reference Guide for more information.	
	Storepath	A string indicating the path to the certificate store on the target. The format for this path will vary depending on the certificate store type. For example, for a Java keystore, this will be a file path (e.g. /opt/myapp/store.jks), but for an F5 device, this will be a partition name on the device (e.g. Common). See Certificate Store Operations: Adding or Modifying a Certificate Store in the Keyfactor Command Reference Guide for more information.	
	CertStoreInventoryJobId	A string indicating the GUID that identifies the inventory job for the certificate store in the Keyfactor Command database. This will be null if an inventory schedule is not set for the certificate	

Name	Description		
	Name	Description	
		store.	
	CertStoreType	An integer indicating the ID of the certificate store type, as defined in Keyfactor Command, for this certificate store. (0-Javakeystore,2-PEMFile, 3-F5SSLProfiles,4-IISRoots, 5-NetScaler, 6-IISPersonal, 7-F5WebServer, 8-IISRevoked, 9-F5WebServerREST, 10-F5SSLProfilesREST, 11-F5CABundlesREST, 100-AmazonWebServices, 101-FileTransferProtocol)	
	Approved	A Boolean that indicates whether a certificate store is approved (true) or not (false). If a certificate store is approved, it can be used and updated. A certificate store that has been discovered using the discover feature but not yet marked as approved will be false here.	
	CreatelfMissing	A Boolean that indicates whether a new certificate store should be created with the information provided (true) or not (false). This option is only valid for Java keystores and any custom certi- ficate store types you have defined to support this functionality.	
	Properties	Some types of certificate stores have additional properties that are stored in this parameter. The data is stored in a series of, typically, key value pairs that define the property name and value (see <u>GET Certificate Store Types on page 518</u> for more information).  When reading this field, the values are returned as simple key value pairs, with the values being individual values. When writing, the values are specified as objects, though they are typically single values.	
		For example, on a GET request for a <i>PEM</i> store configured with a separate private key, the contents of this field might be:	
		<pre>"{    \"privateKeyPath\":\"/opt/app/mystore.key\",    \"separatePrivateKey\":\"true\" }"</pre>	
		However, the syntax used when updating the properties sets the value as a key value pair using <i>value</i> as the key. For example, on a POST or PUT request for a <i>PEM</i> store configured with a separate private key, the contents of this field might be:	

Name	Description		
	Name	Description	
		<pre>"{    \"privateKeyPath\":{\"value\":\"/- opt/app/mystore.key\"},    \"separatePrivateKey\":{\"value\":\"true\"} }"</pre>	
		<ul> <li>Tip: Built-in stores that make use of this field include:         <ul> <li>AWS stores use this field to store secured versions of the access key and secret.</li> <li>F5 REST stores (all types) use this field to store the primary node information (PrimaryNode, PrimaryNodeCheckRetryWaitSecs, PrimaryNodeCheckRetryMax) and F5 version (F5Version).</li> <li>IIS stores (all types) use this field to store the port for WinRM communications.</li> <li>PEM stores use this field to store the path to the private key file, if defined, and the Boolean value indicating whether a separate private key path is defined.</li> </ul> </li> </ul>	
	AgentId	A string indicating the Keyfactor Command GUID of the orchestrator for this store.	
	AgentAssigned	A Boolean that indicates whether there is an orchestrator assigned to this certificate store (true) or not (false).	
	ContainerName	A string indicating the name of the certificate store's associated container.	
	InventorySchedule	The inventory schedule for this certificate store.	
	ReenrollmentStatus	An array that indicates whether the certificate store can use the re-enrollment function with accompanying data about the re-enrollment job.	
	SetNewPasswordAllowed	A Boolean that indicates whether the store password can be changed (true) or not (false).	
	Password	An array indicating the source for and details of the credential	

Name	Description		
	Name	Description	
		information Keyfactor Command will use to access the certificates in a specific certificate store (the store password).	
		Note: Secret data is stored in the secrets table or a PAM provider and is not returned in responses.	

# 2.2.11 Certificate Store Types

CertificateStoreTypes define constraints and properties of different kinds of certificates stores. Keyfactor Command contains default certificate store types and also allows users to define certificate store types for custom certificate stores.

Table 225: Certificate Store Type Endpoints

Endpoint	Method	Description	Link
/{id}	DELETE	Deletes a certificate store type using StoreType number.	DELETE Certificate Store Types ID below
/{id}	GET	Returns certificate store type details for the specified certificate store type using StoreType number.	GET Certificate Store Types  ID on the next page
/Name/{name}	GET	Returns certificate store type details for the specified certificate store type using ShortName.	GET CertificateStoreTypes Name Name on page 511
/	DELETE	Delete multiple certificate store types using StoreType number.	DELETE Certificate Store Types on page 517
/	GET	Returns all certificate store types with paging and options to the specified detail level.	GET Certificate Store Types on page 518
1	POST	Creates a new certificate store type.	POST Certificate Store Types on page 523
1	PUT	Updates a certificate store type using StoreType number.	PUT Certificate Store Types on page 535

## 2.2.11.1 DELETE Certificate Store Types ID

The DELETE /CertificateStoreTypes/{id} method is used to delete an existing certificate store type with the specified ID. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: CertificateStoreManagement: *Modify* 

Table 226: DELETE Certificate Store Types {id} Input Parameters

Name	In	Description
id	Path	Required. The ID of the certificate store type to delete.
		Use the <i>GET /CertificateStoreTypes</i> method (see <u>GET Certificate Store Types on page 518</u> ) to retrieve a list of all the certificate store types to determine the certificate store type ID.

### 2.2.11.2 GET Certificate Store Types ID

The GET /CertificateStoreTypes/{id} method is used to return the certificate store type with the specified ID. This method returns HTTP 200 OK on a success with details for the certificate store type specified.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: CertificateStoreManagement: *Read* 

Table 227: GET Certificate Store Types {id} Input Parameters

Name	In	Description
id	Path	Required. The ID of the certificate store type.  Use the GET /CertificateStoreTypes method (see GET Certificate Store Types on page 518) to retrieve a list of all the certificate store types to determine the certificate store type ID.

Table 228: GET Certificate Store Types {id} Response Data

Name	Description		
Name	A string containing the full name of the certificate store type.		
ShortName	A string containing th	e short name assigned to the certificate store type.	
Capability	A string containing a store).	reference name for the certificate store type (e.g. NS for a NetScaler	
StoreType	A unique integer for to Command.	the certificate store type. The ID is automatically assigned by Keyfactor	
ImportType	An integer that indicates the import type for the certificate store type. The ID is automatically assigned by Keyfactor Command and generally matches the <i>StoreType</i> for custom certificate store types.		
LocalStore	A Boolean that indicates whether the store is local to the orchestrator machine (true) as, for example, JKS and PEM stores managed by the Keyfactor Java Agent or remote (false) as, for example, IIS stores managed by the Keyfactor Universal Orchestrator.		
SupportedOperations	An array containing a series of Boolean values that indicate whether the certificate store type is enabled for the following functions:  • Add • Create • Discovery • Enrollment • Remove		
Properties	An array of unique parameters for the certificate store type. In the Keyfactor Command Management Portal these are known as <i>Custom Fields</i> . Property parameters include:		
	Name	Description	
	Name	A string containing the short name of the property.	
	DisplayName	A string containing the full display name of the property.	
	Туре	A string containing the type of the property:  • String  • Bool  • MultipleChoice	

Name	Description		
	Name	Description	
		• Secret	
	DependsOn	A string containing the name of the parameter on which this parameter depends. This only applies if at least two custom parameters have been created for this certificate store type. This option is used to configure one custom parameter to display only if another custom parameter contains a value.	
	DefaultValue	A string containing the default value(s) of the parameter. If <i>Type</i> is <i>Multiple Choice</i> , this field should contain a comma-separated list of multiple choice options for this parameter. If <i>Type</i> is <i>Boolean</i> , this field should contain <i>true</i> or <i>false</i> .	
	Required	A Boolean that indicates whether the parameter is required (true) or not (false).	
	Note: There are three standard properties that are used for any built-in certificate store types that require server credentials (e.g. F5):  • ServerUsername  • ServerPassword  • ServerUseSsl		
	versions of Ke through store Command will	the separate certificate store server records that existed in previous yfactor Command. For legacy support, if credentials are not provided properties during creation or editing of a certificate store, Keyfactor lattempt to find a certificate store server record and copy the credento the store properties for future use.	
PasswordOptions	Options for the passw	ord in the certificate store type. Password options include:	
	Name	Description	
	EntrySupported	A Boolean that indicates whether entry of a password for the certificate in the certificate store is allowed (true) or not (false).	
	StoreRequired	A Boolean that indicates whether entry of a password on the certificate store as a whole is required (true) or not (false).	
	Style	A string containing the style of password:  • Default: Keyfactor Command will randomly generate a	

Name	Description	
	Name	Description
		password.  • Custom: Allow a password to be entered and authenticated when enrolling for a certificate through Keyfactor Command when installing to a store of this type. The Custom option can be selected only if the Allow Custom Password in the Application Settings, is equal to True. For more details, see Application Settings: Enrollment Tab in the Keyfactor Command Reference Guide.
StorePathValue	An array containing the	value(s) for the certificate store path.
PrivateKeyAllowed	<ul> <li>A string containing the option for private key requirements for certificates stored in stores with this certificate store type:</li> <li>Forbidden: Private key is not required; generally, applies to trust stores (e.g. Root CA certificates).</li> <li>Optional: Private key is optional; applies to store types that could represent either a Trust Store or End-Entity Store.</li> <li>Required: Private key is required; applies to stores that hold an End-Entity Certificate (server or client authorization).</li> </ul>	
ServerRequired	A Boolean that indicates whether server access is required for adding certificate stores for this certificate store type (true) or not (false). If set to true, a user will be prompted for a username and password to connect to the remote server.	
PowerShell	A Boolean that indicates whether jobs for the store type are implemented using PowerShell (true) instead of a .NET class or not (false).	
BlueprintAllowed	A Boolean that indicates whether certificate stores of this type will be included when creating or applying blueprints. For more details, see <i>Orchestrator Blueprints</i> in the <i>Keyfactor Command Reference Guide</i> .	
CustomAliasAllowed	<ul> <li>A string containing the selected certificate store type alias option:</li> <li>Forbidden: A custom alias is not required and cannot be supplied.</li> <li>Optional: A custom alias is optional.</li> <li>Required: A custom alias is required.</li> <li>The certificate store alias serves as an identifier for the certificate in the store. Depending on the type of store, it may be a file name, a certificate thumbprint, a string reference, or some other information. Some types of stores may not support associating an alias with the certificate (e.g. IIS trusted root).</li> </ul>	
EntryParameters	An array of unique parameters that are required when performing management jobs on a	

Name	Description	
	certificate store of this	type. Entry parameter options include:
	Name	Description
	Name	A string containing the short name of the entry parameter.
	DisplayName	A string containing the full display name of the entry parameter.
	Туре	A string containing the type of the entry parameter:  • String  • Bool  • MultipleChoice  • Secret
	RequiredWhen	<ul> <li>An array of Boolean values indicating the circumstances under which a value is required to be provided for this entry parameter. These are: <ul> <li>HasPrivateKey: If set to true, a value must be provided for this field when configuring a management job (either add or remove) if the certificate has an associated private key in Keyfactor Command. This would be the case, for example, when doing a PFX enrollment and adding the resulting certificate to a certificate store.</li> <li>OnAdd: If set to true, a value must be provided for this field when configuring an add certificate job.</li> <li>OnRemove: If set to true, a value must be provided for this field when configuring a remove certificate job.</li> </ul> </li> <li>OnReenrollment: If set to true, a value must be provided for this field when configuring a reenrollment job.</li> </ul>
	DependsOn	A string containing the name of the parameter on which this parameter depends. This only applies if at least two custom parameters have been created for this certificate store type. This option is used to configure one custom parameter to display only if another custom parameter contains a value.
	DefaultValue	A string containing the default value for the entry parameter. If <i>Type</i> is <i>Multiple Choice</i> , this field should contain a single value that represents the default selection from the provided list (see Options) for this entry parameter. If <i>Type</i> is <i>Boolean</i> , this field should contain <i>true</i> or <i>false</i> .
	Options	A string containing a comma-separated list of multiple choice options for this entry parameter.

Name	Description		
	<ul> <li>Tip: What's the difference between properties (custom fields) and entry parameters?</li> <li>Properties are about the certificate store definition itself and are static. For example, you might use a property to define the primary node name of an F5 instance. This node name is the same no matter what inventory or management jobs you do with the F5 device(s). Values for properties are entered in the certificate store record when creating or editing the certificate store record.</li> <li>Entry parameters are about the specific certificate within the certificate store. They are used to send additional information related to the certificate to the server or device that hosts the certificate store when running management jobs for that certificate store. Often this is more fluid information that isn't the same for every use of that certificate store. For example, several virtual servers with separate certificates in the same folder may exist on a NetScaler device. When replacing one certificate, updates may need to be made to only the virtual server that is using the certificate. In this case, the authorized user will be prompted to enter the virtual server name based on an entry parameter. Values for entry parameters are entered at the time a management job is initiated (e.g. adding a certificate to a certificate store).</li> </ul>		
InventoryEndpoint	A string containing the orchestrator endpoint to which inventory updates are sent.		
InventoryJobType	GUID identifying the job type for inventory jobs.		
ManagementJobType	A GUID identifying the job type for management jobs.		
DiscoveryJobType	A GUID identifying the job type for discovery jobs.		
EnrollmentJobType	A GUID identifying the job type for reenrollment jobs.		

# 2.2.11.3 GET CertificateStoreTypes Name Name

The GET /CertificateStoreTypes/Name/{name} method is used to return the certificate store type with the specified short name. This method returns HTTP 200 OK on a success with details for the certificate store type specified.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: CertificateStoreManagement: *Read* 

Table 229: GET Certificate Store Types Name {ShortName} Input Parameters

Name	In	Description
name	Path	Required. The short name of the certificate store type.  Use the GET /CertificateStoreTypes method (see GET Certificate Store Types on page 518) to retrieve a list of all the certificate store types to determine the certificate store type short name.

Table 230: GET Certificate Store Types Name {ShortName} Response Data

Name	Description		
Name	A string containing the full name of the certificate store type.		
ShortName	A string containing th	e short name assigned to the certificate store type.	
Capability	A string containing a store).	reference name for the certificate store type (e.g. NS for a NetScaler	
StoreType	A unique integer for t Command.	the certificate store type. The ID is automatically assigned by Keyfactor	
ImportType	An integer that indicates the import type for the certificate store type. The ID is automatically assigned by Keyfactor Command and generally matches the <i>StoreType</i> for custom certificate store types.		
LocalStore	A Boolean that indicates whether the store is local to the orchestrator machine (true) as, for example, JKS and PEM stores managed by the Keyfactor Java Agent or remote (false) as, for example, IIS stores managed by the Keyfactor Universal Orchestrator.		
SupportedOperations	An array containing a series of Boolean values that indicate whether the certificate store type is enabled for the following functions:  • Add • Create • Discovery • Enrollment • Remove		
Properties	An array of unique parameters for the certificate store type. In the Keyfactor Command Management Portal these are known as <i>Custom Fields</i> . Property parameters include:		
	Name	Description	
	Name	A string containing the short name of the property.	
	DisplayName	A string containing the full display name of the property.	
	Туре	A string containing the type of the property:  • String  • Bool  • MultipleChoice	

Name	Description		
	Name	Description	
		• Secret	
	DependsOn	A string containing the name of the parameter on which this parameter depends. This only applies if at least two custom parameters have been created for this certificate store type. This option is used to configure one custom parameter to display only if another custom parameter contains a value.	
	DefaultValue	A string containing the default value(s) of the parameter. If <i>Type</i> is <i>Multiple Choice</i> , this field should contain a comma-separated list of multiple choice options for this parameter. If <i>Type</i> is <i>Boolean</i> , this field should contain <i>true</i> or <i>false</i> .	
	Required	A Boolean that indicates whether the parameter is required (true) or not (false).	
	Note: There are three standard properties that are used for any built-in certificate store types that require server credentials (e.g. F5):  • ServerUsername  • ServerPassword  • ServerUseSsl		
	versions of Ke through store Command will	the separate certificate store server records that existed in previous yfactor Command. For legacy support, if credentials are not provided properties during creation or editing of a certificate store, Keyfactor lattempt to find a certificate store server record and copy the credento the store properties for future use.	
PasswordOptions	Options for the passw	ord in the certificate store type. Password options include:	
	Name	Description	
	EntrySupported	A Boolean that indicates whether entry of a password for the certificate in the certificate store is allowed (true) or not (false).	
	StoreRequired	A Boolean that indicates whether entry of a password on the certificate store as a whole is required (true) or not (false).	
	Style	A string containing the style of password:  • Default: Keyfactor Command will randomly generate a	

Name	Description	
	Name	Description
		password.  • Custom: Allow a password to be entered and authenticated when enrolling for a certificate through Keyfactor Command when installing to a store of this type. The Custom option can be selected only if the Allow Custom Password in the Application Settings, is equal to True. For more details, see Application Settings: Enrollment Tab in the Keyfactor Command Reference Guide.
StorePathValue	An array containing the	value(s) for the certificate store path.
PrivateKeyAllowed	<ul> <li>A string containing the option for private key requirements for certificates stored in stores with this certificate store type:</li> <li>Forbidden: Private key is not required; generally, applies to trust stores (e.g. Root CA certificates).</li> <li>Optional: Private key is optional; applies to store types that could represent either a Trust Store or End-Entity Store.</li> <li>Required: Private key is required; applies to stores that hold an End-Entity Certificate (server or client authorization).</li> </ul>	
ServerRequired	A Boolean that indicates whether server access is required for adding certificate stores for this certificate store type (true) or not (false). If set to true, a user will be prompted for a username and password to connect to the remote server.	
PowerShell	A Boolean that indicates whether jobs for the store type are implemented using PowerShell (true) instead of a .NET class or not (false).	
BlueprintAllowed	A Boolean that indicates whether certificate stores of this type will be included when creating or applying blueprints. For more details, see <i>Orchestrator Blueprints</i> in the <i>Keyfactor Command Reference Guide</i> .	
CustomAliasAllowed	<ul> <li>A string containing the selected certificate store type alias option:</li> <li>Forbidden: A custom alias is not required and cannot be supplied.</li> <li>Optional: A custom alias is optional.</li> <li>Required: A custom alias is required.</li> <li>The certificate store alias serves as an identifier for the certificate in the store. Depending on the type of store, it may be a file name, a certificate thumbprint, a string reference, or some other information. Some types of stores may not support associating an alias with the certificate (e.g. IIS trusted root).</li> </ul>	
EntryParameters	An array of unique parameters that are required when performing management jobs on a	

Name	Description	
	certificate store of this	type. Entry parameter options include:
	Name	Description
	Name	A string containing the short name of the entry parameter.
	DisplayName	A string containing the full display name of the entry parameter.
	Туре	A string containing the type of the entry parameter:  • String  • Bool  • MultipleChoice  • Secret
	RequiredWhen	<ul> <li>An array of Boolean values indicating the circumstances under which a value is required to be provided for this entry parameter. These are: <ul> <li>HasPrivateKey: If set to true, a value must be provided for this field when configuring a management job (either add or remove) if the certificate has an associated private key in Keyfactor Command. This would be the case, for example, when doing a PFX enrollment and adding the resulting certificate to a certificate store.</li> <li>OnAdd: If set to true, a value must be provided for this field when configuring an add certificate job.</li> <li>OnRemove: If set to true, a value must be provided for this field when configuring a remove certificate job.</li> </ul> </li> <li>OnReenrollment: If set to true, a value must be provided for this field when configuring a reenrollment job.</li> </ul>
	DependsOn	A string containing the name of the parameter on which this parameter depends. This only applies if at least two custom parameters have been created for this certificate store type. This option is used to configure one custom parameter to display only if another custom parameter contains a value.
	DefaultValue	A string containing the default value for the entry parameter. If <i>Type</i> is <i>Multiple Choice</i> , this field should contain a single value that represents the default selection from the provided list (see Options) for this entry parameter. If <i>Type</i> is <i>Boolean</i> , this field should contain <i>true</i> or <i>false</i> .
	Options	A string containing a comma-separated list of multiple choice options for this entry parameter.

Name	Description		
	<ul> <li>Tip: What's the difference between properties (custom fields) and entry parameters?</li> <li>Properties are about the certificate store definition itself and are static. For example, you might use a property to define the primary node name of an F5 instance. This node name is the same no matter what inventory or management jobs you do with the F5 device(s). Values for properties are entered in the certificate store record when creating or editing the certificate store record.</li> <li>Entry parameters are about the specific certificate within the certificate store. They are used to send additional information related to the certificate to the server or device that hosts the certificate store when running management jobs for that certificate store. Often this is more fluid information that isn't the same for every use of that certificate store. For example, several virtual servers with separate certificates in the same folder may exist on a NetScaler device. When replacing one certificate, updates may need to be made to only the virtual server that is using the certificate. In this case, the authorized user will be prompted to enter the virtual server name based on an entry parameter. Values for entry parameters are entered at the time a management job is initiated (e.g. adding a certificate to a certificate store).</li> </ul>		
InventoryEndpoint	A string containing the orchestrator endpoint to which inventory updates are sent.		
InventoryJobType	A GUID identifying the job type for inventory jobs.		
ManagementJobType	A GUID identifying the job type for management jobs.		
DiscoveryJobType	A GUID identifying the job type for discovery jobs.		
EnrollmentJobType	A GUID identifying the job type for reenrollment jobs.		

## 2.2.11.4 DELETE Certificate Store Types

The DELETE /CertificateStoreTypes method is used to delete multiple certificate store types in one request. The certificate store type IDs should be supplied in the request body as a JSON array of integers. IDs of any certificate store types that could not be deleted are returned in the response body. Delete operations will continue until the entire array of IDs has been processed. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: CertificateStoreManagement: *Modify* 

Table 231: DELETE Certificate Store Types Input Parameters

Name	In	Description
ids	Body	Required. An array of Keyfactor Command certificate store type IDs for certificate store types that should be deleted in the form (without parameter name):  [106,108,109]  Use the GET /CertificateStoreTypes method (see GET Certificate Store Types below) to retrieve a list of all the certificate store types to determine the certificate store type IDs.

## 2.2.11.5 GET Certificate Store Types

The GET /CertificateStoreTypes method is used to retrieve a list of all certificate store types. This method returns HTTP 200 OK on a success with details of the certificate store types.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: CertificateStoreManagement: *Read* 

Table 232: GET Certificate Store Types Input Parameters

Name	In	Description
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.

Table 233: GET Certificate Store Types Response Data

Name	Description		
Name	A string containing the full name of the certificate store type.		
ShortName	A string containing th	e short name assigned to the certificate store type.	
Capability	A string containing a store).	reference name for the certificate store type (e.g. NS for a NetScaler	
StoreType	A unique integer for t Command.	the certificate store type. The ID is automatically assigned by Keyfactor	
ImportType		ates the import type for the certificate store type. The ID is automatically r Command and generally matches the <i>StoreType</i> for custom certificate	
LocalStore	A Boolean that indicates whether the store is local to the orchestrator machine (true) as, for example, JKS and PEM stores managed by the Keyfactor Java Agent or remote (false) as, for example, IIS stores managed by the Keyfactor Universal Orchestrator.		
SupportedOperations	An array containing a series of Boolean values that indicate whether the certificate store type is enabled for the following functions:  • Add • Create • Discovery • Enrollment • Remove		
Properties	An array of unique parameters for the certificate store type. In the Keyfactor Command Management Portal these are known as <i>Custom Fields</i> . Property parameters include:		
	Name	Description	
	Name	A string containing the short name of the property.	
	DisplayName	A string containing the full display name of the property.	
	Туре	A string containing the type of the property:  • String  • Bool  • MultipleChoice  • Secret	

Name	Description			
	Name	Description		
	DependsOn	A string containing the name of the parameter on which this parameter depends. This only applies if at least two custom parameters have been created for this certificate store type. This option is used to configure one custom parameter to display only if another custom parameter contains a value.		
	DefaultValue	A string containing the default value(s) of the parameter. If <i>Type</i> is <i>Multiple Choice</i> , this field should contain a comma-separated list of multiple choice options for this parameter. If <i>Type</i> is <i>Boolean</i> , this field should contain <i>true</i> or <i>false</i> .		
	Required	A Boolean that indicates whether the parameter is required (true) or not (false).		
	store types th	assword		
PasswordOptions	Options for the passw	ord in the certificate store type. Password options include:		
	Name	Description		
	EntrySupported	A Boolean that indicates whether entry of a password for the certificate in the certificate store is allowed (true) or not (false).		
	StoreRequired	A Boolean that indicates whether entry of a password on the certificate store as a whole is required (true) or not (false).		
	Style	<ul> <li>A string containing the style of password:</li> <li>Default: Keyfactor Command will randomly generate a password.</li> <li>Custom: Allow a password to be entered and authen-</li> </ul>		

Name	Description		
	Name Description		
		ticated when enrolling for a certificate through Keyfactor Command when installing to a store of this type. The Custom option can be selected only if the <i>Allow Custom Password</i> in the Application Settings, is equal to <i>True</i> . For more details, see <i>Application Settings: Enrollment Tab</i> in the <i>Keyfactor Command Reference Guide</i> .	
StorePathValue	An array containing the	value(s) for the certificate store path.	
PrivateKeyAllowed	<ul> <li>A string containing the option for private key requirements for certificates stored in stores with this certificate store type:</li> <li>Forbidden: Private key is not required; generally, applies to trust stores (e.g. Root CA certificates).</li> <li>Optional: Private key is optional; applies to store types that could represent either a Trust Store or End-Entity Store.</li> <li>Required: Private key is required; applies to stores that hold an End-Entity Certificate (server or client authorization).</li> </ul>		
ServerRequired	A Boolean that indicates whether server access is required for adding certificate stores for this certificate store type (true) or not (false). If set to true, a user will be prompted for a username and password to connect to the remote server.		
PowerShell	A Boolean that indicates whether jobs for the store type are implemented using PowerShell (true) instead of a .NET class or not (false).		
BlueprintAllowed	A Boolean that indicates whether certificate stores of this type will be included when creating or applying blueprints. For more details, see <i>Orchestrator Blueprints</i> in the <i>Keyfactor Command Reference Guide</i> .		
CustomAliasAllowed	<ul> <li>A string containing the selected certificate store type alias option:</li> <li>Forbidden: A custom alias is not required and cannot be supplied.</li> <li>Optional: A custom alias is optional.</li> <li>Required: A custom alias is required.</li> <li>The certificate store alias serves as an identifier for the certificate in the store. Depending on the type of store, it may be a file name, a certificate thumbprint, a string reference, or some other information. Some types of stores may not support associating an alias with the certificate (e.g. IIS trusted root).</li> </ul>		
EntryParameters		nmeters that are required when performing management jobs on a type. Entry parameter options include:	

Name	Description		
	Name	Description	
	Name	A string containing the short name of the entry parameter.	
	DisplayName	A string containing the full display name of the entry parameter.	
	Туре	A string containing the type of the entry parameter:  • String  • Bool  • MultipleChoice  • Secret	
	RequiredWhen	<ul> <li>An array of Boolean values indicating the circumstances under which a value is required to be provided for this entry parameter. These are: <ul> <li>HasPrivateKey: If set to true, a value must be provided for this field when configuring a management job (either add or remove) if the certificate has an associated private key in Keyfactor Command. This would be the case, for example, when doing a PFX enrollment and adding the resulting certificate to a certificate store.</li> <li>OnAdd: If set to true, a value must be provided for this field when configuring an add certificate job.</li> <li>OnRemove: If set to true, a value must be provided for this field when configuring a remove certificate job.</li> </ul> </li> <li>OnReenrollment: If set to true, a value must be provided for this field when configuring a reenrollment job.</li> </ul>	
	DependsOn	A string containing the name of the parameter on which this parameter depends. This only applies if at least two custom parameters have been created for this certificate store type. This option is used to configure one custom parameter to display only if another custom parameter contains a value.	
	DefaultValue	A string containing the default value for the entry parameter. If <i>Type</i> is <i>Multiple Choice</i> , this field should contain a single value that represents the default selection from the provided list (see Options) for this entry parameter. If <i>Type</i> is <i>Boolean</i> , this field should contain <i>true</i> or <i>false</i> .	
	Options	A string containing a comma-separated list of multiple choice options for this entry parameter.	

Name	Description
	<ul> <li>Tip: What's the difference between properties (custom fields) and entry parameters?</li> <li>Properties are about the certificate store definition itself and are static. For example, you might use a property to define the primary node name of an F5 instance. This node name is the same no matter what inventory or management jobs you do with the F5 device(s). Values for properties are entered in the certificate store record when creating or editing the certificate store record.</li> <li>Entry parameters are about the specific certificate within the certificate store. They are used to send additional information related to the certificate to the server or device that hosts the certificate store when running management jobs for that certificate store. Often this is more fluid information that isn't the same for every use of that certificate store. For example, several virtual servers with separate certificates in the same folder may exist on a NetScaler device. When replacing one certificate, updates may need to be made to only the virtual server that is using the certificate. In this case, the authorized user will be prompted to enter the virtual server name based on an entry parameter. Values for entry parameters are entered at the time a management job is initiated (e.g. adding a certificate to a certificate store).</li> </ul>
InventoryEndpoint	A string containing the orchestrator endpoint to which inventory updates are sent.
InventoryJobType	A GUID identifying the job type for inventory jobs.
ManagementJobType	A GUID identifying the job type for management jobs.
DiscoveryJobType	A GUID identifying the job type for discovery jobs.
EnrollmentJobType	A GUID identifying the job type for reenrollment jobs.

# 2.2.11.6 POST Certificate Store Types

The POST /CertificateStoresTypes method is used to create certificate store types in Keyfactor Command. This method returns HTTP 200 OK on a success with a message body containing a list of certificate store type details.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: CertificateStoreManagement: *Modify* 

Table 234: POST Certificate Store Types Input Parameters

Name	In	Description	
Name	Body	<b>Required</b> . A string containing the full name of the certificate store type. A unique value must be supplied.	
ShortName	Body	<b>Required</b> . A string containing the short name assigned to the certificate store type. A unique value must be supplied with a maximum of 10 characters.	
Capability	Body	A string containing a NetScaler store).	reference name for the certificate store type (e.g. NS for a
LocalStore	Body	(true) as, for example	tes whether the store is local to the orchestrator machine e, JKS and PEM stores managed by the Keyfactor Java Agent for example, IIS stores managed by the Keyfactor Universal fault is <i>false</i> .
SupportedOperations	Body	An array containing a series of Boolean values that indicate whether the certificate store type is enabled for the following functions:  • Add • Create • Discovery • Enrollment • Remove  The default for each value is false.	
Properties	Body	An array of unique parameters for the certificate store type. In the Keyfacto Command Management Portal these are known as <i>Custom Fields</i> . Property parameters include:	
		Name	Description
		Name	<b>Required</b> . A string containing the short name of the property. If you choose to define a property, this field is <b>required</b> .
		DisplayName	<b>Required</b> . A string containing the full display name of the property. If you choose to define a property, this field is <b>required</b> .
			Required. A string containing the type of the property:  • String  • Bool  • MultipleChoice

Name	In	Description		
		Name	Description	
			Secret	
			If you choose to define a property, this field is required.	
		DependsOn	A string containing the name of the parameter on which this parameter depends. This only applies if at least two custom parameters have been created for this certificate store type. This option is used to configure one custom parameter to display only if another custom parameter contains a value.	
		DefaultValue	A string containing the default value(s) of the parameter. If <i>Type</i> is <i>Multiple Choice</i> , this field should contain a comma-separated list of multiple choice options for this parameter. If <i>Type</i> is <i>Boolean</i> , this field should contain <i>true</i> or <i>false</i> .	
		Required	A Boolean that indicates whether the parameter is required (true) or not (false).	
			are three standard properties that are used for any built- store types that require server credentials (e.g. F5): Username Password	
		These replace in previous ve credentials ar or editing of a find a certific	e the separate certificate store server records that existed ersions of Keyfactor Command. For legacy support, if we not provided through store properties during creation a certificate store, Keyfactor Command will attempt to attend to be properties for future use.	
		For example, to set a	multiple choice property:	
		"Type": "! "Depends0:	ame": "Popular Pets", MultipleChoice",	

Name	In	Description		
		"Required": false } ] This value is unset by default.		
PasswordOptions	Body	Options for the password in the certificate store type. Password options include:		
		Name	Description	
		EntrySupported	A Boolean that indicates whether entry of a password for the certificate in the certificate store is allowed (true) or not (false). The default is <i>false</i> .	
			StoreRequired	A Boolean that indicates whether entry of a password on the certificate store as a whole is required (true) or not (false). The default is <i>false</i> .
		Style	<ul> <li>A string containing the style of password:         <ul> <li>Default: Keyfactor Command will randomly generate a password.</li> <li>Custom: Allow a password to be entered and authenticated when enrolling for a certificate through Keyfactor Command when installing to a store of this type. The Custom option can be selected only if the Allow Custom Password in the Application</li></ul></li></ul>	
StorePathType	Body	store location.  • Fixed: A store path IIS).  • MultipleChoice: Al	n does not apply, generally one store per device (e.g.  low a comma separated list of options to be entered able to select from when defining the certificate store	

Name	In	Description	
StorePathValue	Body	An array containing the value(s) for the certificate store path if the StorePathType is set to Fixed or Multiple Choice.  Multiple choice values should be provided in a bracketed comma-delimited list like so:  "StorePathValue": "[\"Apple\",\"Cherry\",\"Peach\",\"Pear\"]" This value is unset by default.	
PrivateKeyAllowed	Body	<ul> <li>A string containing the option for private key requirements for certificates stored in stores with this certificate store type:</li> <li>Forbidden: Private key is not required; generally, applies to trust stores (e.g. Root CA certificates).</li> <li>Optional: Private key is optional; applies to store types that could represent either a Trust Store or End-Entity Store.</li> <li>Required: Private key is required; applies to stores that hold an End-Entity Certificate (server or client authorization).</li> <li>The default value is Forbidden.</li> </ul>	
ServerRequired	Body	A Boolean that indicates whether server access is required for adding certificate stores for this certificate store type (true) or not (false). If set to true, a user will be prompted for a username and password to connect to the remote server. The default is <i>false</i> .	
PowerShell	Body	A Boolean that indicates whether jobs for the store type are implemented using PowerShell (true) instead of a .NET class or not (false). The default is <i>false</i> .	
BlueprintAllowed	Body	A Boolean that indicates whether certificate stores of this type will be included when creating or applying blueprints. For more details, see <i>Orchestrator Blueprints</i> in the <i>Keyfactor Command Reference Guide</i> . The default is <i>false</i> .	
CustomAliasAllowed	Body	<ul> <li>A string containing the selected certificate store type alias option:</li> <li>Forbidden: A custom alias is not required and cannot be supplied.</li> <li>Optional: A custom alias is optional.</li> <li>Required: A custom alias is required.</li> <li>The certificate store alias serves as an identifier for the certificate in the store.</li> <li>Depending on the type of store, it may be a file name, a certificate thumbprint, a string reference, or some other information. Some types of stores may not support associating an alias with the certificate (e.g. IIS trusted root).</li> <li>The default value is Forbidden.</li> </ul>	
EntryParameters	Body	An array of unique parameters that are required when performing management jobs on a certificate store of this type. Entry parameter options include:	

Name	In	Description	
		Name	Description
		Name	<b>Required</b> . A string containing the short name of the entry parameter. If you choose to define an entry parameter, this field is <b>required</b> . The name should be entered without spaces.
		DisplayName	<b>Required</b> . A string containing the full display name of the entry parameter. If you choose to define an entry parameter, this field is <b>required</b> .
		Туре	Required. A string containing the type of the entry parameter:  • String • Bool • MultipleChoice • Secret  If you choose to define an entry parameter, this field is required.
		RequiredWhen	An array of Boolean values indicating the circumstances under which a value is required to be provided for this entry parameter. These are:  • HasPrivateKey: If set to true, a value must be provided for this field when configuring a management job (either add or remove) if the certificate has an associated private key in Keyfactor Command. This would be the case, for example, when doing a PFX enrollment and adding the resulting certificate to a certificate store. The default is false.  • OnAdd: If set to true, a value must be provided for this field when configuring an add certificate job. The default is false.  • OnRemove: If set to true, a value must be provided for this field when configuring a remove certificate job. The default is false.  • OnReenrollment: If set to true, a value must be provided for this field when configuring a reenrollment: If set to true, a value must
		DependsOn	A string containing the name of the parameter on

Name	In	Description		
		Name	Description	
			which this parameter depends. This only applies if at least two custom parameters have been created for this certificate store type. This option is used to configure one custom parameter to display only if another custom parameter contains a value.	
		DefaultValue	A string containing the default value for the entry parameter. If <i>Type</i> is <i>Multiple Choice</i> , this field should contain a single value that represents the default selection from the provided list (see Options) for this entry parameter. If <i>Type</i> is <i>Boolean</i> , this field should contain <i>true</i> or <i>false</i> .  This value is unset by default.	
		Options	A string containing a comma-separated list of multiple choice options for this entry parameter. This field should only be populated if <i>Type</i> is set to <i>MultipleChoice</i> .  This value is unset by default.	
		For example, to set a multiple choice entry parameter:		
	"Type": "Mu "RequiredWh "HasPriv "OnAdd": "OnRemov "OnReenr }, "DefaultVal	oAnimal",  ne": "Favorite Zoo Animal",  ltipleChoice",  nen": {  rateKey": false,		
		This value is unset by d	efault.	
		entry paramete	e difference between properties (custom fields) and ers? ers are about the certificate store definition itself and	

Name In	Description	on
		are static. For example, you might use a property to define the primary node name of an F5 instance. This node name is the same no matter what inventory or management jobs you do with the F5 device(s). Values for properties are entered in the certificate store record when creating or editing the certificate store record.  • Entry parameters are about the specific certificate within the certificate store. They are used to send additional information related to the certificate to the server or device that hosts the certificate store when running management jobs for that certificate store. Often this is more fluid information that isn't the same for every use of that certificate store. For example, several virtual servers with separate certificates in the same folder may exist on a NetScaler device. When replacing one certificate, updates may need to be made to only the virtual server that is using the certificate. In this case, the authorized user will be prompted to enter the virtual server name based on an entry parameter. Values for entry parameters are entered at the time a management job is initiated (e.g. adding a certificate to a certificate store).

Table 235: POST Certificate Store Types Response Data

Name	Description		
Name	A string containing the full name of the certificate store type.		
ShortName	A string containing th	e short name assigned to the certificate store type.	
Capability	A string containing a store).	reference name for the certificate store type (e.g. NS for a NetScaler	
StoreType	A unique integer for t Command.	the certificate store type. The ID is automatically assigned by Keyfactor	
ImportType	=	ates the import type for the certificate store type. The ID is automatically r Command and generally matches the <i>StoreType</i> for custom certificate	
LocalStore	A Boolean that indicates whether the store is local to the orchestrator machine (true) as, for example, JKS and PEM stores managed by the Keyfactor Java Agent or remote (false) as, for example, IIS stores managed by the Keyfactor Universal Orchestrator.		
SupportedOperations	An array containing a series of Boolean values that indicate whether the certificate store type is enabled for the following functions:  • Add  • Create  • Discovery  • Enrollment  • Remove		
Properties	An array of unique parameters for the certificate store type. In the Keyfactor Command Management Portal these are known as <i>Custom Fields</i> . Property parameters include:		
	Name	Description	
	Name	A string containing the short name of the property.	
	DisplayName	A string containing the full display name of the property.	
	Туре	A string containing the type of the property:  • String  • Bool  • MultipleChoice	

Name	Description			
	Name	Description		
		• Secret		
	DependsOn	A string containing the name of the parameter on which this parameter depends. This only applies if at least two custom parameters have been created for this certificate store type. This option is used to configure one custom parameter to display only if another custom parameter contains a value.		
	DefaultValue	A string containing the default value(s) of the parameter. If <i>Type</i> is <i>Multiple Choice</i> , this field should contain a comma-separated list of multiple choice options for this parameter. If <i>Type</i> is <i>Boolean</i> , this field should contain <i>true</i> or <i>false</i> .		
	Required	A Boolean that indicates whether the parameter is required (true) or not (false).		
	Note: There are three standard properties that are used for any built-in certifica store types that require server credentials (e.g. F5):  • ServerUsername  • ServerPassword  • ServerUseSsl			
	versions of Ke through store Command will	the separate certificate store server records that existed in previous yfactor Command. For legacy support, if credentials are not provided properties during creation or editing of a certificate store, Keyfactor lattempt to find a certificate store server record and copy the credento the store properties for future use.		
PasswordOptions	Options for the passw	ord in the certificate store type. Password options include:		
	Name	Description		
	EntrySupported	A Boolean that indicates whether entry of a password for the certificate in the certificate store is allowed (true) or not (false).		
	StoreRequired	A Boolean that indicates whether entry of a password on the certificate store as a whole is required (true) or not (false).		
	Style	A string containing the style of password:  • Default: Keyfactor Command will randomly generate a		

Name	Description		
	Name	Description	
		password.  • Custom: Allow a password to be entered and authenticated when enrolling for a certificate through Keyfactor Command when installing to a store of this type. The Custom option can be selected only if the Allow Custom Password in the Application Settings, is equal to True. For more details, see Application Settings: Enrollment Tab in the Keyfactor Command Reference Guide.	
StorePathValue	An array containing the	value(s) for the certificate store path.	
PrivateKeyAllowed	<ul> <li>A string containing the option for private key requirements for certificates stored in stores with this certificate store type:</li> <li>Forbidden: Private key is not required; generally, applies to trust stores (e.g. Root CA certificates).</li> <li>Optional: Private key is optional; applies to store types that could represent either a Trust Store or End-Entity Store.</li> <li>Required: Private key is required; applies to stores that hold an End-Entity Certificate (server or client authorization).</li> </ul>		
ServerRequired	A Boolean that indicates whether server access is required for adding certificate stores for this certificate store type (true) or not (false). If set to true, a user will be prompted for a username and password to connect to the remote server.		
PowerShell	A Boolean that indicates whether jobs for the store type are implemented using PowerShell (true) instead of a .NET class or not (false).		
BlueprintAllowed	A Boolean that indicates whether certificate stores of this type will be included when creating or applying blueprints. For more details, see <i>Orchestrator Blueprints</i> in the <i>Keyfactor Command Reference Guide</i> .		
CustomAliasAllowed	<ul> <li>A string containing the selected certificate store type alias option:</li> <li>Forbidden: A custom alias is not required and cannot be supplied.</li> <li>Optional: A custom alias is optional.</li> <li>Required: A custom alias is required.</li> <li>The certificate store alias serves as an identifier for the certificate in the store. Depending on the type of store, it may be a file name, a certificate thumbprint, a string reference, or some other information. Some types of stores may not support associating an alias with the certificate (e.g. IIS trusted root).</li> </ul>		
EntryParameters	An array of unique parameters that are required when performing management jobs on a		

Name	Description		
	certificate store of this type. Entry parameter options include:		
	Name	Description	
	Name	A string containing the short name of the entry parameter.	
	DisplayName	A string containing the full display name of the entry parameter.	
	Туре	A string containing the type of the entry parameter:  • String  • Bool  • MultipleChoice  • Secret	
	RequiredWhen	<ul> <li>An array of Boolean values indicating the circumstances under which a value is required to be provided for this entry parameter. These are: <ul> <li>HasPrivateKey: If set to true, a value must be provided for this field when configuring a management job (either add or remove) if the certificate has an associated private key in Keyfactor Command. This would be the case, for example, when doing a PFX enrollment and adding the resulting certificate to a certificate store.</li> <li>OnAdd: If set to true, a value must be provided for this field when configuring an add certificate job.</li> <li>OnRemove: If set to true, a value must be provided for this field when configuring a remove certificate job.</li> </ul> </li> <li>OnReenrollment: If set to true, a value must be provided for this field when configuring a reenrollment job.</li> </ul>	
	DependsOn	A string containing the name of the parameter on which this parameter depends. This only applies if at least two custom parameters have been created for this certificate store type. This option is used to configure one custom parameter to display only if another custom parameter contains a value.	
	DefaultValue	A string containing the default value for the entry parameter. If <i>Type</i> is <i>Multiple Choice</i> , this field should contain a single value that represents the default selection from the provided list (see Options) for this entry parameter. If <i>Type</i> is <i>Boolean</i> , this field should contain <i>true</i> or <i>false</i> .	
	Options	A string containing a comma-separated list of multiple choice options for this entry parameter.	

Name	Description
	<ul> <li>Tip: What's the difference between properties (custom fields) and entry parameters?</li> <li>Properties are about the certificate store definition itself and are static. For example, you might use a property to define the primary node name of an F5 instance. This node name is the same no matter what inventory or management jobs you do with the F5 device(s). Values for properties are entered in the certificate store record when creating or editing the certificate store record.</li> <li>Entry parameters are about the specific certificate within the certificate store. They are used to send additional information related to the certificate to the server or device that hosts the certificate store when running management jobs for that certificate store. Often this is more fluid information that isn't the same for every use of that certificate store. For example, several virtual servers with separate certificates in the same folder may exist on a NetScaler device. When replacing one certificate, updates may need to be made to only the virtual server that is using the certificate. In this case, the authorized user will be prompted to enter the virtual server name based on an entry parameter. Values for entry parameters are entered at the time a management job is initiated (e.g. adding a certificate to a certificate store).</li> </ul>
InventoryEndpoint	A string containing the orchestrator endpoint to which inventory updates are sent.
InventoryJobType	A GUID identifying the job type for inventory jobs.
ManagementJobType	A GUID identifying the job type for management jobs.
DiscoveryJobType	A GUID identifying the job type for discovery jobs.
EnrollmentJobType	A GUID identifying the job type for reenrollment jobs.

## 2.2.11.7 PUT Certificate Store Types

The PUT /CertificateStoreTypes method is used to update a certificate store type in Keyfactor Command. This method returns HTTP 200 OK on a success with a message body containing a list of certificate store type details.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: CertificateStoreManagement: *Modify* 



Warning: Any previously populated fields that are not submitted with their full existing data using this method will be cleared of their existing data. When using this method, you should first do a GET to retrieve all the values for the record you want to update, enter corrected data into the field(s) you want to update,

and then submit all the fields using PUT, including the fields that contain values but which you are not changing.

Table 236: PUT Certificate Store Types Input Parameters

Name	In	Description		
StoreType	Body	<b>Required</b> . The Keyfactor Command reference ID for the certificate store type.		
Name	Body	<b>Required</b> . A string containing the full name of the certificate store type. A unique value must be supplied.		
ShortName	Body	<b>Required</b> . A string containing the short name assigned to the certificate store type. A unique value must be supplied with a maximum of 10 characters.		
Capability	Body	A string containing a r NetScaler store).	reference name for the certificate store type (e.g. NS for a	
		has registered	pability cannot be changed on an edit if an orchestrator d with Keyfactor Command, been approved, and included estore type in its capability list.	
LocalStore	Body	A Boolean that indicates whether the store is local to the orchestrator machine (true) as, for example, JKS and PEM stores managed by the Keyfactor Java Agent or remote (false) as, for example, IIS stores managed by the Keyfactor Universal Orchestrator. The default is <i>false</i> .		
SupportedOperations	Body	An array containing a series of Boolean values that indicate whether the certificate store type is enabled for the following functions:  • Add  • Create  • Discovery  • Enrollment  • Remove  The default for each value is false.		
Properties	Body	An array of unique parameters for the certificate store type. In the Command Management Portal these are known as <i>Custom Fields</i> . parameters include:		
		Name	Description	
		StoreTypeID	<b>Required</b> . An integer identifying the certificate store type. This is the same ID referenced by the StoreType parameter, above. If you are updating a certificate store type, this field is <b>required</b> .	
			Required. A string containing the short name of the	

Name	In	Description		
		Name	Description	
			property. If you choose to define a property, this field is <b>required</b> .	
		DisplayName	<b>Required</b> . A string containing the full display name of the property. If you choose to define a property, this field is <b>required</b> .	
	Туре	Required. A string containing the type of the property:  • String  • Bool  • MultipleChoice  • Secret  If you choose to define a property, this field is required.		
	DependsOn	A string containing the name of the parameter on which this parameter depends. This only applies if at least two custom parameters have been created for this certificate store type. This option is used to configure one custom parameter to display only if another custom parameter contains a value.		
		DefaultValue	A string containing the default value(s) of the parameter. If <i>Type</i> is <i>Multiple Choice</i> , this field should contain a comma-separated list of multiple choice options for this parameter. If <i>Type</i> is <i>Boolean</i> , this field should contain <i>true</i> or <i>false</i> .	
		Required	A Boolean that indicates whether the parameter is required (true) or not (false).	
	in certificate s	lassword		

Name	In	Description				
		into the store pr	e store server record and copy the credentials from it roperties for future use.			
		<pre>"Properties": [</pre>				
		This value is unset by de	fault.			
PasswordOptions	Body	Options for the password in the certificate store type. Password options include:				
		Name	Description			
		EntrySupported	A Boolean that indicates whether entry of a password for the certificate in the certificate store is allowed (true) or not (false). The default is <i>false</i> .			
		StoreRe			StoreRequired	A Boolean that indicates whether entry of a password on the certificate store as a whole is required (true) or not (false). The default is <i>false</i> .
			Style	<ul> <li>A string containing the style of password:</li> <li>Default: Keyfactor Command will randomly generate a password.</li> <li>Custom: Allow a password to be entered and authenticated when enrolling for a certificate through Keyfactor Command when installing to a store of this type. The Custom option can be selected only if the Allow Custom Password in the Application Settings, is equal to True. For more details, see Application Settings: Enrollment Tab in</li> </ul>		

Name	In	Description	
		Name	Description
			theKeyfactor Command Reference Guide.
			The default value is <i>Default</i> .
StorePathType	Body	<ul> <li>A string containing the selected store type:</li> <li>Freeform: Users are required to enter a path defining the certificate store location.</li> <li>Fixed: A store path does not apply, generally one store per device (e.g. IIS).</li> <li>MultipleChoice: Allow a comma separated list of options to be entered that users will be able to select from when defining the certificate store location.</li> <li>This value is unset by default.</li> </ul>	
StorePathValue	Body	An array containing the value(s) for the certificate store path if the  StorePathType is set to Fixed or Multiple Choice.  Multiple choice values should be provided in a bracketed comma-delimited list  like so:  "StorePathValue": "[\"Apple\",\"Cherry\",\"Peach\",\"Pear\"]"  This value is unset by default.	
PrivateKeyAllowed	Body	<ul> <li>A string containing the option for private key requirements for certificates stored in stores with this certificate store type: <ul> <li>Forbidden: Private key is not required; generally, applies to trust stores (e.g. Root CA certificates).</li> <li>Optional: Private key is optional; applies to store types that could represent either a Trust Store or End-Entity Store.</li> <li>Required: Private key is required; applies to stores that hold an End-Entity Certificate (server or client authorization).</li> </ul> </li> <li>The default value is Forbidden.</li> </ul>	
ServerRequired	Body	A Boolean that indicates whether server access is required for adding certificate stores for this certificate store type (true) or not (false). If set to true, a user will be prompted for a username and password to connect to the remote server. The default is <i>false</i> .	
PowerShell	Body	A Boolean that indicates whether jobs for the store type are implemented using PowerShell (true) instead of a .NET class or not (false). The default is <i>false</i> .	
BlueprintAllowed	Body		s whether certificate stores of this type will be included ng blueprints. For more details, see <i>Orchestrator Blue</i> -

Name	In	Description														
		prints in the Keyfactor Command Reference Guide. The default is false.														
CustomAliasAllowed	Body	<ul> <li>A string containing the selected certificate store type alias option:</li> <li>Forbidden: A custom alias is not required and cannot be supplied.</li> <li>Optional: A custom alias is optional.</li> <li>Required: A custom alias is required.</li> <li>The certificate store alias serves as an identifier for the certificate in the store.</li> <li>Depending on the type of store, it may be a file name, a certificate thumbprint, a string reference, or some other information. Some types of stores may not support associating an alias with the certificate (e.g. IIS trusted root).</li> <li>The default value is Forbidden.</li> </ul>														
EntryParameters	Body		ameters that are required when performing management ore of this type. Entry parameter options include:													
		Name	Description													
		StoreTypeID	Required. An integer identifying the certificate store type. This is the same ID referenced by the StoreType parameter, above. If you are updating a certificate store type, this field is required.													
		Name	<b>Required</b> . A string containing the short name of the entry parameter. If you choose to define an entry parameter, this field is <b>required</b> . The name should be entered without spaces.													
															DisplayName	<b>Required</b> . A string containing the full display name of the entry parameter. If you choose to define an entry parameter, this field is <b>required</b> .
	Туре	Required. A string containing the type of the entry parameter:  • String  • Bool  • MultipleChoice  • Secret  If you choose to define an entry parameter, this field is required.														
		RequiredWhen	An array of Boolean values indicating the circum-													

Name	In	Description	
		Name	Description
			stances under which a value is required to be provided for this entry parameter. These are:  • HasPrivateKey: If set to true, a value must be provided for this field when configuring a management job (either add or remove) if the certificate has an associated private key in Keyfactor Command. This would be the case, for example, when doing a PFX enrollment and adding the resulting certificate to a certificate store. The default is false.  • OnAdd: If set to true, a value must be provided for this field when configuring an add certificate job. The default is false.  • OnRemove: If set to true, a value must be provided for this field when configuring a remove certificate job. The default is false.  • OnReenrollment: If set to true, a value must be provided for this field when configuring a reenrollment: If set to true, a value must
		DependsOn	A string containing the name of the parameter on which this parameter depends. This only applies if at least two custom parameters have been created for this certificate store type. This option is used to configure one custom parameter to display only if another custom parameter contains a value.
	DefaultValue	A string containing the default value for the entry parameter. If <i>Type</i> is <i>Multiple Choice</i> , this field should contain a single value that represents the default selection from the provided list (see Options) for this entry parameter. If <i>Type</i> is <i>Boolean</i> , this field should contain <i>true</i> or <i>false</i> .  This value is unset by default.	
		Options	A string containing a comma-separated list of multiple choice options for this entry parameter. This field should only be populated if <i>Type</i> is set to <i>MultipleChoice</i> .  This value is unset by default.
		For example, to set a m	ultiple choice entry parameter:

Description Name In "EntryParameter": [ "StoreTypeId": 111, "Name": "ZooAnimal", "DisplayName": "Favorite Zoo Animal", "Type": "MultipleChoice", "RequiredWhen": { "HasPrivateKey": false, "OnAdd": true, "OnRemove": true, "OnReenrollment": true "DefaultValue": "Penguin", "Options": "Tiger, Bear, Giraffe, Lion, Wolf, Penguin, Zebra" ] This value is unset by default. Tip: What's the difference between properties (custom fields) and entry parameters? • Properties are about the certificate store definition itself and are static. For example, you might use a property to define the primary node name of an F5 instance. This node name is the same no matter what inventory or management jobs you do with the F5 device(s). Values for properties are entered in the certificate store record when creating or editing the certificate store record. • Entry parameters are about the specific certificate within the certificate store. They are used to send additional information related to the certificate to the server or device that hosts the certificate store when running management jobs for that certificate store. Often this is more fluid information that isn't the same for every use of that certificate store. For example, several virtual servers with separate certificates in the same folder may exist on a NetScaler device. When replacing one certificate, updates may need to be made to only the virtual

server that is using the certificate. In this case, the authorized user will be prompted to enter the virtual server name based on an entry parameter. Values for entry parameters are entered at the time a management job is initiated (e.g. adding

a certificate to a certificate store).

Table 237: PUT Certificate Store Types Response Data

Name	Description		
Name	A string containing the full name of the certificate store type.		
ShortName	A string containing th	e short name assigned to the certificate store type.	
Capability	A string containing a store).	reference name for the certificate store type (e.g. NS for a NetScaler	
StoreType	A unique integer for to Command.	the certificate store type. The ID is automatically assigned by Keyfactor	
ImportType	_	ates the import type for the certificate store type. The ID is automatically r Command and generally matches the <i>StoreType</i> for custom certificate	
LocalStore	A Boolean that indicates whether the store is local to the orchestrator machine (true) as, for example, JKS and PEM stores managed by the Keyfactor Java Agent or remote (false) as, for example, IIS stores managed by the Keyfactor Universal Orchestrator.		
SupportedOperations	An array containing a series of Boolean values that indicate whether the certificate store type is enabled for the following functions:  • Add • Create • Discovery • Enrollment • Remove		
Properties	An array of unique parameters for the certificate store type. In the Keyfactor Command Management Portal these are known as <i>Custom Fields</i> . Property parameters include:		
	Name	Description	
	Name	A string containing the short name of the property.	
	DisplayName	A string containing the full display name of the property.	
	Туре	A string containing the type of the property:  • String  • Bool  • MultipleChoice	

Name	Description		
	Name	Description	
		• Secret	
	DependsOn	A string containing the name of the parameter on which this parameter depends. This only applies if at least two custom parameters have been created for this certificate store type. This option is used to configure one custom parameter to display only if another custom parameter contains a value.	
	DefaultValue	A string containing the default value(s) of the parameter. If <i>Type</i> is <i>Multiple Choice</i> , this field should contain a comma-separated list of multiple choice options for this parameter. If <i>Type</i> is <i>Boolean</i> , this field should contain <i>true</i> or <i>false</i> .	
	Required	A Boolean that indicates whether the parameter is required (true) or not (false).	
		assword	
	versions of Ke through store Command will	the separate certificate store server records that existed in previous yfactor Command. For legacy support, if credentials are not provided properties during creation or editing of a certificate store, Keyfactor lattempt to find a certificate store server record and copy the credento the store properties for future use.	
PasswordOptions	Options for the passw	ord in the certificate store type. Password options include:	
	Name	Description	
	EntrySupported	A Boolean that indicates whether entry of a password for the certificate in the certificate store is allowed (true) or not (false).	
	StoreRequired	A Boolean that indicates whether entry of a password on the certificate store as a whole is required (true) or not (false).	
	Style	A string containing the style of password:  • Default: Keyfactor Command will randomly generate a	

Name	Description	
	Name	Description
		password.  • Custom: Allow a password to be entered and authenticated when enrolling for a certificate through Keyfactor Command when installing to a store of this type. The Custom option can be selected only if the Allow Custom Password in the Application Settings, is equal to True. For more details, see Application Settings: Enrollment Tab in the Keyfactor Command Reference Guide.
StorePathValue	An array containing the	value(s) for the certificate store path.
PrivateKeyAllowed	<ul> <li>A string containing the option for private key requirements for certificates stored in stores with this certificate store type:</li> <li>Forbidden: Private key is not required; generally, applies to trust stores (e.g. Root CA certificates).</li> <li>Optional: Private key is optional; applies to store types that could represent either a Trust Store or End-Entity Store.</li> <li>Required: Private key is required; applies to stores that hold an End-Entity Certificate (server or client authorization).</li> </ul>	
ServerRequired	A Boolean that indicates whether server access is required for adding certificate stores for this certificate store type (true) or not (false). If set to true, a user will be prompted for a username and password to connect to the remote server.	
PowerShell	A Boolean that indicates whether jobs for the store type are implemented using PowerShell (true) instead of a .NET class or not (false).	
BlueprintAllowed	A Boolean that indicates whether certificate stores of this type will be included when creating or applying blueprints. For more details, see <i>Orchestrator Blueprints</i> in the <i>Keyfactor Command Reference Guide</i> .	
CustomAliasAllowed	<ul> <li>A string containing the selected certificate store type alias option:</li> <li>Forbidden: A custom alias is not required and cannot be supplied.</li> <li>Optional: A custom alias is optional.</li> <li>Required: A custom alias is required.</li> <li>The certificate store alias serves as an identifier for the certificate in the store. Depending on the type of store, it may be a file name, a certificate thumbprint, a string reference, or some other information. Some types of stores may not support associating an alias with the certificate (e.g. IIS trusted root).</li> </ul>	
EntryParameters	An array of unique parameters that are required when performing management jobs on a	

Name	Description	
	certificate store of this	type. Entry parameter options include:
	Name	Description
	Name	A string containing the short name of the entry parameter.
	DisplayName	A string containing the full display name of the entry parameter.
	Туре	A string containing the type of the entry parameter:  • String  • Bool  • MultipleChoice  • Secret
	RequiredWhen	<ul> <li>An array of Boolean values indicating the circumstances under which a value is required to be provided for this entry parameter. These are: <ul> <li>HasPrivateKey: If set to true, a value must be provided for this field when configuring a management job (either add or remove) if the certificate has an associated private key in Keyfactor Command. This would be the case, for example, when doing a PFX enrollment and adding the resulting certificate to a certificate store.</li> <li>OnAdd: If set to true, a value must be provided for this field when configuring an add certificate job.</li> <li>OnRemove: If set to true, a value must be provided for this field when configuring a remove certificate job.</li> </ul> </li> <li>OnReenrollment: If set to true, a value must be provided for this field when configuring a reenrollment job.</li> </ul>
	DependsOn	A string containing the name of the parameter on which this parameter depends. This only applies if at least two custom parameters have been created for this certificate store type. This option is used to configure one custom parameter to display only if another custom parameter contains a value.
	DefaultValue	A string containing the default value for the entry parameter. If <i>Type</i> is <i>Multiple Choice</i> , this field should contain a single value that represents the default selection from the provided list (see Options) for this entry parameter. If <i>Type</i> is <i>Boolean</i> , this field should contain <i>true</i> or <i>false</i> .
	Options	A string containing a comma-separated list of multiple choice options for this entry parameter.

Name	Description
	<ul> <li>Tip: What's the difference between properties (custom fields) and entry parameters?</li> <li>Properties are about the certificate store definition itself and are static. For example, you might use a property to define the primary node name of an F5 instance. This node name is the same no matter what inventory or management jobs you do with the F5 device(s). Values for properties are entered in the certificate store record when creating or editing the certificate store record.</li> <li>Entry parameters are about the specific certificate within the certificate store. They are used to send additional information related to the certificate to the server or device that hosts the certificate store when running management jobs for that certificate store. Often this is more fluid information that isn't the same for every use of that certificate store. For example, several virtual servers with separate certificates in the same folder may exist on a NetScaler device. When replacing one certificate, updates may need to be made to only the virtual server that is using the certificate. In this case, the authorized user will be prompted to enter the virtual server name based on an entry parameter. Values for entry parameters are entered at the time a management job is initiated (e.g. adding a certificate to a certificate store).</li> </ul>
InventoryEndpoint	A string containing the orchestrator endpoint to which inventory updates are sent.
InventoryJobType	A GUID identifying the job type for inventory jobs.
ManagementJobType	A GUID identifying the job type for management jobs.
DiscoveryJobType	A GUID identifying the job type for discovery jobs.
EnrollmentJobType	A GUID identifying the job type for reenrollment jobs.

## 2.2.12 CSR Generation

The CSR Generation component of the Keyfactor API includes methods necessary to generate certificate signing requests and determine which ones are pending.

Table 238: CSR Generation Endpoints

Endpoint	Method	Description	Link
/Pending/{id}	DELETE	Deletes a pending CSR by ID.	DELETE CSR Generation Pending ID on the next page
/Pending/{id}	GET	Returns the details of a specific CSR request based on the ID number.	GET CSR Generation Pending ID on the next page

Endpoint	Method	Description	Link
/Pending	DELETE	Deletes multiple pending CSRs.	DELETE CSR Generation Pending on the next page
/Pending	GET	Returns a list of all pending CSRs.	GET CSR Generation Pending on the next page
/Generate	POST	Generate and configure a CSR request.	POST CSR Generation Generate on page 551

### 2.2.12.1 DELETE CSR Generation Pending ID

The DELETE /CSRGeneration/Pending/{id} method is used to delete a certificate signing request with the defined ID that has not yet been enrolled. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: CertificateEnrollment: *PendingCsr* 

Table 239: DELETE CSR Generation Pending {id} Input Parameters

In	Description
Path	Required. The ID of the certificate signing request for the CSR that should be deleted.
	Use the GET /CSRGeneration/Pending method (see GET CSR Generation Pending on the next page) to retrieve a list of all the pending CSRs to determine the CSR IDs.

### 2.2.12.2 GET CSR Generation Pending ID

The GET /CSRGeneration/Pending/{id} method is used to return a generated CSR with the defined ID that has not yet been enrolled. This method returns HTTP 200 OK on a success with the CSR in PEM format. This method does not return the parsed subject name or CSR request time. If you need that information, use the GET /CSRGeneration/Pending method (see GET CSR Generation Pending on the next page).



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: CertificateEnrollment: *PendingCsr* 

Table 240: GET CSR Generation Pending {id} Input Parameters

Name	In	Description
id	Path	Required. The ID of the CSR that should be retrieved.

Table 241: GET CSR Generation Pending {id} Response Data

Name	Description
CSRFilePath	The proposed file name for the CSR file.  This is considered deprecated and may be removed in a future release.
CSR	The text of the CSR in PEM format.

#### 2.2.12.3 DELETE CSR Generation Pending

The DELETE /CSRGeneration/Pending method is used to delete multiple certificate signing requests that have not yet been enrolled in one request. The IDs should be supplied in the request body as a JSON array of integers. Delete operations will continue until the entire array of IDs has been processed. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: CertificateEnrollment: *PendingCsr* 

Table 242: DELETE CSR Generation Pending Input Parameters

Name	In	Description
ids	Body	<b>Required</b> . An array of Keyfactor Command certificate signing request IDs for CSRs that should be deleted in the form (without parameter name):  [8,14,27]
		Use the <i>GET /CSRGeneration/Pending</i> method (see <u>GET CSR Generation Pending below</u> ) to retrieve a list of all the pending CSRs to determine the CSR IDs.

#### 2.2.12.4 GET CSR Generation Pending

The GET /CSRGeneration/Pending method is used to return details for generated CSRs that have not yet been enrolled. This method returns HTTP 200 OK on a success with details of the pending CSRs with details.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: CertificateEnrollment: *PendingCsr* 

Table 243: GET CSR Generation Pending Input Parameters

Name	In	Description
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>Id</i> .
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.

Table 244: GET CSR Generation Pending Response Data

Name	Description
Id	A unique integer for the CSR generated.
CSR	A string containing the text of the CSR in PEM format.
RequestTime	A string containing the date and time that the CSR was generated in UTC time.
Subject	An array containing the subject of the certificate including the certificate subject information, the subject alternative names, the key length, and the hash algorithm.

#### 2.2.12.5 POST CSR Generation Generate

The POST /CSRGeneration/Generate method is used to generate and configure a CSR. This method returns HTTP 200 OK on a success with a message body containing the text of the CSR file created.

This method generates a private key and stores it in the Keyfactor Command database. When you use the CSR resulting from this method to enroll for a certificate through Keyfactor Command (see <u>POST Enrollment CSR on page 600</u>), the resulting certificate is married together with the stored private key and may then be download with private key (see POST Certificates Recover on page 261).



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: CertificateEnrollment: *CsrGeneration* 



**Note:** This endpoint no longer includes the CSRFilePath return value in the response from the API call. Code separate from the API should be used to handle receipt of the CSR and placement on the file system.

Table 245: POST CSR Generation Generate Input Parameters

Name	In	Description			
Subject	Body	Required. A string containing the subject name for the certificate using X.500 format for the full distinguished name (DN). For example:  "Subject": "CN=websrvr14.keyexample.com,OU=IT,O=\"Key Example, Inc.\",L-L=Independence,ST=OH,C=US"  Supported subject name fields are:			
		Name	Abbreviation	Description	
		CommonName	CN	Required*. The desired common name of the certificate to be requested with the CSR.  This field is required if the Common Name Regular Expression application setting is set to the default value of .+. See the Application Settings: Enrollment Tab section of the Keyfactor Command Reference Guide for more information.	
		Organization	0	The desired organization of the certificate to be requested with the CSR.	
		OrganizationalUnit	OU	The desired organizational unit of the certificate to be requested with the CSR.	
		Locality	L	The desired city of the certificate to be requested with the CSR.	
		State	ST	The desired state of the certificate to be requested with the CSR.	
		Country	С	The desired country (two characters) of the certificate to be requested with the CSR.	
		Email	Е	The desired email address of the certificate to be requested with the CSR.	
КеуТуре	Body	Required. A string indicating the desired key encryption of the certificate. Accepted key types are:  • RSA			

Name	In	Description		
		• ECC		
KeyLength	Body	Required. An integer indicating the desired key size of the certificate. Accepted key sizes are:  • 256 • 384 • 521 • 2048 • 4096 • 8192		
Template	Body	A string indicating the desired template to be used for the certificate to be requested with the CSR. The template must have been configured in Keyfactor Command to support CSR generation. This field is optional.  Tip: Although you can include a template in your CSR, template handling in CSRs is future functionality, and the template will not be parsed back out of the CSR. Instead, submit a template directly with your CSR enrollment (see POST Enrollment CSR on page 600).		
SANs	Body	An array of key/value pairs that represent the elements for Keyfactor Command to use when generating the subject alternative name (SAN) for the certificate requested by the CSR. Possible values for the key are:		
		Value	Description	
		rfc822	RFC 822 Name	
		dns	DNS Name	
		directory	Directory Name	
		uri	Uniform Resource Identifier	
		ip4	IP v4 Address	
		ip6	IP v6 Address	
		registeredid	Registered ID (an OID)	
		ms_ntprincipalname	MS_NTPrincipalName (a string)	
		ms_ntdsreplication	MS_NTDSReplication (a GUID)	
		For example:		

Name	In	Description
		<pre>"SANs": {     "dns": [         "dnssan1.keyexample.com",         "dnssan2.keyexample.com",         "dnssan3.keyexample.com" ],     "ip4": [         "192.168.2.73" ]</pre>

Table 246: POST CSR Generation Generate Response Data

Name	Description
CSR	The text of the CSR in PEM format.

## 2.2.13 Custom Job Types

The Custom Job Types component of the Keyfactor API includes methods necessary to create, update, list and delete custom orchestrator job types. Custom job types are intended to execute jobs on an orchestrator built using the AnyAgent framework that are outside the standard list of job functions built into Keyfactor Command. This powerful feature can execute just about any job that requires processing on the orchestrator and submitting data back to Keyfactor Command. The data submitted by custom jobs to Keyfactor Command is stored as a string and is limited to 2 MB.

Table 247: Custom Job Types Endpoints

Endpoint	Method	Description	Link
/{id}	DELETE	Deletes the custom job type for the specified ID.	DELETE Custom Job Types ID on the next page
/{id}	GET	Returns details for the custom job type for the specified ID.	GET Custom Job Types ID on the next page
/	GET	Returns all the custom job types.	GET Custom Job Types on page 556
/	POST	Creates a custom job type.	POST Custom Job Types on page 558
/	PUT	Updates an existing custom job type.	PUT Custom Job Types on page 561

## 2.2.13.1 DELETE Custom Job Types ID

The DELETE /JobTypes/Custom/{id} method is used to delete an existing custom job type with the specified GUID. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: AgentManagement: *Modify* 

Table 248: DELETE JobTypes Custom {id} Input Parameters

Name	In	Description
id	Path	Required. The Keyfactor Command reference GUID of the custom job type.
		Use the <i>GET /JobTypes/Custom</i> method (see <u>GET Custom Job Types on the next page</u> ) to retrieve a list of all the custom job types to determine the job type GUID.

#### 2.2.13.2 GET Custom Job Types ID

The GET /JobTypes/Custom/{id} method is used to return a custom job type with the specified GUID. This method returns HTTP 200 OK on a success with details for the custom job type.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: AgentManagement: *Read* 

Table 249: GET JobTypes Custom {id} Input Parameters

Name	In	Description
id	Path	Required. The Keyfactor Command reference GUID of the custom job type.
		Use the <i>GET /JobTypes/Custom</i> method (see <u>GET Custom Job Types on the next page</u> ) to retrieve a list of all the custom job types to determine the job type GUID.

Table 250: GET JobTypes Custom {id} Response Data

Name	Description				
ld	The Keyfactor Command reference GUID for the custom job type. This ID is automatically set by Keyfactor Command.				
JobTypeName	A string containing the when submitting a job	e short name for the custo for it.	m job type. This is used	to reference the job type	
Description	A string containing a d	lescription for the custom	job type.		
JobTypeFields	An array of job type fit type fields parameters	elds that indicate the type s are:	of tasks the job type is	designed to perform. Job	
	Name	Description			
	Name	A string that indicates the name for the job type field.			
	Туре	A value that indicates the data type of the job type field.  Possible values are:			
		Integer Value	Enum Value	Description	
		1	String	String	
		2	Int	Integer	
		3	DateTime	Date	
		4	Bool	Boolean	
	DefaultValue	A string containing the default value of the job type field.  If <i>Type</i> is <i>Boolean</i> , this field should contain <i>true</i> or <i>false</i> .			
	Required	A Boolean that sets whether the job type field is required (true) or not (false).			

#### 2.2.13.3 GET Custom Job Types

The GET /JobTypes/Custom method is used to retrieve a list of all custom job types. This method returns HTTP 200 OK on a success with details for each job type.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: AgentManagement: *Read* 

Table 251: GET JobTypes Custom Input Parameters

Name	In	Description
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.

Table 252: GET JobTypes Custom Response Data

Name	Description				
Id	The Keyfactor Command reference GUID for the custom job type. This ID is automatically set by Keyfactor Command.				
JobTypeName	A string containing the when submitting a job	e short name for the custo o for it.	m job type. This is used	to reference the job type	
Description	A string containing a c	description for the custom	job type.		
JobTypeFields	An array of job type fi	elds that indicate the type s are:	of tasks the job type is	designed to perform. Job	
	Name Description				
	Name	A string that indicates the name for the job type field.			
	Туре	A value that indicates the data type of the job type field.  Possible values are:			
		Integer Value	Enum Value	Description	
		1	String	String	
		2	Int	Integer	
		3	DateTime	Date	
		4	Bool	Boolean	
	DefaultValue	A string containing the default value of the job type field.  If <i>Type</i> is <i>Boolean</i> , this field should contain <i>true</i> or <i>false</i> .			
	Required	A Boolean that sets whether the job type field is required (true) or not (false).			

# 2.2.13.4 POST Custom Job Types

The POST /JobTypes/Custom method is used to create a custom orchestrator job type in Keyfactor Command. This method returns HTTP 200 OK on a success with a message body containing a list of custom job type details.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: AgentManagement: *Modify* 

Table 253: POST JobTypes Custom Input Parameters

Name	In	Description				
JobTypeName	Body	<b>Required</b> . A string containing the short name for the custom job type. This is used to reference the job type when submitting a job for it. This name should not contain spaces.				
Description	Body	A string containing a	description for the cust	tom job type.		
JobTypeFields	Body	An array of job type fields that indicate the type of tasks the job type is designed to perform. Job type fields parameters are:				
		Name	Description			
		Name	<b>Required</b> . A string the field.	nat indicates the nar	me for the job type	
		Туре	field.	either an integer o	a type of the job type r the matching enum	
			Integer Value	Enum Value	Description	
			1	String	String	
			2	Int	Integer	
			3	DateTime	Date	
			4	Bool	Boolean	
		DefaultValue	field.  If <i>Type</i> is <i>Boolean</i> , th	is field should conta	ult value of the job type ain <i>true</i> or <i>false</i> . ameter is set to <i>true</i> .	
		Required	A Boolean that sets whether the job type field is required (true) or not (false). The default is <i>false</i> .			
		For example:				
				"JobTypeFields" { "Name": "	: [ Favorite Type of Pe	t",

Name	In	Description
		<pre>"Type": "String",     "DefaultValue": "Cat",     "Required": true }, {     "Name": "Model Year of First Car",     "Type": "Int" }, {     "Name": "Mother's Birthday",     "Type": "DateTime" } </pre>

Table 254: POST JobTypes Custom Response Data

Name	Description				
Id	The Keyfactor Command reference GUID for the custom job type. This ID is automatically set by Keyfactor Command.				
JobTypeName	A string containing the when submitting a job	e short name for the custo o for it.	m job type. This is used	to reference the job type	
Description	A string containing a c	description for the custom	job type.		
JobTypeFields	An array of job type fi	elds that indicate the type s are:	of tasks the job type is	designed to perform. Job	
	Name	Description			
	Name	A string that indicates the name for the job type field.			
	Туре	A value that indicates the data type of the job type field.  Possible values are:			
		Integer Value	Enum Value	Description	
		1	String	String	
		2	Int	Integer	
		3	DateTime	Date	
		4	Bool	Boolean	
	DefaultValue	A string containing the default value of the job type field.  If <i>Type</i> is <i>Boolean</i> , this field should contain <i>true</i> or <i>false</i> .			
	Required	A Boolean that sets whether the job type field is required (true) or not (false).			

## 2.2.13.5 PUT Custom Job Types

The PUT /JobTypes/Custom method is used to create a custom orchestrator job type in Keyfactor Command. This method returns HTTP 200 OK on a success with a message body containing a list of certificate store type details.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: AgentManagement: *Modify* 



Warning: Any previously populated fields that are not submitted with their full existing data using this method will be cleared of their existing data. When using this method, you should first do a GET to retrieve all the values for the record you want to update, enter corrected data into the field(s) you want to update, and then submit all the fields using PUT, including the fields that contain values but which you are not changing.

Table 255: PUT JobTypes Custom Input Parameters

Name	In	Description			
Id	Body	The Keyfactor Command reference GUID for the custom job type. This ID is automatically set by Keyfactor Command.			
JobTypeName	Body		ntaining the short nam e when submitting a jo		
Description	Body	A string containing a	description for the cust	tom job type.	
JobTypeFields	Body	An array of job type f perform. Job type fie	ields that indicate the t	type of tasks the job	type is designed to
		Name	Description		
		Name	Required. A string th field.	at indicates the nar	me for the job type
		Туре	field.	either an integer o	a type of the job type
			Integer Value	Enum Value	Description
			1	String	String
			2	Int	Integer
			3	DateTime	Date
			4	Bool	Boolean
		DefaultValue	Required*. A string containing the default value of the job type field.  If <i>Type</i> is <i>Boolean</i> , this field should contain <i>true</i> or <i>false</i> .  This field is <b>required</b> if the <i>Required</i> parameter is set to <i>true</i> .		ain <i>true</i> or <i>false</i> .
		Required	Required	A Boolean that sets v (true) or not (false).	
		For example:			

Name	In	Description
		"JobTypeFields": [  {     "Name": "Favorite Type of Pet",     "Type": "String",     "DefaultValue": "Cat",     "Required": true }, {     "Name": "Model Year of First Car",     "Type": "Int" }, {     "Name": "Mother's Birthday",     "Type": "DateTime" } ]

Table 256: PUT JobTypes Custom Response Data

Name	Description				
Id	The Keyfactor Command reference GUID for the custom job type. This ID is automatically set by Keyfactor Command.				
JobTypeName	A string containing the when submitting a job	e short name for the custon o for it.	m job type. This is used	to reference the job type	
Description	A string containing a c	description for the custom j	job type.		
JobTypeFields	An array of job type fi	elds that indicate the type s are:	of tasks the job type is	designed to perform. Job	
	Name	Description			
	Name	A string that indicates the name for the job type field.			
	Туре	A value that indicates the data type of the job type field.  Possible values are:			
		Integer Value	Enum Value	Description	
		1	String	String	
		2	Int	Integer	
		3	DateTime	Date	
		4	Bool	Boolean	
	DefaultValue	A string containing the default value of the job type field.  If <i>Type</i> is <i>Boolean</i> , this field should contain <i>true</i> or <i>false</i> .			
	Required	A Boolean that sets whether the job type field is required (true) or not (false).			

## 2.2.14 Enrollment

The Enrollment component of the Keyfactor API includes methods necessary to enroll certificate signing requests (CSRs) and personal information exchanges (PFXs).

Table 257: Enrollment Endpoints

Endpoint	Method	Description	Link
/Settings/{Id}	GET	Returns the template settings to use during enrollment.	GET Enrollment Settings ID below
/CSR/Context/My	GET	Returns the templates available for CSR enrollment by the current user.	GET Enrollment CSR Content My on page 573
/PFX/Context/My	GET	Returns the templates available for PFX enrollment by the current user.	GET Enrollment PFX Content My on page 585
/AvailableRenewal/Id/{id}	GET	Returns the type of renewals available for the referenced certificate ID.	GET Enrollment Available Renewal ID on page 597
/AvailableRenewal/Thumbprint/ {thumbprint}	GET	Returns the type of renewals available for the referenced certificate thumbprint.	GET Enrollment Available Renewal Thumbrint on page 598
/CSR	POST	Performs a CSR enrollment.	POST Enrollment CSR on page 600
/PFX	POST	Performs a PFX enrollment.	POST Enrollment PFX on page 605
/CSR/Parse	POST	Returns information found in a CSR in a human friendly form.	POST Enrollment CSR Parse on page 618
/PFX/Deploy	POST	Adds a certificate into a certificate store following a PFX enrollment or certificate renewal.	POST Enrollment PFX Deploy on page 619
/PFX/Replace	POST	Replaces a certificate in a certificate store following a PFX enrollment.	POST Enrollment PFX Replace on page 625
/Renew	POST	Performs a certificate renewal.	POST Enrollment Renew on page 627

## 2.2.14.1 GET Enrollment Settings ID

The GET /Enrollment/Settings/{id} method is used to return the template settings to use during enrollment for a given template. The response will be the resolved values for the template settings (based on whether they are global or template-specific). This method returns HTTP 200 OK on a success with details of the template regular expressions, defaults, and policy. If there is a template-specific setting, the template-specific setting will be shown in the response. If there is not a template-specific setting, the global settings will be shown in the response.



Tip: The following permissions (see <u>Security Overview</u>) are required to use this feature: CertificateEnrollment: *EnrollCSR* or CertificateEnrollment: *EnrollPFX* or CertificateEnrollment: *CsrGen*eration

Table 258: GET Enrollment Settings {id} Input Parameters

Name	Description
id	The enrollment template Id.  Use the GET /Templates method (see GET Templates on page 1185) to retrieve a list of all the templates to determine the template ID.

Table 259: GET Enrollment Settings {id} Response Body

Name	Description				
TemplateRegexes	An object containing the regular expressions resolved for the template. Regular expression details are:				
	Name	Description			
	SubjectPart	ojectPart A string indicating the portion of the subject the regular expression applies to (e.g. CN).			
	RegEx	A string specifying the regular expression against which data entered in the indicated subject part field (e.g. CN) in the enrollment pages of the Keyfactor Command Management Portal or using an API enrollment method will be validated.  Use the GET /Templates/SubjectParts method (see GET Templates Subject Parts on page 1184) to retrieve a list of all the supported subject parts.  The following are some regular expression examples:			
		Subject Part	Example		
		CN (Common Name)	This regular expression specifies that the data entered in the field must consist of some number of characters in the first portion of the field made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly ".keyexample.com":		
			^[a-zA-Z0-9'_ \.\-]*\.keyexample\.com\$ The default value for the Common Name regular expression is:		
			.+ This requires entry of at least one character in the Common Name field in the enrollment pages.		
		O (Organization)	This regular expression requires that the organization name entered in the field be one of "Key Example Inc", "Key Example" or "Key Example Inc.":  ^(?:Key Example Inc Key Example Key Example, Inc\.)\$  The period in the final company name (Key Example, Inc.) needs to be escaped in the regular expression		

Name	Description			
	Name	Description		
		Subject Part	Example	
			with a slash ("\") but the comma does not.	
		OU (Organization Unit)	This regular expression requires that the organizational unit entered in the field be one of these four departments:  ^(?:IT HR Accounting E-Commerce)\$	
		L (City/Locality)	This regular expression requires that the city entered in the field be one of these five cities:  ^(?:Boston Chicago New York London Dallas)\$	
		ST (State/Province)	This regular expression requires that the state entered in the field be one of these eight states:  ^(?:Massachusetts Illinois New York Ontario Texas)\$	
		C (Country)	This regular expression requires that the country entered in the field be either US or CA:  ^(?:US CA)\$	
		E (Email)	This regular expression specifies that the data entered in the field must consist of some number of characters prior to the "@" made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly "@keyexample.com":  ^[a-zA-Z0-9'_\.\-]*@keyexample\.com\$	
		DNS (Subject Alternative Name: DNS Name)	This regular expression specifies that the data entered in the field must consist of some number of characters in the first portion of the field made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly either ".keyexample1.com" or ".keyexample2.com":  ^[a-zA-Z0-9'_\.\-]*\.	

Name	Description			
	Name	Description		
		Subject Part	Example	
			<pre>(?:keyexample1\.com keyexample2\.com )\$</pre>	
		IPv4 (Subject Alternative Name: IPv4 Address)	This regular expression specifies that the data entered in the field must be exactly "130.101." followed by anywhere between 1 and 3 numbers followed by exactly "." followed by anywhere between 1 and 3 numbers:  ^130\.101\.(?:[0-9]{1,3})\.(?:[0-9]{1,3})\$  This regular expression specifies only that the IPv4 address is made up of 4 sets of between 1 and 3 numbers separated by periods:  ^(?:[0-9]{1,3}\.){3}[0-9]{1,3}\$	
		IPv6 (Subject Alternative Name: IPv6 Address)	This regular expression specifies that the data entered in the field must be made up of eight sets of between one and four numbers and/or uppercase letters separated by colons:  ^(?:[A-F0-9]{1,4}:){7}[A-F0-9]{1,4}\$	
		MAIL (Subject Alternative Name: Email)	This regular expression specifies that the data entered in the field must consist of some number of characters prior to the "@" made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly "@keyexample.com":  ^[a-zA-Z0-9'_\.\-]*@keyexample\.com\$	
		UPN (Subject Alternative Name: User Prin- cipal Name)	This regular expression specifies that the data entered in the field must consist of some number of characters prior to the "@" made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly "@keyexample.com":  ^[a-zA-Z0-9'_\.\-]*@keyexample\.com\$	
	Error	A string specifying the	error message displayed to the user when the subject	

Name	Description				
	Name	Description			
		part referenced in the CSR or entered for a PFX enrollment does not match the given regular expression. Note that the error message already includes a leading string with the subject part (e.g. "Common Name:" or "Invalid CN provided:" depending on the interface used). Your custom message follows this.			
TemplateDefaults	defined, take pred	ng the template defaults resolved for the template. Template-level defaults, if edence over global-level template defaults. For more information about global-aults, see <a href="MEETTEMPLATER">GET Templates Settings on page 1165</a> . The template default object ving parameters:			
	Value	Description			
	SubjectPart	A string indicating the portion of the subject the default applies to (e.g. L for City/Locality).  Use the GET /Templates/SubjectParts method (see GET Templates Subject Parts on page 1184) to retrieve a list of all the supported subject parts.			
	Value	A string containing the value to assign as the default for that subject part (e.g. Chicago).			
	For example:				
	"Value' }, { "Subjec	nults": [ ctPart": "L", de la			
TemplatePolicy	An array containin parameters:	g the template policy settings. The template policy array contains the following			
	Value	Description			
	RSAValidKeySize	An object containing a comma-delimited list of integers defining the valid RSA key sizes supported for all templates used for enrollment. The supported values are:			

Name	Description		
	Value	Description	
		<ul><li>2048</li><li>4096</li></ul>	
	ECCValidCurves	An object containing a list of strings defining the valid elliptic curve algorithms for ECC templates. These may be specified using the well-known OIDs for ECC algorithms or by friendly name. Well-known OIDs include:  • 1.2.840.10045.3.1.7 = P-256/prime256v1/secp256r1  • 1.3.132.0.34 = P-384/secp384r1  • 1.3.132.0.35 = P-521/secp521r1  When specifying by friendly name, do not include a slash (use "P-256", not "P-256/prime256v1/secp256r1").	
	AllowKeyReuse	A Boolean that indicates whether private key reuse is allowed (true) or not (false). This option allows to certificate renewals.	
	AllowWildcards	A Boolean that indicates whether wildcards are allowed (true) or not (false).	
	RFCEnforcement	A Boolean that indicates whether RFC 2818 compliance enforcement is enabled (true) or not (false). When this option is set to <i>true</i> , certificate enrollments made through Keyfactor Command for this template must include at least one DNS SAN. In the Keyfactor CommandManagement Portal, this causes the CN entered in PFX enrollment to automatically be replicated as a SAN, which the user can either change or accept. For CSR enrollment, if the CSR does not have a SAN that matches the CN, one will automatically be added to the certificate if this is set.	
	For example:		
	"TemplatePolicy": {     "RSAValidKeySize         2048,         4096 ],     "ECCValidCurves"         "1.2.840.1004         "1.3.132.0.35 ],     "AllowKeyReuse":     "AllowWildcards"     "RFCEnforcement"	s": [ : [ 5.3.1.7", " false, : true,	

Name	Description
	"AllowEd448": false, "AllowEd25519": false }

#### 2.2.14.2 GET Enrollment CSR Content My

The GET /Enrollment/CSR/Context/My method is used to check the templates and CAs available for CSR enrollment for the current user. This method has no input parameters. It returns HTTP 200 OK on a success with the list of templates that are available for enrollment via Keyfactor Command and the CAs those templates may be enrolled from along with template and CA configuration details. Results are returned based on the enrollment permissions of the user making the request—both Keyfactor Command permissions and template and CA level permissions on the originating CA. Templates or standalone CAs are included in the results only if the user has appropriate permissions in both locations and the template and CA are configured for CSR enrollment in Keyfactor Command.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: CertificateEnrollment: *EnrollCSR* 

Name	Description				
Templates	An array containing the templates available for enrollment by the user. The array contains the following parameters:				
	Name	Description			
	Id	An integer indicating the template.	Keyfactor Command reference ID of the certificate		
	Name	typically does not contain	ommon name (short name) of the template. This name in spaces. For a template created using a Microsoft manage- e Microsoft template name.		
	DisplayName	typically does not contain	A string containing the common name (short name) of the template. This name typically does not contain spaces. For a template created using a Microsoft management tool, this will be the Microsoft template name.		
	Forest	A string containing the name of the configuration tenant the template is associated with.			
	KeySize	A string indicating the minimum supported key size of the template.			
	RequiresAp- proval	A Boolean indicating whether the template has been configured with the Microsoft <i>CA certificate manager approval</i> option enabled ( <i>true</i> ) or not ( <i>false</i> ).			
	RFCEn- forcement	A Boolean indicating whether certificate enrollments made through Keyfactor Command for this template must include at least one DNS SAN ( <i>true</i> ) or not ( <i>false</i> ). In the Keyfactor Command Management Portal, this causes the CN entered in PFX enrollment to automatically be replicated as a SAN, which the user can either change or accept. For CSR enrollment, if the CSR does not have a SAN that matches the CN, one will automatically be added to the certificate if this is set. By default, this is set to <i>false</i> at a system-wide level and may be overridden on a template-bytemplate basis.			
	CAs	ment, that are configured	thorities from which the template is available for enroll- d for enrollment in Keyfactor Command, and on which the llment permissions. Information about the CA includes:		
		Name	Description		
		Name	The full name of the CA, made up of the DNS host- name of the certificate authority (e.g.		

Name	Description	
	Name	Description
		corpca01.keyexample.com) and the logical name (e.g CorplssuingCA1) for a full name similar to corpca01.keyexample.com\\CorplssuingCA1.
	RFCEnforcement	A Boolean that sets whether certificate enrollments made through Keyfactor Command for this CA must include at least one DNS SAN ( <i>true</i> ) or not ( <i>false</i> ). In the Keyfactor Command Management Portal, this causes the CN entered in PFX enrollment to automatically be replicated as a SAN, which the user can either change or accept. For CSR enrollment, if the CSR does not have a SAN that matches the CN, one will automatically be added to the certificate if this is set. This setting at the CA level applies only to standalone CAs. For CAs that use templates, this setting is controlled at the template level and is ignored at the CA level.
	SubscriberTerms	A Boolean that sets whether to add a checkbox on the enrollment pages to force users to agree to a custom set of terms before enrolling (true) or not (false).
		Tip: Configure a link to the custom terms using the URL to Subscriber Terms application setting. See Application Settings: Enrollment Tab in the Keyfactor Command Reference Guide for more information.

process. This functionality offers such benefits as:

certificate requirements per template.

• Providing additional information to the CA with the CSR.

• Preventing users from requesting invalid certificates, based on your specific

Once created on the template, these values are shown in Keyfactor Command on the PFX and CSR enrollment pages in the *Additional Enrollment Fields* section. The

Description Name

Name

# fields are mandatory during enrollment. The data will appear on the CA / Issued

Certificates attribute tab for certificates enrolled with a template configured with Keyfactor Command enrollment fields.



Description

Note: These are not metadata fields, so they are not stored in the Keyfactor Command database, but simply passed through to the CA. The CA in turn could, via a gateway or policy module, use this data to perform required actions.

The array contains the following parameters:

Name	Description			
Id	An integer indicating the ID of the custom enrollment field.			
Name	A string indicating the name of the custom enrollment field. This name will appear on the enrollment pages.			
Options	For multiple choice values, an array of strings containing the value choices.			
DataType	An integer indicating the parameter type. The options are:			
	Value	Description		
	1	String: A free-form data entry field.		
	2	Multiple Choice: Provides a list of acceptable values for the field. The multiple choice values are provided in the <i>Options</i> parameter.		

#### For example:

```
"EnrollmentFields": [
      "Id": 3,
      "Name": "MyCustomField",
      "Options": ["Green", "Red", "Yellow", "Blue"],
      "DataType": 2
```

Name	Description		
	Name	Description	
		1	
	MetadataFields	<ul> <li>An object containing template-level metadata field settings. Template-level metadata field configurations can override global metadata field configurations in these possible ways: <ul> <li>Configuration on the metadata field of required, optional or hidden.</li> <li>The default value for the metadata field.</li> <li>A regular expression defined for the field (string fields only) against which entered data will be validated along with its associated message.</li> <li>For fields of data type multiple choice, the list of values that appear in multiple choice dropdowns.</li> </ul> </li> <li>Metadata field settings defined on a template apply to enrollments made with that template only. Template-level metadata field settings, if defined, take precedence over global-level metadata field settings.</li> <li>The metadata field settings array contains the following parameters:</li> </ul>	
		Name	Description
		Id	The Keyfactor Command reference ID of the template- specific metadata setting.
		DefaultValue	A string containing the default value defined for the metadata field for the specific template.
		Metadatald	An integer indicating the global metadata field associated with the template-specific settings.
		Validation	A string containing the template-specific regular expression against which data entered in a string field will be validated. When a user enters information in a metadata field that does not match the specified regular expression, he or she will see the warning message specified in the Message field. For example:  ^[a-zA-Z0-9'_\.\-]*@  (keyexample\.org keyexample\.com)\$  This regular expression specifies that the data entered in the field must consist of some number of characters prior

Name	Description			
	Name	Description		
		Name	Description	
		letters, nur and/or hyp "@keyexar		de up only of lowercase letters, uppercase rs, apostrophes, underscores, periods, s followed by exactly either .org" or "keyexample.com". y supported for metadata fields with data
		Enrollment		indicates how metadata fields should be PFX and CSR Enrollment pages. Possible
			Value	Description
			0	Optional Users have the option to either enter a value or not enter a value in the field.
			1	Required Users are required to enter data in the field when populating metadata fields on the PFX and CSR Enrollment pages. The field is not required on the certificate details or Add Certificate page.
			2	Hidden The field is hidden and does not appear on the PFX and CSR Enroll- ment pages. This field still appears on the certificate details and the Add Certificate page.
		Message	enters informat	ning a message to present when a user tion in a metadata field that does not plate-specific regular expression ( <i>Valid</i> -

Name	Description			
	Name	Description		
		Name	Description	
		Options	An array containing a comma separated list of values that should appear in the field dropdown for multiple choice fields.  This field is only supported for metadata fields with data type <i>multiple choice</i> .	
		For example:		
		"Metada  "Valida g keyexample\ "Enroll "Messag @keyexample.c }, {  "Id": 1 "Defaul "Metada "Valida "Enroll "Messag	LtValue": "reggie.wallace@keyexample.com",  ataId": 4,  ation": "^[a-zA-Z0-9'_\\.\\-]*@(keyexample\\.or- \\.com)\$",  Lment": 1,  ge": "Your email address must be of the form user- com or fname.lname@keyexample.com."	
	Regexes	An object containing the global template regular expression settings. These apply to all enrollments that are not otherwise overridden by individual template settings, including those that do not use a template (e.g. from a standalone CA). Regular expression details are:		
		Name D	escription	
		Template- Th	ne Keyfactor Command reference ID of the certificate template	

Name	Description				
	Name	Description	Description		
		Name	Description		
		Id	the regular expres	ssion is associated with.	
		SubjectP- art	A string indicating the portion of the subject the regular expression applies to (e.g. CN).		
		RegEx	A string specifying the regular expression against which data entered in the indicated subject part field (e.g. CN) in the enrollment pages of the Keyfactor Command Management Portal or using an API enrollment method will be validated.  Use the GET /Templates/SubjectParts method (see GET Templates Subject Parts on page 1184) to retrieve a list of all the supported subject parts.  The following are some regular expression examples:		
			Subject Part	Example	
			CN (Common Name)	This regular expression specifies that the data entered in the field must consist of some number of characters in the first portion of the field made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly ".keyexample.com":  ^[a-zA-Z0-9'_ \.\-]*\.keyexample\.com\$	
				The default value for the Common Name regular expression is:  .+  This requires entry of at least one character in the Common Name field in the enrollment pages.	
			O (Organ- ization)	This regular expression requires that the	

Name	Description					
	Name	Description	Description			
		Name	Description			
			Subject Part	Example		
				organization name entered in the field be one of "Key Example Inc", "Key Example" or "Key Example Inc.":		
				^(?:Key Example Inc Key Example Key Example, Inc\.)\$ The period in the final company name (Key Example, Inc.) needs to be escaped in the regular expression with a slash ("\") but the comma does not.		
			OU (Organ- ization Unit)	This regular expression requires that the organizational unit entered in the field be one of these four departments:  ^(?:IT HR Accounting E-Commerce)\$		
			L (City/Locality)	This regular expression requires that the city entered in the field be one of these five cities:  ^(?:Boston Chicago New York London Dallas)\$		
			ST (State/Provin- ce)	This regular expression requires that the state entered in the field be one of these eight states:  (?:Massachusetts Illinois Ne w York Ontario Texas)\$		
			C (Country)	This regular expression requires that the country entered in the field be either US or CA:  ^(?:US CA)\$		

Name	Description					
	Name	Description	Description			
		Name	Description	Description		
			Subject Part	Example		
			E (Email)	This regular expression specifies that the data entered in the field must consist of some number of characters prior to the "@" made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly "@keyexample.com":  ^[a-zA-Z0-9'_ \.\-]*@keyexample\.com\$		
			DNS (Subject Alternative Name: DNS Name)	This regular expression specifies that the data entered in the field must consist of some number of characters in the first portion of the field made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly either ".keyexample1.com" or ".keyexample2.com":  ^[a-zA-Z0-9'_\.\-]*\.		
				(?:keyexample1\.com keyexample2\.com)\$		
			IPv4 (Subject Alternative Name: IPv4 Address)	This regular expression specifies that the data entered in the field must be exactly "130.101." followed by anywhere between 1 and 3 numbers followed by exactly "." followed by anywhere between 1 and 3 numbers:  ^130\.101\.(?:[0-9]{1,3})\.		
				(?:[0-9]{1,3})\$ This regular expression specifies only that the IPv4 address is made up of 4 sets of		

Name	Description					
	Name	Description	Description			
		Name	Description	Description		
			Subject Part	Example		
				between 1 and 3 numbers separated by periods:  ^(?:[0-9]{1,3}\.){3}[0-9] {1,3}\$		
			IPv6 (Subject Alternative Name: IPv6 Address)	This regular expression specifies that the data entered in the field must be made up of eight sets of between one and four numbers and/or uppercase letters separated by colons:  ^(?:[A-F0-9]{1,4}:){7}[A-F0-9]{1,4}\$		
			MAIL (Subject Alternative Name: Email)	This regular expression specifies that the data entered in the field must consist of some number of characters prior to the "@" made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly "@keyexample.com":  ^[a-zA-Z0-9'_ \.\-]*@keyexample\.com\$		
			UPN (Subject Alternative Name: User Principal Name)	This regular expression specifies that the data entered in the field must consist of some number of characters prior to the "@" made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly "@keyexample.com":  ^[a-zA-Z0-9'_ \.\-]*@keyexample\.com\$		

Name	Description				
	Name	Description			
		Name	Description		
		Error	A string specifying the error message displayed to the user when the subject part referenced in the CSR or entered for a PFX enrollment does not match the given regular expression. Note that the error message already includes a leading string with the subject part (e.g. "Common Name:" or "Invalid CN provided:" depending on the interface used). Your custom message follows this.		
	Exten- dedKeyUsages	Currently not	in use.		
	Curve	_	ating the OID of the elliptical curve algorithm configured for the ECC templates.		
Stan- daloneCAs	An array containing enrollment information for standalone certificate authorities available for enrollment for the current user. Information about the CA includes:				
	Name	Descrip	tion		
	Name	authority daloneCa	name of the CA, made up of the DNS hostname of the certificate y (e.g. myca.keyexample.com) and the logical name (e.g. CorpStan-A1) for a full name similar to myca.keyexample prpStandaloneCA1.		
	RFCEnforcement	Commar In the Ke PFX enro either ch that mat is set. Th	an that sets whether certificate enrollments made through Keyfactor and for this CA must include at least one DNS SAN ( <i>true</i> ) or not ( <i>false</i> ). Explactor Command Management Portal, this causes the CN entered in collment to automatically be replicated as a SAN, which the user can mange or accept. For CSR enrollment, if the CSR does not have a SAN exches the CN, one will automatically be added to the certificate if this ais setting at the CA level applies only to standalone CAs. For CAs that polates, this setting is controlled at the template level and is ignored at evel.		
	SubscriberTerms		an that sets whether to add a checkbox on the enrollment pages to ers to agree to a custom set of terms before enrolling ( <i>true</i> ) or not		
		A	Tip: Configure a link to the custom terms using the URL to Subscriber Terms application setting. See Application Settings: Enrollment Tab in the Keyfactor Command Reference Guide for more information.		

#### 2.2.14.3 GET Enrollment PFX Content My

The GET /Enrollment/PFX/Context/My method is used to check the templates and CAs available for PFX enrollment for the current user. This method has no input parameters. It returns HTTP 200 OK on a success with the list of templates that are available for enrollment via Keyfactor Command and the CAs those templates may be enrolled from along with template and CA configuration details. Results are returned based on the enrollment permissions of the user making the request—both Keyfactor Command permissions and template and CA level permissions on the originating CA. Templates or standalone CAs are included in the results only if the user has appropriate permissions in both locations and the template and CA are configured for PFX enrollment in Keyfactor Command.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: CertificateEnrollment: *EnrollPFX* 

Table 261: GET Enrollment PFX Content My Response Body

Name	Description				
Templates	An array containing parameters:	the templates available for	enrollment by the user. The array contains the following		
	Name	Description			
	Id	An integer indicating the Keyfactor Command reference ID of the certificate template.			
	Name	typically does not contain	ommon name (short name) of the template. This name a spaces. For a template created using a Microsoft manage-e Microsoft template name.		
	DisplayName	typically does not contain	A string containing the common name (short name) of the template. This name typically does not contain spaces. For a template created using a Microsoft management tool, this will be the Microsoft template name.		
	Forest	A string containing the name of the configuration tenant the template is associated with.			
	KeySize	A string indicating the minimum supported key size of the template.			
	RequiresAp- proval	A Boolean indicating whether the template has been configured with the Microsoft <i>CA certificate manager approval</i> option enabled ( <i>true</i> ) or not ( <i>false</i> ).			
	RFCEn- forcement	A Boolean indicating whether certificate enrollments made through Keyfactor Command for this template must include at least one DNS SAN ( <i>true</i> ) or not ( <i>false</i> ). In the Keyfactor Command Management Portal, this causes the CN entered in PFX enrollment to automatically be replicated as a SAN, which the user can either change or accept. For CSR enrollment, if the CSR does not have a SAN that matches the CN, one will automatically be added to the certificate if this is set. By default, this is set to <i>false</i> at a system-wide level and may be overridden on a template-by-template basis.			
	CAs	An array of certificate authorities from which the template is available for enrollment, that are configured for enrollment in Keyfactor Command, and on which the requesting user has enrollment permissions. Information about the CA includes:			
		Name	Description		
		Name	The full name of the CA, made up of the DNS host- name of the certificate authority (e.g.		

Name	Description	Description				
	Name	Description	Description			
		Name	Description			
			corpca01.keyexample.com) and the logical name (e.g. CorplssuingCA1) for a full name similar to corpca01.keyexample.com\\CorplssuingCA1.			
		RFCEnforcement	A Boolean that sets whether certificate enrollments made through Keyfactor Command for this CA must include at least one DNS SAN ( <i>true</i> ) or not ( <i>false</i> ). In the Keyfactor Command Management Portal, this causes the CN entered in PFX enrollment to automatically be replicated as a SAN, which the user can either change or accept. For CSR enrollment, if the CSR does not have a SAN that matches the CN, one will automatically be added to the certificate if this is set. This setting at the CA level applies only to standalone CAs. For CAs that use templates, this setting is controlled at the template level and is ignored at the CA level.			
		SubscriberTerms	A Boolean that sets whether to add a checkbox on the enrollment pages to force users to agree to a custom			

**Tip:** Configure a link to the custom terms using the *URL* to *Subscriber Terms* application setting. See *Application Settings: Enrollment Tab* in the *Keyfactor Command Reference Guide* for more information.

set of terms before enrolling (true) or not (false).

EnrollmentFields An object containing custom enrollment fields. These are configured on a pertemplate basis to allow you to submit custom fields with CSR enrollments and PFX enrollments to supply custom request attributes to the CA during the enrollment process. This functionality offers such benefits as:

- Preventing users from requesting invalid certificates, based on your specific certificate requirements per template.
- Providing additional information to the CA with the CSR.

Once created on the template, these values are shown in Keyfactor Command on the PFX and CSR enrollment pages in the *Additional Enrollment Fields* section. The

Description Name

Name

# fields are mandatory during enrollment. The data will appear on the CA / Issued Certificates attribute tab for certificates enrolled with a template configured with

Keyfactor Command enrollment fields.



Description

Note: These are not metadata fields, so they are not stored in the Keyfactor Command database, but simply passed through to the CA. The CA in turn could, via a gateway or policy module, use this data to perform required actions.

The array contains the following parameters:

Name	Description			
Id	An integer indicating the ID of the custom enrollment field.			
Name	A string indicating the name of the custom enrollment field.  This name will appear on the enrollment pages.			
Options	For multiple choice values, an array of strings containing the value choices.			
DataType	An integer indic	rating the parameter type. The options are:		
	Value	Description		
	1	String: A free-form data entry field.		
	2	Multiple Choice: Provides a list of acceptable values for the field. The multiple choice values are provided in the <i>Options</i> parameter.		

#### For example:

```
"EnrollmentFields": [
      "Id": 3,
      "Name": "MyCustomField",
      "Options": ["Green", "Red", "Yellow", "Blue"],
      "DataType": 2
```

Name	Description		
	Name	Description	
		1	
	MetadataFields	<ul> <li>An object containing template-level metadata field settings. Template-level metadata field configurations can override global metadata field configurations in these possible ways: <ul> <li>Configuration on the metadata field of required, optional or hidden.</li> <li>The default value for the metadata field.</li> <li>A regular expression defined for the field (string fields only) against which entered data will be validated along with its associated message.</li> <li>For fields of data type multiple choice, the list of values that appear in multiple choice dropdowns.</li> </ul> </li> <li>Metadata field settings defined on a template apply to enrollments made with that template only. Template-level metadata field settings, if defined, take precedence over global-level metadata field settings.</li> <li>The metadata field settings array contains the following parameters:</li> </ul>	
		Name	Description
		Id	The Keyfactor Command reference ID of the template- specific metadata setting.
		DefaultValue	A string containing the default value defined for the metadata field for the specific template.
		Metadatald	An integer indicating the global metadata field associated with the template-specific settings.
		Validation	A string containing the template-specific regular expression against which data entered in a string field will be validated. When a user enters information in a metadata field that does not match the specified regular expression, he or she will see the warning message specified in the Message field. For example:  ^[a-zA-Z0-9'_\.\-]*@  (keyexample\.org keyexample\.com)\$  This regular expression specifies that the data entered in the field must consist of some number of characters prior

Name	Description			
	Name	Description		
		Name	Description	
		letters, numbers, apostrophes, and/or hyphens followed by ex "@keyexample.org" or "keyexa		
		Enrollment		indicates how metadata fields should be PFX and CSR Enrollment pages. Possible
			Value	Description
			0	Optional Users have the option to either enter a value or not enter a value in the field.
			1	Required Users are required to enter data in the field when populating metadata fields on the PFX and CSR Enrollment pages. The field is not required on the certificate details or Add Certificate page.
			2	Hidden The field is hidden and does not appear on the PFX and CSR Enroll- ment pages. This field still appears on the certificate details and the Add Certificate page.
		Message	enters informa	ning a message to present when a user tion in a metadata field that does not plate-specific regular expression ( <i>Valid</i> -

Name	Description			
	Name	Description		
		Name	Description	
		Options	An array containing a comma separated list of values that should appear in the field dropdown for multiple choice fields.  This field is only supported for metadata fields with data type <i>multiple choice</i> .	
		For example:		
		<pre>"MetadataFields": [</pre>		
	Regexes	to all enrollme settings, includ	raining the global template regular expression settings. These apply onts that are not otherwise overridden by individual template ding those that do not use a template (e.g. from a standalone CA). sion details are:	
		Name	Description	
		Template-	The Keyfactor Command reference ID of the certificate template	

Name	Description				
	Name	Description	Description		
		Name	Description		
		Id	the regular expression is associated with.		
		SubjectP- art	A string indicating sion applies to (e.	the portion of the subject the regular expresg. CN).	
		RegEx	A string specifying the regular expression against which data entered in the indicated subject part field (e.g. CN) in the enrollment pages of the Keyfactor Command Management Portal or using an API enrollment method will be validated.  Use the GET/Templates/SubjectParts method (see GET Templates Subject Parts on page 1184) to retrieve a list of all the supported subject parts.  The following are some regular expression examples:		
			Subject Part	Example	
			CN (Common Name)	This regular expression specifies that the data entered in the field must consist of some number of characters in the first portion of the field made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly ".keyexample.com":  ^[a-zA-Z0-9' \.\-]*\.keyexample\.com\$	
				The default value for the Common Name regular expression is:  + This requires entry of at least one character in the Common Name field in the enrollment pages.	
			O (Organ- ization)	This regular expression requires that the	

Name	Description					
	Name	Description	Description			
		Name	Description			
			Subject Part	Example		
				organization name entered in the field be one of "Key Example Inc", "Key Example" or "Key Example Inc.":		
				^(?:Key Example Inc Key Example Key Example, Inc\.)\$ The period in the final company name (Key Example, Inc.) needs to be escaped in the regular expression with a slash ("\") but the comma does not.		
			OU (Organ- ization Unit)	This regular expression requires that the organizational unit entered in the field be one of these four departments:  ^(?:IT HR Accounting E-Commerce)\$		
			L (City/Locality)	This regular expression requires that the city entered in the field be one of these five cities:  ^(?:Boston Chicago New York London Dallas)\$		
			ST (State/Provin- ce)	This regular expression requires that the state entered in the field be one of these eight states:  (?:Massachusetts Illinois Ne		
			C (Country)	w York Ontario Texas)  This regular expression requires that the country entered in the field be either US or CA:  ^(?:US CA)\$		

Name	Description					
	Name	Description	Description			
		Name	Description			
			Subject Part	Example		
			E (Email)	This regular expression specifies that the data entered in the field must consist of some number of characters prior to the "@" made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly "@keyexample.com":  ^[a-zA-Z0-9'_ \.\-]*@keyexample\.com\$		
			DNS (Subject Alternative Name: DNS Name)	This regular expression specifies that the data entered in the field must consist of some number of characters in the first portion of the field made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly either ".keyexample1.com" or ".keyexample2.com":  ^[a-zA-Z0-9'_\.\-]*\.		
				<pre>(?:keyexample1\.com keyexamp le2\.com)\$</pre>		
			IPv4 (Subject Alternative Name: IPv4 Address)	This regular expression specifies that the data entered in the field must be exactly "130.101." followed by anywhere between 1 and 3 numbers followed by exactly "." followed by anywhere between 1 and 3 numbers:  ^130\.101\.(?:[0-9]{1,3})\.		
				(?:[0-9]{1,3})\$ This regular expression specifies only that the IPv4 address is made up of 4 sets of		

Name	Description					
	Name	Description	Description			
		Name	Description			
			Subject Part	Example		
				between 1 and 3 numbers separated by periods:  ^(?:[0-9]{1,3}\.){3}[0-9] {1,3}\$		
			IPv6 (Subject Alternative Name: IPv6 Address)	This regular expression specifies that the data entered in the field must be made up of eight sets of between one and four numbers and/or uppercase letters separated by colons:  ^(?:[A-F0-9]{1,4}:){7}[A-F0-9]{1,4}\$		
			MAIL (Subject Alternative Name: Email)	This regular expression specifies that the data entered in the field must consist of some number of characters prior to the "@" made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly "@keyexample.com":  ^[a-zA-Z0-9'_ \.\-]*@keyexample\.com\$		
			UPN (Subject Alternative Name: User Principal Name)	This regular expression specifies that the data entered in the field must consist of some number of characters prior to the "@" made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly "@keyexample.com":  ^[a-zA-Z0-9'_ \.\-]*@keyexample\.com\$		

Name	Description			
	Name	Description		
		Name	Description	
		Error	A string specifying the error message displayed to the user when the subject part referenced in the CSR or entered for a PFX enrollment does not match the given regular expression. Note that the error message already includes a leading string with the subject part (e.g. "Common Name:" or "Invalid CN provided:" depending on the interface used). Your custom message follows this.	
	Exten- dedKeyUsages	Currently not	in use.	
	Curve	_	ating the OID of the elliptical curve algorithm configured for the ECC templates.	
Stan- daloneCAs	An array containing enrollment information for standalone certificate authorities available for enrollment for the current user. Information about the CA includes:			
	Name	Descrip	tion	
	Name	authority daloneCa	The full name of the CA, made up of the DNS hostname of the certificate authority (e.g. myca.keyexample.com) and the logical name (e.g. CorpStandaloneCA1) for a full name similar to myca.keyexample.com\\CorpStandaloneCA1.	
	RFCEnforcement	Commar In the Ke PFX enro either ch that mat is set. Th	an that sets whether certificate enrollments made through Keyfactor and for this CA must include at least one DNS SAN ( <i>true</i> ) or not ( <i>false</i> ). Explactor Command Management Portal, this causes the CN entered in collment to automatically be replicated as a SAN, which the user can mange or accept. For CSR enrollment, if the CSR does not have a SAN exches the CN, one will automatically be added to the certificate if this ais setting at the CA level applies only to standalone CAs. For CAs that polates, this setting is controlled at the template level and is ignored at evel.	
	SubscriberTerms		an that sets whether to add a checkbox on the enrollment pages to ers to agree to a custom set of terms before enrolling ( <i>true</i> ) or not	
		A	Tip: Configure a link to the custom terms using the URL to Subscriber Terms application setting. See Application Settings: Enrollment Tab in the Keyfactor Command Reference Guide for more information.	

## 2.2.14.4 GET Enrollment Available Renewal ID

The GET /Enrollment/AvailableRenewal/ID/{id} method is used to check a specific certificate by ID to determine which renewal types are supported, if any. This method or the GET /Enrollment/AvailableRenewal/Thumbprint method can be used before using the POST /Enrollment/Renew method to make a determination as to which fields need to be submitted, depending on whether one-click renewal is supported. This method returns HTTP 200 OK on a success with the supported renewal type.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: Certificates: *Read* 

At either the global or collection level. See note under CollectionId, below.

Table 262: GET Enrollment Available Renewal ID {id} Input Parameters

Name	In	Description
id	Path	Required. An integer specifying the Keyfactor Command reference ID of the certificate on which to check the renewal status.  Use the GET /Certificates method to determine the certificate ID. This information is also available in the certificate details for a certificate in the Keyfactor Command Management Portal.
CollectionId	Query	An integer specifying an optional certificate collection identifier to validate that the user executing the request has sufficient permissions to do so. If a certificate collection ID is not supplied, the user must have global permissions to complete the action. Supplying a certificate collection ID allows for a check of the user's certificate collection-level permissions to determine whether the user has sufficient permissions at a collection level to complete the action. See <i>Certificate Permissions</i> in the <i>Keyfactor Command Reference Guide</i> for more information.

Table 263: GET Enrollment Available Renewal ID {id} Response Body

Name	Description		
AvailableRenewalType	An integer indicating the supported renewal type. Possible values are:		
	Value	Description	
	0	None—renewal is not supported for this certificate.	
	1	Seeded PFX is supported. A renewal can be done if a template and certificate authority are supplied in the renewal request, but one-click renewal is not supported.	
	2	<ul> <li>One-click renewal is supported. A renewal can be done using the same template and certificate authority used in the original certificate, and a template and certificate authority do not need to be supplied in the renewal request.</li> <li>One-click renewal is only supported if either one of the following is true: <ul> <li>The certificate is located together with its private key in one or more managed certificate store(s).</li> </ul> </li> <li>The certificate was enrolled with a template that has been configured in Keyfactor Command to allow private keys to be encrypted and stored in the Keyfactor Command database. See Certificate Templates in the Keyfactor Command Reference Guide for more information.</li> </ul>	
	Tip: If	the AvailableRenewalType is 2, 1 is also supported for the certificate.	
Message		viding more details about the available renewal type result (e.g. "One click available for this certificate. Template does not have PFX enrollment	

# 2.2.14.5 GET Enrollment Available Renewal Thumbprint

The GET /Enrollment/AvailableRenewal/Thumbprint/{thumbprint} method is used to check a specific certificate by thumbprint to determine which renewal types are supported, if any. This method or the GET /Enrollment/AvailableRenewal/ID method can be used before using the POST /Enrollment/Renew method to make a determination as to which fields need to be submitted, depending on whether one-click renewal is supported. This method returns HTTP 200 OK on a success with the supported renewal type.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: Certificates: *Read* 

At either the global or collection level. See note under CollectionId, below.

Table 264: GET Enrollment Available Renewal Thumbprint {thumbprint} Input Parameters

Name	In	Description
thumbprint	Path	<b>Required</b> . The thumbprint of the certificate on which to check the renewal status.  Use the <i>GET /Certificates</i> method to determine the certificate thumbprint. This information is also available in the certificate details for a certificate in the Keyfactor Command Management Portal.
CollectionId	Query	An integer specifying an optional certificate collection identifier to validate that the user executing the request has sufficient permissions to do so. If a certificate collection ID is not supplied, the user must have global permissions to complete the action. Supplying a certificate collection ID allows for a check of the user's certificate collection-level permissions to determine whether the user has sufficient permissions at a collection level to complete the action. See <i>Certificate Permissions</i> in the <i>Keyfactor Command Reference Guide</i> for more information.

Table 265: GET Enrollment Available Renewal Thumbprint {thumbprint} Response Body

Name	Description		
AvailableRenewalType	An integer indicating the supported renewal type. Possible values are:		
	Value	Description	
	0	None—renewal is not supported for this certificate.	
	1	Seeded PFX is supported. A renewal can be done if a template and certificate authority are supplied in the renewal request, but one-click renewal is not supported.	
	2	<ul> <li>One-click renewal is supported. A renewal can be done using the same template and certificate authority used in the original certificate, and a template and certificate authority do not need to be supplied in the renewal request.</li> <li>One-click renewal is only supported if either one of the following is true: <ul> <li>The certificate is located together with its private key in one or more managed certificate store(s).</li> </ul> </li> <li>The certificate was enrolled with a template that has been configured in Keyfactor Command to allow private keys to be encrypted and stored in the Keyfactor Command database. See Certificate Templates in the Keyfactor Command Reference Guide for more information.</li> </ul>	
	Tip: If	the AvailableRenewalType is 2, 1 is also supported for the certificate.	
Message		viding more details about the available renewal type result (e.g. "One click available for this certificate. Template does not have PFX enrollment	

### 2.2.14.6 POST Enrollment CSR

The POST /Enrollment/CSR method is used to enroll for a certificate using a certificate signing request (CSR). This method returns HTTP 200 OK on a success with a message body containing a list of certificate details and any metadata that was associated with the certificate request.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: CertificateEnrollment: *EnrollCSR* 



**Tip:** Use the GET /Enrollment/CSR/Context/My method before this method to check which templates and CAs are available for enrollment for the requesting user before submitting the enrollment request.



**Note:** As of Keyfactor Command version 10, enrollment (PFX and CSR), renewal, and revocation requests all flow through Keyfactor Command workflow. This will result in no changes to the enrollment, renewal, and revocation user experience unless customizations have been added in workflow (see <a href="Workflow Definitions">Workflow Definitions</a>).

Table 266: POST Enrollment CSR Input Parameters

Name	In	Description	
CSR	Body	<b>Required</b> . The base-64 encoded CSR that will be passed in for enrollment.	
Timestamp	Body	<b>Required</b> . The current date and time. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
Template	Body	Required*. A string that sets the name of the certificate template that should be used to issue the certificate. The template short name should be used.  This field is required unless the enrollment is being done against a standalone CA.	
CertificateAuthority	Body	Required*. A string that sets the name of the certificate authority that will be used to enroll against if there is more than one available with the provided template name. The certificate authority name can either be provided in hostname\\logical name format or as just the logical name. For example:  corpca01.keyexample.com\\CorplssuingCA1 OR CorplssuingCA1  If no certificate authority is provided, one will be chosen at random from the certificate authorities available for enrollment with the provided Template.  This field is optional unless the enrollment is being done against a standalone CA, in which case it is required.	
IncludeChain	Body	A Boolean that sets whether to include the certificate chain in the response (true) or not (false). The default is <i>false</i> .	
Metadata	Body	An array of key/value pairs that set the values for the metadata fields that will be associated with the certificate once it is in Keyfactor Command. The <i>key</i> is the field name and the <i>value</i> is the value for the field. For example:	
		<pre>"Metadata": {     "AppOwnerFirstName": "William", // This is a String field.     "AppOwnerLastName": "Smith",     "AppOwnerEmailAddress": "willi- am.smith@keyexample.com",     "BusinessCritical": "true", // This is a Boolean field.     "BusinessUnit": "E-Business", // This is a Multiple Choice field with a pre-defined value.</pre>	

Name	In	Description	
		BigText field.  "SiteCode": 3, integer field.  "TicketResolutionDa Date field in yyyy-mm- }	section of the Keyfactor Command Refer-
SANs	Body	Command to use when gener	at represent the elements for Keyfactor ating the subject alternative name (SAN) by the CSR. Possible values for the key are:
		Value	Description
		rfc822	RFC 822 Name
		dns	DNS Name
		directory	Directory Name
		uri	Uniform Resource Identifier
		ip4	IP v4 Address
		ip6	IP v6 Address
		registeredid	Registered ID (an OID)
		ms_ntprincipalname	MS_NTPrincipalName (a string)
		ms_ntdsreplication	MS_NTDSReplication (a GUID)
		For example:	
		"SANs": {     "dns": [         "dnssan1.keyexam         "dnssan2.keyexam         "dnssan3.keyexam     ],     "ip4": [         "192.168.2.73"     ] }	ple.com",

Name	In	Description	
		Note: Entering SANs with this option may either append or overwrite the SANs in the CSR request depending on how the issuing CA is configured. Please be sure to check that the certificate has the correct SANs after issuance. Any SAN added automatically as a result of the RFC 2818 compliance settings (see GET Templates on page 1185) will still be added alongside anything you add here. Review the SAN Attribute Policy Handler for the Keyfactor CA Policy Module (see Installing the Keyfactor CA Policy Module Handlers in the Keyfactor Command Server Installation Guide) for more information.	
Additional Enrollment Fields	Body	An array of key/value pairs that provide values for any custom enrollment fields set on the certificate template to supply custom request attributes to the CA during the enrollment process. For example:  "AdditionalEnrollmentFields": { "CustomStringOne":  "ValueOne", "CustomMultiChoiceTwo": "ValueTwo" }  See Configuring Template Options of the Keyfactor Command Referent Guide for more information.	
x-CertificateFormat	Header	<b>Required</b> . The desired output format for the certificate. Available options are DER and PEM.	

Table 267: POST Enrollment CSR Response Data

Value	Description			
CertificateInformation	Information about the certificate that was requested. CSR information includes:			
	Value	Description		
	SerialNumber	Serial number of the certificate.		
	IssuerDN	Issuer DN of the certificate.		
	Thumbprint	Thumbprint of the certificate.		
	KeyfactorID	ID of the certificate in Keyfactor Command.		
	KeyfactorRequestID	ID of the request in Keyfactor Command.		
	Certificates	An array of certificates in the order of: end entity, intermediate CA, Root CA. Intermediate CA and root CA certificates will only be included if the request parameter <i>IncludeChain</i> was set to <i>true</i> .		
	RequestDisposition	State of the request (e.g. issued).		
	DispositionMessage	Enrollment message (e.g. issued).		
	EnrollmentContext	An internally used Keyfactor Command field.		
Metadata	An array of the custom metadata values set on the certificate. The values vary depending customization done in your environment. The information is presented in the following structure:			
	Name	Description		
	MetadataFieldTypeName	The name of the metadata field in Keyfactor Command.		
	Value	The value of the metadata.		
	See the <i>Certificate Metadata</i> section of the <i>Keyfactor Command Reference Guide</i> for more information.			

## 2.2.14.7 POST Enrollment PFX

The POST /Enrollment/PFX method is used to enroll for a certificate by supplying data in the desired fields. This method returns HTTP 200 OK on a success with a message body containing a list of certificate details and any metadata that was associated with the certificate request.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: CertificateEnrollment: *EnrollPFX* 

Global or container-level schedule permissions for certificate stores are needed to install a certificate generated with this method into a certificate store (see the <u>x-CertificateFormat on page 616</u> parameter) using the POST /Enrollment/PFX/Deploy method (see <u>POST Enrollment PFX Deploy on page 619</u>) or POST /Enrollment/PFX/Replace method (see POST Enrollment PFX Replace on page 625).



**Tip:** Use the GET /Enrollment/PFX/Context/My method before this method to check which templates and CAs are available for enrollment for the requesting user before submitting the enrollment request.



**Note:** As of Keyfactor Command version 10, enrollment (PFX and CSR), renewal, and revocation requests all flow through Keyfactor Command workflow. This will result in no changes to the enrollment, renewal, and revocation user experience unless customizations have been added in workflow (see <a href="Workflow Definitions">Workflow Definitions</a>).

This method has two available versions. Keyfactor recommends using the newer method when possible. For more information about versioning, see Versioning on page 6.

#### Version 2

Version 2 of the POST /Enrollment/PFX method redesigns how enrollment flow works to handle require approval functionality in a Keyfactor Command workflow with support for delivery into certificate stores. Users who are planning to use require approval workflow functionality *and* deliver enrolled certificates into certificate stores must use version 2 of this endpoint.



Note: The PopulateMissingValuesFromAD parameter has been removed from the version 2 endpoint.

Table 268: POST Enrollment PFX v2 Input Parameters

Name	In	Description			
Stores			An object containing a comma delimited set of arrays indicating the certificate stores to which the certificate should be distributed. Store details include:		
		Name	Description		
	StoreId	An array of GUIDs indicating the certificate store(s) to which the certificate should be deployed.  Use the GET /CertificateStores method (see GET Certificate Stores on page 377) with a query of "Approved eq true" to retrieve a list of all your approved certificate stores to determine the GUID(s) of the store(s).			
				Alias	The alias of the certificate upon entry into the store.  The format of and requirement for this varies depending on the certificate store type and whether the <i>Overwrite</i> flag is selected. See <a href="PFX Enrollment">PFX Enrollment</a> in the <i>Keyfactor Command Reference Guide</i> for more information.
			Overwrite	A Boolean that sets whether a certificate in the store with the <i>Alias</i> provided should be overwritten with the new certificate (true) or not (false). The default is <i>false</i> . Use the <i>GET /Certificates/Locations/{id}</i> method (see <i>GET Certificates Locations ID on page 216</i> ) to retrieve a list of the locations an existing certificate is in to determine the alias used for the certificate in the certificate store.	
	Properties	An array of key/value pairs for the unique parameters defined for the certificate store type that need to be populated for the certificate. The <i>key</i> is the name of the specific parameter from the certificate store type definition as returned in the JobProperties on the store type using the <i>GET CertificateStoreTypes</i> method and the <i>value</i> is the value that should be set for that parameter on the certificate in the certificate store. For example, for NetScaler, the key name that is optionally used to associate the certificate with a virtual server is <i>NetscalerVserver</i> and is returned by <i>GET CertificateStoreTypes</i> like so:  "JobProperties": [ "NetscalerVserver" ]			

Name	In	Description		
		Name Description		
		It can be seen in the Keyfactor Command Manage Portal when editing the certificate store type in th field for Management Job Custom Fields.  The setting is referenced using the following form:  "Properties": {"NetscalerVserver": "MyVirtualServame"}	at:	
		Note: The only built-in certificate store ty that makes use of properties that can be so on a certificate-by-certificate basis in the sis NetScaler. You may have custom certificate types that make use of this functions	set store cate	
CustomFriendlyName	Body	Required*. A string that sets a custom friendly name for the certificate.  This field is required if the Require Custom Friendly Name application setting is set to true (the default is false). See Application Settings: Enrollment Tab in the Keyfactor Command Reference Guide for more information.		
Password	Body	Required. A string that sets the password used to encrypt the contents of the PFX file. The minimum password length is controlled by the <i>Password Length</i> application setting. The default is 12. See <u>Application Settings:</u> Enrollment Tab in the <i>Keyfactor Command Reference Guide</i> for more information.		
Subject	Body	Required*. A string containing the subject name using X.500 format. For example:  "Subject": "CN=websrvr14.keyexample.com,OU=IT,O=\"Key Example, Inc.\",L=Independence,ST=OH,C=US"  This field is required if the Common Name Regular Expression application setting is set to the default value of .+. See Application Settings: Enrollment  Tab in the Keyfactor Command Reference Guide for more information.		
IncludeChain	Body	A Boolean that sets whether to include the certificate chain in the response (true) or not (false). The default is <i>true</i> .		
RenewalCertificateId	Body	An integer that sets the ID of the certificate to be renewed when the method is called on a certificate renewal.  The RenewalCertificateId parameter is used in conjunction with InstallIntoExistingCertificateStores parameter to make the determination as to		

Name	In	Description
		distribution of the certificate to certificate stores. If <i>InstallIntoExistingCertificateStores</i> is <i>true</i> , the certificate will be distributed to certificate stores that the certificate identified in <i>RenewalCertificateId</i> is found in.
CertificateAuthority	Body	Required*. A string that sets the name of the certificate authority that will be used to enroll against if there is more than one available with the provided template name. The certificate authority name can either be provided in hostname\\logical name format or as just the logical name. For example:  corpca01.keyexample.com\\CorplssuingCA1 OR CorplssuingCA1  If no certificate authority is provided, one will be chosen at random from the certificate authorities available for enrollment with the provided Template.  This field is optional unless the enrollment is being done against a standalone CA, in which case it is required.
Metadata	Body	An array of key/value pairs that set the values for the metadata fields that will be associated with the certificate once it is in Keyfactor Command. The key is the field name and the value is the value for the field. For example:  "Metadata": {     "AppOwnerFirstName": "William", // This is a String field.     "AppOwnerLastName": "Smith",     "AppOwnerEmailAddress": "william.smith@keyexample.com",     "BusinessCritical": "true", // This is a Boolean field.     "BusinessUnit": "E-Business", // This is a Multiple Choice field with a pre-defined value.     "Notes": "Here are some notes.", // This is a BigText field.     "SiteCode": 3, // This is an integer field.     "TicketResolutionDate": "2021-07-23" // This is a Date field in yyyy-mm-dd format. }  See Certificate Metadata in the Keyfactor Command Reference Guide for more information.
Timestamp	Body	The current date and time. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
Template	Body	<b>Required</b> *. A string that sets the name of the certificate template that

Name	In	Description		
		should be used to issue the certificate. The template short name should be used.  This field is <b>required</b> unless the enrollment is being done against a standalone CA.		
SANs	Body	An array of key/value pairs that represent the elements for Keyfactor Command to use when generating the subject alternative name (SAN) for the certificate requested by the CSR. Possible values for the key are:		
		Value	Description	
		rfc822	RFC 822 Name	
		dns	DNS Name	
		directory	Directory Name	
		uri	Uniform Resource Identifier	
		ip4	IP v4 Address	
		ip6	IP v6 Address	
		registeredid	Registered ID (an OID)	
		ms_ntprincipalname	MS_NTPrincipalName (a string)	
		ms_ntdsreplication	MS_NTDSReplication (a GUID)	
		For example:		
		"SANs": {     "dns": [         "dnssan1.keyexample.com",         "dnssan2.keyexample.com",         "dnssan3.keyexample.com" ],     "ip4": [         "192.168.2.73" ]		
InstallIn- toExistingCertificateStores	Body	A Boolean that sets whether to deploy the certificate to certificate stores (true) or not (false). The default is <i>true</i> .  The <i>RenewalCertificateId</i> parameter is used in conjunction with <i>InstallIntoExistingCertificateStores</i> parameter to make the determination as to		

Name	In	Description
		distribution of the certificate to certificate stores. If <i>InstallIntoExistingCertificateStores</i> is <i>true</i> , the certificate will be distributed to certificate stores that the certificate identified in <i>RenewalCertificateId</i> is found in.
Additional Enrollment Fields	Body	An array of key/value pairs that provide values for any custom enrollment fields set on the certificate template to supply custom request attributes to the CA during the enrollment process. For example:  "AdditionalEnrollmentFields": { "CustomStringOne":  "MyValue", "CustomMultiChoiceOne": "ValueTwo" }  See Configuring Template Options in the Keyfactor Command Reference Guide for more information.
x-CertificateFormat	Header	<b>Required</b> . The desired output format for the certificate. Available options are PFX, Zip, and Store. If Store is selected, no certificate blob will be returned in the response. The Store option is designed to be used when pushing a newly obtained PFX certificate to a certificate store (see <a href="POST_Enrollment PFX Deploy on page 619">POST_Enrollment PFX Deploy on page 619</a> ).

Table 269: POST Enrollment PFX v2 Response Data

Value	Description				
SuccessfulStores	An object containing a comma delimited list of certificate stores, referenced by certificate store GUID, to which the certificate was successfully scheduled for deployment.				
CertificateInformation	Information about the certif	Information about the certificate that was requested. Certificate information includes:			
	Value	Description			
	SerialNumber	A string indicating the serial number of the certificate.			
	IssuerDN	A string indicating the issuer DN of the certificate.			
	Thumbprint	A string indicating the thumbprint of the certificate.			
	KeyfactorID	An integer indicating the Keyfactor Command reference ID of the certificate.			
	PKCS12Blob	A string containing the base-64-encoded representation of the certificate in Zip or PFX format with the optional certificate chain. The string will need to be base-64 decoded for both Zip and PFX. This can be accomplished in a number of ways. For example, using PowerShell:  \$b64 = Get-Content 'C:\path\to\source\file' \$targetFile = 'C:\path\to\target\file'  \$bytes = [Convert]::FromBase64String(\$b64) [IO.File]::WriteAllBytes(\$targetFile, \$bytes)  Note: No value is returned for the PKCS12Blob if you select a certificate format of <i>Store</i> in the header. The <i>Store</i> option is designed to be used when pushing a newly obtained PFX certificate to a certificate store (see POST Enrollment PFX Deploy on page 619).			
	Password	An internally used Keyfactor Command field.			
	KeyfactorRequestId	An integer indicating the Keyfactor Command reference ID of the certificate request.			
	RequestDisposition	A string indicating the state of the request (e.g. issued).			
	DispositionMessage	A string providing a message about the enrollment (e.g. The			

Value	Description			
	Value	Description		
		private key was successfully retained.).		
	EnrollmentContext	An internally used Keyfactor Command field.		
Metadata	·	idata values set on the certificate. The values vary depending on environment. The information is presented in the following		
	Name	Description		
	MetadataFieldTypeName	The name of the metadata field in Keyfactor Command.		
	Value	The value of the metadata.		
	See <u>Certificate Metadata</u> in t	the Keyfactor Command Reference Guide for more information.		

## Version 1

Version 1 of the POST /Enrollment/PFX method includes the same capabilities as version 2 except when used in conjunction with Keyfactor Command workflows that require approval with an intended end goal of delivering the resulting certificate into a certificate store. In this specific case, version 2 must be used.

Table 270: POST Enrollment PFX v1 Input Parameters

Name	In	Description
CustomFriendlyName	Body	Required*. A string that sets a custom friendly name for the certificate.  This field is required if the Require Custom Friendly Name application setting is set to true (the default is false). See Application Settings: Enrollment Tab in the Keyfactor Command Reference Guide for more information.
Password	Body	<b>Required</b> . A string that sets the password used to encrypt the contents of the PFX file. The minimum password length is controlled by the <i>Password Length</i> application setting. The default is <i>12</i> . See <u>Application Settings: Enrollment Tab</u> in the <i>Keyfactor Command Reference Guide</i> for more information.
PopulateMissingValuesFromAD	Body	A Boolean that sets whether to populate the information in the subject from Active Directory (true) or not (false). The default is <i>false</i> .
Subject	Body	Required*. A string containing the subject name using X.500 format. For example:  "Subject": "CN=we- ebsrvr14.keyexample.com,OU=IT,O=\"Key Example, Inc.\",L=Independence,ST=OH,C=US"  This field is required if the Common Name Regular Expression application setting is set to the default value of .+. See Application Settings: Enrollment Tab in the Keyfactor Command Reference Guide for more information.
IncludeChain	Body	A Boolean that sets whether to include the certificate chain in the response (true) or not (false). The default is <i>true</i> .
RenewalCertificateId	Body	An integer that sets the ID of the certificate to be renewed when the method is called on a certificate renewal.
CertificateAuthority	Body	Required*. A string that sets the name of the certificate authority that will be used to enroll against if there is more than one available with the provided template name. The certificate authority name can either be provided in hostname\logical name format or as just the logical name. For example:  corpca01.keyexample.com\\CorplssuingCA1 OR CorplssuingCA1  If no certificate authority is provided, one will be chosen at random from the certificate authorities available for enrollment with the provided Template.

Name	In	Description
		This field is optional unless the enrollment is being done against a standalone CA, in which case it is <b>required</b> .
Timestamp	Body	The current date and time. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
Template	Body	Required*. A string that sets the name of the certificate template that should be used to issue the certificate. The template short name should be used.  This field is required unless the enrollment is being done against a standalone CA.
Metadata	Body	An array of key/value pairs that set the values for the metadata fields that will be associated with the certificate once it is in Keyfactor Command. The <i>key</i> is the field name and the <i>value</i> is the value for the field. For example:
		<pre>"Metadata": {     "AppOwnerFirstName": "William", // This is a String field.     "AppOwnerLastName": "Smith",     "AppOwnerEmailAddress": "willi- am.smith@keyexample.com",     "BusinessCritical": "true", // This is a Boolean field.     "BusinessUnit": "E-Business", // This is a Multiple Choice field with a pre-defined value.     "Notes": "Here are some notes.", // This is a BigText field.     "SiteCode": 3, // This is an integer field.     "TicketResolutionDate": "2021-07-23" // This is a Date field in yyyy-mm-dd format. }</pre>
		See <u>Certificate Metadata</u> in the <i>Keyfactor Command Reference Guide</i> for more information.
SANs	Body	An array of key/value pairs that represent the elements for Keyfactor Command to use when generating the subject alternative name (SAN) for the certificate requested by the CSR. Possible values for the key are:

Name	In	Description	
		Value	Description
		rfc822	RFC 822 Name
		dns	DNS Name
		directory	Directory Name
		uri	Uniform Resource Identifier
		ip4	IP v4 Address
		ip6	IP v6 Address
		registeredid	Registered ID (an OID)
		ms_ntprincipalname	MS_NTPrincipalName (a string)
		ms_ntdsreplication	MS_NTDSReplication (a GUID)
		For example:	
		"SANs": {     "dns": [         "dnssan1.keyexa         "dnssan2.keyexa         "dnssan3.keyexa     ],     "ip4": [         "192.168.2.73"     ] }	mple.com",
Additional Enrollment Fields	Body	enrollment fields set on the request attributes to the CA example:  "AdditionalEnrollmer" "MyValue", "Custom	chat provide values for any custom certificate template to supply custom during the enrollment process. For intFields": { "CustomStringOne": MultiChoiceOne": "ValueTwo" } ptions in the Keyfactor Command Referation.
x-CertificateFormat	Header	options are PFX, Zip, and Sto blob will be returned in the to be used when pushing a r	ut format for the certificate. Available ore. If Store is selected, no certificate response. The Store option is designed newly obtained PFX certificate to a certificate to PFX Deploy on page 619).

Table 271: POST Enrollment PFX v1 Response Data

Value	Description			
CertificateInformation	Information about the certificate that was requested. Certificate information includes:			
	Value	Description		
	SerialNumber	Serial number of the certificate.		
	IssuerDN	Issuer DN of the certificate.		
	Thumbprint	Thumbprint of the certificate.		
	KeyfactorID	ID of the certificate in Keyfactor Command.		
	KeyfactorRequestID	ID of the request in Keyfactor Command.		
	PKCS12Blob	The base-64-encoded representation of the certificate in Zip or PFX format with the optional certificate chain. The string will need to be base-64 decoded for both Zip and PFX. This can be accomplished in a number of ways. For example, using PowerShell:  \$b64 = Get-Content 'C:\path\to\source\file' \$targetFile = 'C:\path\to\target\file'  \$bytes = [Convert]::FromBase64String(\$b64) [IO.File]::WriteAllBytes(\$targetFile, \$bytes)  Note: No value is returned for the PKCS12Blob if you select a certificate format of <i>Store</i> in the header. The <i>Store</i> option is designed to be used when pushing a newly obtained PFX certificate to a certificate store (see POST Enrollment PFX Deploy on page 619).		
	RequestDisposition	State of the request (e.g. issued).		
	DispositionMessage	Enrollment message (e.g. The private key was successfully retained.).		
	EnrollmentContext	An internally used Keyfactor Command field.		
	Password	An internally used Keyfactor Command field.		
Metadata	An array of the custom metadata values set on the certificate. The values vary depending or customization done in your environment. The information is presented in the following structure:			

Value	Description		
	Name	Description	
	MetadataFieldTypeName	The name of the metadata field in Keyfactor Command.	
	Value	The value of the metadata.	
	See <u>Certificate Metadata</u> in the Ke	eyfactor Command Reference Guide for more information.	

## 2.2.14.8 POST Enrollment CSR Parse

The POST /Enrollment/CSR/Parse method takes a CSR in the body, parses it, and returns all elements that were found in the CSR. This method returns HTTP 200 OK on a success with the parsed CSR contents.

Table 272: POST Enrollment CSR Parse Input Parameters

Name	In	Description
CSR	Body	Required. Base-64-encoded CSR with the Begin and End Certificate Request tags.

Table 273: POST Enrollment CSR Parse Response Data

Name	Description			
(CSR Contents)	An array containing key/value pairs representing all the elements in the CSR. Possible values include:			
contents)	Name	Description		
	Key Length	An integer indicating the desired key size of the certificate.		
	Кеу Туре	A string indicating the desired key encryption of the certificate.		
	CN	The common name of the certificate.		
	0	The organization of the certificate.		
	OU	The organizational unit of the certificate.		
	L	The city of the certificate.		
	ST	The state of the certificate.		
	С	The country (two characters) of the certificate.		
	E	The email address of the certificate.		
	DNS Name	A SAN value containing a DNS name.		
	IP Address	A SAN value containing an IP v4 or IP v6 address.		
	RFC822 Name	A SAN value containing an email message.		
	URL	A SAN value containing a uniform resource identifier.		
	Directory Name	A SAN value containing a directory name.		
	Registered ID	A SAN value containing a registered ID.		
	Other name:Principal Name	A SAN value containing a user principal name (UPN) value.		
	Other name:DS Object Guid	A SAN value containing the MS_NTDSReplication value.		
		s cannot be added to a CSR generated within Keyfactor Command found in CSRs generated outside Keyfactor Command.		

# 2.2.14.9 POST Enrollment PFX Deploy

The POST /Enrollment/PFX/Deploy method is used to put a certificate into a certificate store. It is intended to be used immediately after using the POST /Enrollment/PFX method to enroll for a PFX using the *Store* value for the *x*-

certificate format header (see <u>POST Enrollment PFX on page 605</u>) or the POST /Enrollment/Renew method to renew a certificate already in a certificate store. This method returns HTTP 200 OK on a success with a message body containing the failed and succeeded stores.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature:

CertificateStoreManagement: *Schedule* CertificateEnrollment: *EnrollPFX* 

Permissions for certificate stores can be set at either the global or certificate store container level. See *Container Permissions* in the *Keyfactor Command Reference Guide* for more information about global vs container permissions.



**Tip:** The POST /Enrollment/PFX/Deploy method must be used within 5 minutes of acquiring a certificate with the POST /Enrollment/PFX or POST /Enrollment/Renew method as the same user who executed the certificate request. After 5 minutes, the temporary staging data needed in order to deploy the certificate is automatically cleared and is no longer available for deployment.

Table 274: POST Enrollment PFX Deploy Input Parameters

Name	Туре	Description			
Stores	Body	deployed with add	<b>Required</b> *. An array indicating the certificate stores to which the certificate should be deployed with additional properties as needed based on the store type and whether an existing certificate is being overwritten with the new certificate. Store parameters are:		
		Name	Description		
		StoreId	An array of GUIDs indicating the certificate store(s) to which the certificate should be deployed.  Use the GET /CertificateStores method (see GET Certificate Stores on page 377) with a query of "Approved -eq true" to retrieve a list of all your approved certificate stores to determine the GUID(s) of the store(s).		
		Alias	The alias of the certificate upon entry into the store. The format of and requirement for this varies depending on the certificate store type and whether the <i>Overwrite</i> flag is selected. See the <a href="PFX Enrollment">PFX Enrollment</a> section of the <i>Keyfactor Command Reference Guide</i> for more information.		
		Overwrite	A Boolean that sets whether a certificate in the store with the <i>Alias</i> provided should be overwritten with the new certificate (true) or not (false). The default is <i>false</i> .  Use the <i>GET /Certificates/Locations/{id}</i> method (see <u>GET Certificates Locations ID on page 216</u> ) to retrieve a list of the locations an existing certificate is in to determine the alias used for the certificate in the certificate store.		
	Properties	An array of key/value pairs for the unique parameters defined for the certificate store type that need to be populated for the certificate. The <i>key</i> is the name of the specific parameter from the certificate store type definition as returned in the JobProperties on the store type using the <i>GET CertificateStoreTypes</i> method and the <i>value</i> is the value that should be set for that parameter on the certificate in the certificate store. For example, for NetScaler, the key name that is optionally used to associate the certificate with a virtual server is <i>NetscalerVserver</i> and is returned by <i>GET CertificateStoreTypes</i> like so:  "JobProperties": ["NetscalerVserver"]  It can be seen in the Keyfactor Command Management Portal when editing the certificate store type in the field for <i>Management Job Custom Fields</i> .			

Name	Туре	Description		
		Name	Description	
			The setting is referenced using the following format:  "Properties": {"Nets- calerVserver":"MyVirtualServerName"}  Note: The only built-in certificate store type that makes use of properties that can be set on a certificate-by-certificate basis in the store is NetScaler. You may have custom certificate store types that make use of this functionality.	
		This replaces the St version 9.4.	coresIDs and StoreTypes parameters as of Keyfactor Command	
Password	Body	<b>Required</b> *. A string with a password used to secure the certificate in the certificate store. This field is <b>required</b> for store types that require an entry password, such as PEM stores.		
CertificateId	Body		eger for the certificate that needs to be deployed. This is returned in e POST /Enrollment/PFX or POST /Enrollment/Renew request as the	
		ficate is issi be provided manager al KeyfactorR	enrollments that do not require manager approval (where the certi- ued immediately), the <i>Certificateld</i> is <b>required</b> . The <i>Requestld</i> may d but is not required in this case. For enrollments that do require approval (where the certificate is not issued immediately), only the equestld will be returned on the enrollment and the <i>Requestld</i> is an deployment.	
RequestId	Body	Required*. The integer of the request ID for the certificate that needs to be deployed. This is returned in the response to the POST /Enrollment/PFX or POST /Enrollment/Renew request as the KeyfactorRequestId.  See the note under CertificateId regarding when this field is required and when it is not.		
JobTime	Body	The date and time when the certificate should be deployed. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z). Dates in the past will cause a management job to be created to run immediately. Dates in the future will result in a management job set to run in the future. The default is to create a management job that runs immediately.		
Storelds	Body	An array of the certificate store GUIDs for the stores to which the certificate should be added.		

Name	Туре	Description			
		The <b>StoreIds</b> parameter is obsolete as of Keyfactor Command version 9.4 and has been replaced by the <b>Stores</b> parameter. It is still supported for backward compatibility, but no longer required.			
StoreTypes	StoreTypes Body	An array of store types used with additional properties as needed based on the store type and whether an existing certificate is being overwritten with the new certificate. The <b>StoreTypes</b> parameter is obsolete as of Keyfactor Command version 9.4 and has been replaced by the <b>Stores</b> parameter. It is still supported for backward compatibility, but is no longer required.  Store type parameters are:			
		Name	Name Description		
		StoreTypeId	The type of certificate store the certificate is being deployed to. The possible values are:		
			Value	Description	
			0	Java Keystore	
			2	PEM File	
			3	F5 SSL Profiles	
			4	IIS Roots	
			5	NetScaler	
			6	IIS Personal	
			7	F5 Web Server	
			8	IIS Revoked	
			9	F5 Web Server REST	
			10	F5 SSL Profiles REST	
			11	F5 CA Bundles REST	
			100	Amazon Web Services	

Name	Туре	Description				
		Name	Description			
			Value	Description		
			101	File Transfer Protocol		
			1xx	User-defined certificate stores will be given a type ID over 101.		
		Alias	format of and r certificate store selected. See th	The alias of the certificate upon entry into the store. The format of and requirement for this varies depending on the certificate store type and whether the <i>Overwrite</i> flag is selected. See the <a href="PFX Enrollment">PFX Enrollment</a> section of the <i>Keyfactor Command Reference Guide</i> for more information.		
		Overwrite	A Boolean that sets whether a certificate in the store with the <i>Alias</i> provided should be overwritten with the new certificate (true) or not (false). The default is <i>false</i> .  Use the <i>GET /Certificates/Locations/{id}</i> method (see <u>GET Certificates Locations ID on page 216</u> ) to retrieve a list of the locations an existing certificate is in to determine the alias used for the certificate in the certificate store.			
		Properties	for the certificate certificate. The the certificate series on the st method and the parameter on the example, for Not associate the country of the setting the ment Job Custo The setting is resulted.	Avalue pairs for the unique parameters defined ate store type that need to be populated for the key is the name of the specific parameter from store type definition as returned in the JobProporter type using the GET CertificateStoreTypes evalue is the value that should be set for that the certificate in the certificate store. For etScaler, the key name that is optionally used to ertificate with a virtual server is NetscalerVserver by GET CertificateStoreTypes like so: erties": ["NetscalerVserver"] in the Keyfactor Command Management Portal ne certificate store type in the field for Management Fields.  Deferenced using the following format:  Deferenced using the following format:  Deferenced using the following format:		

Name	Туре	Description	
		Name	Description
			makes use of properties that can be set on a certificate-by-certificate basis in the store is NetScaler. You may have custom certificate store types that make use of this functionality.

Table 275: POST Enrollment PFX Deploy Response Data

Name	Description
SuccessfulStores	An array of GUIDs for the certificates stores for which management jobs to deploy the certificate were successfully created.
	Note: Successful creation of a management job to deploy a certificate to a certificate store does not necessarily mean that a certificate will successfully be deployed to the store. A management job may fail for any number of reasons (e.g. permissions on the store). Use the GET /Certificates/{id} method with includeLocations=true to confirm that the certificate has successfully been deployed to the target store(s). The locations won't appear in the certificate record until after a certificate store inventory has been completed for each store.
FailedStores	An array of GUIDs for the certificates stores for which management jobs to deploy the certificate could not be created.

## 2.2.14.10 POST Enrollment PFX Replace

The POST /Enrollment/PFX/Replace method is used to replace a certificate in a certificate store. It is intended to be used immediately after using the POST /Enrollment/PFX method to enroll for a PFX using the *Store* value for the *x-certificateformat* header (see POST Enrollment PFX on page 605) or the POST /Enrollment/Renew method to renew a certificate already in a certificate store. This method returns HTTP 200 OK on a success with a message body containing the failed and succeeded stores.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: CertificateStoreManagement: *Schedule* CertificateEnrollment: *EnrollPFX* 

Permissions for certificate stores can be set at either the global or certificate store container level. See *Container Permissions* in the *Keyfactor Command Reference Guide* for more information about global vs container permissions.



**Note:** You could achieve the same end using the *POST /Enrollment/PFX/Deploy* method, but in that case you would need to provide the certificate store GUID(s), the alias of the current certificate in the certificate store(s), the certificate store type(s), and set the overwrite flag to true (as well as the certificate ID of the new certificate). To achieve a replacement with the *POST /Enrollment/PFX/Replace* method you only need to provide the certificate IDs of the certificate being replaced and the new certificate. All the rest of the work is done for you. The certificate will be replaced in all locations in which the certificate is found. If you want to replace the certificate in only some of the locations in which it is found, you will need to use the *POST /Enrollment/PFX/Deploy* method (see <u>POST Enrollment PFX Deploy on page 619</u>).



**Tip:** The *POST /Enrollment/PFX/Replace* method must be used within 5 minutes of acquiring a certificate with the *POST /Enrollment/PFX* or POST /Enrollment/Renew method as the same user who executed the certificate request. After 5 minutes, the temporary staging data needed in order to deploy the certificate is automatically cleared and is no longer available for deployment.

Table 276: POST Enrollment PFX Replace Input Parameters

Name	In	Description
ExistingCertificateId	Body	Required. The integer of the certificate that will be replaced that is already in the store(s). A management job will be created to replace the certificate in all stores in which it is found.  Use the GET /Certificates method to determine the certificate ID. This information is also available in the certificate details for a certificate in the Keyfactor Command Management Portal.
CertificateId	Body	Required*. The integer for the certificate that needs to be deployed. This is returned in the response to the POST /Enrollment/PFX request.  Either the CertificateId or the RequestId is required but not both.
RequestId	Body	<b>Required</b> *. The integer of the request ID for the certificate that needs to be deployed. This is returned in the response to the POST /Enrollment/PFX request. Either the <i>CertificateId</i> or the <i>RequestId</i> is <b>required</b> but not both.
Password	Body	Required*. A string with a password used to secure the certificate in the certificate store.  This field is required for store types that require an entry password, such as PEM stores.
JobTime	Body	The date and time when the certificate should be deployed. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z). Dates in the past will cause a management job to be created to run immediately. Dates in the future will result in a management job set to run in the future. The default is to create a management job that runs immediately.

Table 277: POST Enrollment PFX Replace Response Data

Name	Description
SuccessfulStores	An array of GUIDs for the certificates stores for which management jobs to deploy the certificate were successfully created.
	Note: Successful creation of a management job to deploy a certificate to a certificate store does not necessarily mean that a certificate will successfully be deployed to the store. A management job may fail for any number of reasons (e.g. permissions on the store). Use the GET /Certificates/{id} method with includeLocations=true to confirm that the certificate has successfully been deployed to the target store(s). The locations won't appear in the certificate record until after a certificate store inventory has been completed for each store.
FailedStores	An array of GUIDs for the certificates stores for which management jobs to deploy the certificate could not be created.

#### 2.2.14.11 POST Enrollment Renew

The POST /Enrollment/Renew method is used to enroll for a certificate renewal for a certificate that exists in Keyfactor Command. This method returns HTTP 200 OK on a success with details of the new certificate. For certificates in a certificates store, this method does not automatically deploy the new certificate to the certificate store. In this case, the renew request should be followed by a call to either the POST /Enrollment/PFX/Deploy method or POST /Enrollment/PFX/Replace method to deploy the new certificate to the certificate store.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: Certificates: *Read* 

CertificateEnrollment: EnrollPFX

Global or container-level schedule permissions for certificate stores are needed to install a certificate generated with this method into a certificate store using the POST /Enrollment/PFX/Deploy method (see POST Enrollment PFX Deploy on page 619) or POST /Enrollment/PFX/Replace method (see POST Enrollment PFX Replace on page 625).



**Note:** As of Keyfactor Command version 10, enrollment (PFX and CSR), renewal, and revocation requests all flow through Keyfactor Command workflow. This will result in no changes to the enrollment, renewal, and revocation user experience unless customizations have been added in workflow (see <u>Workflow Definitions</u>).

Table 278: POST Enrollment Renew Input Parameters

Name	In	Description
CertificateId	Body	Required*. The integer for the certificate in Keyfactor Command that needs to be renewed.  Either the <i>CertificateId</i> or the <i>Thumbprint</i> is required but not both.
Thumbprint	Body	Required*. The thumbprint for the certificate that needs to be renewed.  Either the <i>CertificateId</i> or the <i>Thumbprint</i> is required but not both.
Timestamp	Body	<b>Required</b> . The current date and time. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
CertificateAuthority	Body	Required*. A string that sets the name of the certificate authority that will be used to enroll against. The certificate authority name should be provided in host-name\\logical name format. For example:  corpca01.keyexample.com\\CorplssuingCA1  This field is required if one-click renewal is not supported for the certificate (see
		GET Enrollment Available Renewal ID on page 597 or GET Enrollment Available Renewal Thumbprint on page 598).
Template	Body	Required*. A string that sets the name of the certificate template that should be used to issue the certificate. The template short name should be used.  This field is required if one-click renewal is not supported for the certificate (see GET Enrollment Available Renewal ID on page 597 or GET Enrollment Available Renewal Thumbprint on page 598).

Table 279: POST Enrollment Renew Response Data

Name	Description
KeyfactorID	ID of the certificate in Keyfactor Command.
KeyfactorRequestID	ID of the request in Keyfactor Command.
Thumbprint	Thumbprint of the certificate.
SerialNumber	Serial number of the certificate.
IssuerDN	Issuer DN of the certificate.
RequestDisposition	State of the request (e.g. issued).
DispositionMessage	Enrollment message (e.g. The private key was successfully retained.).
Password	A password generated for convenience for use on installation to a certificate store. This password may be used when deploying the certificate to a certificate store using the POST /Enrollment/Deploy method, though an alternate password may be used. The passwords do not need to match.

## 2.2.15 License

The License component of the Keyfactor API is primarily intended to view the current license through the API with the GET /License Method.

Table 280: License Endpoint

Endpoint	Method	Description	Link
/	GET	Returns the current license.	GET License below

## 2.2.15.1 GET License

The GET /License method is used to view the current license. This method returns HTTP 200 OK on a success with the license details. This method has no input parameters. For more information regarding licensing, see the <u>Licensing</u> section of the *Keyfactor Command Reference Guide*.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: SystemSettings: *Read* 

Table 281: GET License Response Data

Name	Description				
KeyfactorVersion	A string indicating the Keyfactor Command version number in the format: majorversion.incrementalversion.patchnumber				
LicenseData	An object contain	An object containing your Keyfactor customer information. License data details are:			
	Name	Description			
	Licenseld	A string indica	ting the internal reference GUID of your Keyfactor license.		
	Customer	An object cont	aining identifying information about your organization.		
		Name	Description		
		Name	A string containing your company name as per your Keyfactor account.		
		Id	An integer containing your Keyfactor account number.		
IssuedDate	A string indicating the valid issue date of the license, in UTC.				
ExpirationDate	A string indicating the valid expiration date of the license, in UTC.				
LicensedProducts	An array containi and feature deta		roducts and features included in the license. License product		
	Name		Description		
	ProductId		A string indicating the Keyfactor Command product GUID for the product(s) included in the license.		
	DisplayName		A string indicating the name of the licensed product. For Keyfactor Command, this is "Certificate Management System".		
	MajorRev		A string indicating the valid major release version of the license.		
	MinorRev		A string indicating the valid incremental release version of the license.		

	Name	Description	
	LicensedFeatures	An array containing t	he Keyfactor Command features e.
		Name	Description
		FeatureID	A string indicating the ID code of feature.
		DisplayName	A string indicating the name of the feature as displayed on the license page in the Management Portal.
		Enabled	A Boolean that indicates whether the feature is enabled (true) or not (false).
		Quantity	An integer indicating one of:  • How many of the elements you are licensed for.  • For those features which have no licensing limits, null.  Unlimited is indicated by 999999999.
		ExpirationDate	This field is unused and will always return <i>null</i> .

# 2.2.16 MacEnrollment

The MacEnrollment component of the Keyfactor API includes methods to edit and retrieve the configuration for Mac auto-enrollment.

Table 282: MacEnrollment Endpoints

Endpoint	Method	Description	Link
/	GET	Returns the current Mac auto-enrollment configuration.	GET MacEnrollment below
1	PUTT	Updates the Mac auto-enrollment configuration.	PUT MacEnrollment on the next page

#### 2.2.16.1 GET MacEnrollment

The GET /MacEnrollment method is used to retrieve details for the Mac Auto-Enrollment configuration. This method returns HTTP 200 OK on a success with the Mac Auto-Enrollment configuration details. This method has no input parameters.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: SystemSettings: *Read* 

Table 283: GET MacEnrollment Response Data

Name	Description
Id	An integer indicating the Keyfactor Command referenced ID of the Mac auto-enrollment configuration.
Enabled	An Boolean indicating whether Mac auto-enrollment is configured in the environment (true) or not (false).
Interval	An integer indicating the frequency with which the Mac auto-enrollment agent should check to see if there are new certificates for which to enroll.
UseMetadata	A Boolean indicating whether to automatically associate data in a custom metadata field with an auto-enrolled Mac certificate (true) or not (false).  See Certificate Metadata in the Keyfactor Command Reference Guide for more information about metadata fields.
MetadataField	A string indicating the name of the metadata field to populate for the certificate, if <i>UseMetadata</i> is <i>true</i> .
MetadataValue	A string indicating the value to populate for the metadata field, if <i>UseMetadata</i> is <i>true</i> . This may be either a static value (e.g. a fixed string that indicates this certificate was acquired as a result of an auto-enrollment on a Mac), or a variable retrieved from the Mac. In the current version of the agent, only the Mac serial number is available.

## 2.2.16.2 PUT MacEnrollment

The PUT /MacEnrollment method is used to update the existing Mac Auto-Enrollment configuration. This method returns HTTP 200 OK on a success with the Mac Auto-Enrollment configuration details.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: SystemSettings: *Modify* 



Warning: Any previously populated fields that are not submitted with their full existing data using this method will be cleared of their existing data. When using this method, you should first do a GET to retrieve all the values for the record you want to update, enter corrected data into the field(s) you want to update, and then submit all the fields using PUT, including the fields that contain values but which you are not changing.

Table 284: PUT MacEnrollment Response Data

Name	In	Description
Id	Body	An integer indicating the Keyfactor Command referenced ID of the Mac auto-enrollment configuration.
Enabled	Body	An Boolean indicating whether Mac auto-enrollment is configured in the environment (true) or not (false).
Interval	Body	An integer indicating the frequency with which the Mac auto-enrollment agent should check to see if there are new certificates for which to enroll.
UseMetadata	Body	A Boolean indicating whether to automatically associate data in a custom metadata field with an auto-enrolled Mac certificate (true) or not (false).  See in the <i>Keyfactor Command Reference Guide</i> for more information about metadata fields.
MetadataField	Body	A string indicating the name of the metadata field to populate for the certificate, if <i>UseMetadata</i> is <i>true</i> .
MetadataValue	Body	A string indicating the value to populate for the metadata field, if <i>UseMetadata</i> is <i>true</i> . This may be either a static value (e.g. a fixed string that indicates this certificate was acquired as a result of an auto-enrollment on a Mac), or a variable retrieved from the Mac. In the current version of the agent, only the Mac serial number is available.

Table 285: PUT MacEnrollment Response Data

Name	Description
Id	An integer indicating the Keyfactor Command referenced ID of the Mac auto-enrollment configuration.
Enabled	An Boolean indicating whether Mac auto-enrollment is configured in the environment (true) or not (false).
Interval	An integer indicating the frequency with which the Mac auto-enrollment agent should check to see if there are new certificates for which to enroll.
UseMetadata	A Boolean indicating whether to automatically associate data in a custom metadata field with an auto-enrolled Mac certificate (true) or not (false).  See Certificate Metadata in the Keyfactor Command Reference Guide for more information about metadata fields.
MetadataField	A string indicating the name of the metadata field to populate for the certificate, if <i>UseMetadata</i> is <i>true</i> .
MetadataValue	A string indicating the value to populate for the metadata field, if <i>UseMetadata</i> is <i>true</i> . This may be either a static value (e.g. a fixed string that indicates this certificate was acquired as a result of an auto-enrollment on a Mac), or a variable retrieved from the Mac. In the current version of the agent, only the Mac serial number is available.

# 2.2.17 MetadataFields

MetadataFields contains definitions for metadata that can be associated with certificates in Keyfactor Command.

Table 286: MetadataFields Endpoints

Endpoint	Method	Description	Link
/{id}	DELETE	Deletes an existing metadata field.	DELETE MetadataFields ID on the next page
/{id}	GET	Returns detailed information for the specified metadata field.	GET MetadataFields ID on the next page
/{name}	GET	Returns detailed information for the specified metadata field.	GET MetadataFields Name on page 639
/{id}/InUse	GET	Returns a Boolean stating whether the metadata type is associated with a certificate.	GET MetadataFields ID InUse on page 642
/	DELETE	Deletes multiple metadata fields specified in the request	DELETE

Endpoint	Method	Description	Link
		body.	MetadataFields on page 643
/	GET	Returns all metadata field types with paging (number of pages to return and number of results per page) options.	GET MetadataFields on page 643
/	POST	Creates a new metadata field using values supplied in the request body.	POST MetadataFields on page 647
/	PUT	Updates an existing metadata field using values supplied in the request body.	PUT MetadataFields on page 653

#### 2.2.17.1 DELETE MetadataFields ID

The DELETE /MetadataFields/{id} method is used to delete a metadata field by ID. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: CertificateMetadataTypes: *Modify* 

Table 287: DELETE MetadataFields {id} Input Parameters

Name	In	Description
id	Path	<b>Required</b> . The Keyfactor Command reference ID for the metadata field to be deleted. Use the <i>GET /MetadataFields</i> method (see <u>GET MetadataFields on page 643</u> ) to retrieve a list of all the metadata fields to determine the metadata field's ID.
Force	Query	A Boolean that sets whether to force deletion of the metadata field even if it is in use by one or more certificates (true) or not (false). The default is <i>false</i> .  Use the <i>GET /MetadataFields/{id}/InUse</i> method (see <u>GET MetadataFields ID InUse on page 642</u> ) to determine whether a metadata field is in use.

#### 2.2.17.2 GET MetadataFields ID

The GET /MetadataFields/{id} method is used to return details for the metadata field with a specified unique ID. This method returns HTTP 200 OK on a success with details for the requested metadata field.



Table 288: GET MetadataFields {id} Input Parameters

Name	In	Description
id	Path	<b>Required</b> . An integer indicating the Keyfactor Command reference ID for the metadata field. Use the <i>GET /MetadataFields</i> method (see <u>GET MetadataFields on page 643</u> ) to retrieve a list of all the metadata fields to determine the metadata field's ID.

Table 289: GET MetadataFields {id} Response Data

Name	Description		
ID	An integer indicating the Keyfactor Command reference ID for the metadata field. This ID is automatically set by Keyfactor Command.		
Name	A string indicating the name of the metadata field. This name appears in interfaces where you can use metadata, such as certificate details dialogs, alert dialogs, certificate imports and certificate requests. Once this field has a value associated with it for at least one certificate, you cannot change this name. The metadata name field cannot contain spaces; dashes and underscores are supported.		
Description	A string indicating the description for the	metadata field.	
DataType	An integer indicating the data type of the	metadata field. Possible values are:	
	Value	Description	
	1	String	
	2	Integer	
	3	Date	
	4	Boolean	
	5	Multiple Choice	
	6	Big Text	
Hint	string, integer, big text and date fields on what type of data should be entered in th	radata field. This hint appears in unpopulated metadata editing interfaces to provide the user with a clue as to e field.  Gields with data types string, integer, date or big text.	
Validation	A string containing a regular expression against which data entered in a string field will be validated. When a user enters information in a metadata field that does not match the specified regular expression, he or she will see the warning message specified in the <code>Message</code> field. For example:  ^[a-zA-Z0-9'_\.\-]*@(keyexample\.org keyexample\.com)\$  This regular expression specifies that the data entered in the field must consist of some number of characters prior to the "@" made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly either "@keyexample.org" or "keyexample.com".  This field is only supported for metadata fields with data type <code>string</code> .		

Name	Description	
	<b>Tip:</b> If a template specific option is set for a given metadata field, that takes precedence over the global options. The template-specific regular expression will be used in PFX and CSR enrollment requests using that template (see <a href="GET Templates ID">GET Templates ID</a> on page 1152).	
Enrollment	An integer indicating how metadata fields should be handled on the PFX and CSR Enrollment pages. Possible values are:	
	Value Description	
	O Optional Users have the option to either enter a value or not enter a value in the field.	
	1 Required Users are required to enter data in the field when populating metadata fields on the PFX and CSR Enrollment pages. The field is not required on the certificate details or Add Certificate page.	
	2 Hidden The field is hidden and does not appear on the PFX and CSR Enrollment pages. This field still appears on the certificate details and the Add Certificate page.	
	Tip: If a template-specific handling is set for a given metadata field, it takes precedence over this global setting. The template-specific handling will be used in PFX and CSR enrollment requests using that template (see <a href="https://example.com/get/GET/Templates/">GET Templates ID on page 1152</a> ).	
Message	A string containing a message to present when a user enters information in a metadata field that does not match the specified regular expression ( <i>Validation</i> field).	
	Tip: If a template-specific regular expression message is set for a given metadata field, it takes precedence over this global regular expression message. The template-specific message will be used in PFX and CSR enrollment requests using that template (see <a get="" href="https://gen.gen.gen.gen.gen.gen.gen.gen.gen.gen.&lt;/td&gt;&lt;/tr&gt;&lt;tr&gt;&lt;td&gt;Options&lt;/td&gt;&lt;td&gt;An array containing a comma separated list of values that should appear in the field dropdown for multiple choice fields.&lt;/td&gt;&lt;/tr&gt;&lt;tr&gt;&lt;td&gt;&lt;/td&gt;&lt;td colspan=3&gt;This field is only supported for metadata fields with data type multiple choice.&lt;/td&gt;&lt;/tr&gt;&lt;tr&gt;&lt;td&gt;&lt;/td&gt;&lt;td&gt;Tip: If a template-specific options are set for a given metadata field, these takes precedence over these global options. The template-specific options will be used in PFX and CSR enrollment requests using that template (see &lt;a href=" id"="" templates="">GET Templates ID</a> on page 1152).	
DefaultValue	A string containing a default value with which to pre-populate the metadata field for new certificate	

Name	Description	
	requests made using PFX or CSR enrollment.  This field is only supported for metadata fields with data types <i>string</i> , <i>integer</i> , <i>Boolean</i> or <i>multiple choice</i> .	
	Tip: If a template-specific default is set for a given metadata field, it takes precedence over this global default value. The template-specific default will be used in PFX and CSR enrollment requests using that template (see	

## 2.2.17.3 GET MetadataFields Name

The GET /MetadataFields/{name} method is used to return details for the metadata field with the specified unique name. This method returns HTTP 200 OK on a success with details for the requested metadata field.



Table 290: GET MetadataFields {name} Input Parameters

Name	In	Description
name	Path	<b>Required</b> . A string that indicates the name of the metadata field. This value is not case sensitive.

Table 291: GET MetadataFields {name} Response Data

Name	Description		
ID	An integer indicating the Keyfactor Command reference ID for the metadata field. This ID is automatically set by Keyfactor Command.		
Name	A string indicating the name of the metadata field. This name appears in interfaces where you can use metadata, such as certificate details dialogs, alert dialogs, certificate imports and certificate requests. Once this field has a value associated with it for at least one certificate, you cannot change this name. The metadata name field cannot contain spaces; dashes and underscores are supported.		
Description	A string indicating the description for the	metadata field.	
DataType	An integer indicating the data type of the	metadata field. Possible values are:	
	Value	Description	
	1	String	
	2	Integer	
	3	Date	
	4	Boolean	
	5	Multiple Choice	
	6	Big Text	
Hint	string, integer, big text and date fields on what type of data should be entered in th	radata field. This hint appears in unpopulated metadata editing interfaces to provide the user with a clue as to e field.  Gields with data types string, integer, date or big text.	
Validation	A string containing a regular expression against which data entered in a string field will be validated. When a user enters information in a metadata field that does not match the specified regular expression, he or she will see the warning message specified in the <code>Message</code> field. For example:  ^[a-zA-Z0-9'_\.\-]*@(keyexample\.org keyexample\.com)\$  This regular expression specifies that the data entered in the field must consist of some number of characters prior to the "@" made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly either "@keyexample.org" or "keyexample.com".  This field is only supported for metadata fields with data type <code>string</code> .		

Name	Description		
	Tip: If a template specific option is set for a given metadata field, that takes precedence over the global options. The template-specific regular expression will be used in PFX and CSR enrollment requests using that template (see <a href="GET Templates ID">GET Templates ID</a> on page 1152).		
Enrollment	An integer indicating how metadata fields should be handled on the PFX and CSR Enrollment pages. Possible values are:		
	Value Description		
	O Optional Users have the option to either enter a value or not enter a value in the field.		
	1 Required Users are required to enter data in the field when populating metadata fields on the PFX and CSR Enrollment pages. The field is not required on the certificate details or Add Certificate page.		
	2 Hidden The field is hidden and does not appear on the PFX and CSR Enrollment pages. This field still appears on the certificate details and the Add Certificate page.		
	Tip: If a template-specific handling is set for a given metadata field, it takes precedence over this global setting. The template-specific handling will be used in PFX and CSR enrollment requests using that template (see <a href="https://example.com/get/GET Templates">GET Templates ID on page 1152</a> ).		
Message	A string containing a message to present when a user enters information in a metadata field that does not match the specified regular expression ( <i>Validation</i> field).		
	Tip: If a template-specific regular expression message is set for a given metadata field, it takes precedence over this global regular expression message. The template-specific message will be used in PFX and CSR enrollment requests using that template (see <a href="MEETTEMPLATER">GET Templates ID on page 1152</a> ).		
Options	An array containing a comma separated list of values that should appear in the field dropdown for multiple choice fields.		
	This field is only supported for metadata fields with data type multiple choice.		
	Tip: If a template-specific options are set for a given metadata field, these takes precedence over these global options. The template-specific options will be used in PFX and CSR enrollment requests using that template (see <a href="GET Templates ID">GET Templates ID</a> on page 1152).		
DefaultValue	A string containing a default value with which to pre-populate the metadata field for new certificate		

Name	Description	
	requests made using PFX or CSR enrollment.  This field is only supported for metadata fields with data types <i>string</i> , <i>integer</i> , <i>Boolean</i> or <i>multiple choice</i> .	
	Tip: If a template-specific default is set for a given metadata field, it takes precedence over this global default value. The template-specific default will be used in PFX and CSR enrollment requests using that template (see	

## 2.2.17.4 GET MetadataFields ID InUse

The GET /MetadataFields/{id}/InUse method is used to return a Boolean indicating whether the specified metadata field contains any data for any of the certificates in Keyfactor Command. This is useful to determine before attempting to delete a metadata field. This method returns HTTP 200 OK on a success with a value of true or false.



Table 292: GET MetadataFields {id} In Use Input Parameters

Name	In	Description
id	Path	Required. The Keyfactor Command reference ID for the metadata field.  Use the GET /MetadataFields method (see GET MetadataFields on the next page) to retrieve a list of all the metadata fields to determine the metadata field's ID.

Table 293: GET MetadataFields {id} In Use Response Data

Name	Description	
	A Boolean that indicates whether the specified metadata field contains data for any certificates within Keyfactor Command (true) or not (false). This value is returned without a parameter name.	

#### 2.2.17.5 DELETE MetadataFields

The DELETE /MetadataFields method is used to delete multiple metadata fields in one request. The metadata fields IDs should be supplied in the request body as a JSON array of integers. Delete operations will continue until the entire array of IDs has been processed. Note that metadata fields that are in use for any certificate cannot be deleted unless the force=true parameter is included in the request. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: CertificateMetadataTypes: *Modify* 

Table 294: DELETE MetadataFields Input Parameters

Name	In	Description
ids	Body	<b>Required</b> . An array of Keyfactor Command reference IDs for the metadata fields to be deleted.  Use the <i>GET /MetadataFields</i> method (see <u>GET MetadataFields below</u> ) to retrieve a list of all the metadata fields to determine the metadata field IDs.
Force	Query	A Boolean that sets whether to force deletion of the metadata fields even if they are in use (true) or not (false). The default is <i>False</i> . Use the <i>GET /MetadataFields/{id}/InUse</i> method (see <u>GET MetadataFields ID InUse on the previous page</u> ) to determine whether a metadata field is in use.

#### 2.2.17.6 GET MetadataFields

The GET /MetadataFields method is used to return a list of all metadata fields. This method returns HTTP 200 OK on a success with details for the metadata fields.



Table 295: GET MetadataFields Input Parameters

Name	In	Description	
queryString	Query	A string containing a query to limit the results (e.g. field1 -eq value1 AND field2 -gt value2). The default is to return all records. Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns for the same feature. For querying guidelines, refer to the Keyfactor Command Reference Guide: Using the Logons Search. The query fields supported for this endpoint are:  • Name	
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.	
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.	
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>DisplayOrder</i> .	
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.	

Table 296: GET MetadataFields Response Data

Name	Description		
ID	An integer indicating the Keyfactor Command reference ID for the metadata field. This ID is automatically set by Keyfactor Command.		
Name	A string indicating the name of the metadata field. This name appears in interfaces where you can use metadata, such as certificate details dialogs, alert dialogs, certificate imports and certificate requests. Once this field has a value associated with it for at least one certificate, you cannot change this name. The metadata name field cannot contain spaces; dashes and underscores are supported.		
Description	A string indicating the description for the	metadata field.	
DataType	An integer indicating the data type of the	metadata field. Possible values are:	
	Value	Description	
	1	String	
	2	Integer	
	3	Date	
	4	Boolean	
	5	Multiple Choice	
	6	Big Text	
Hint	A string indicating a short hint for the metadata field. This hint appears in unpopulated metadata string, integer, big text and date fields on editing interfaces to provide the user with a clue as to what type of data should be entered in the field.  This field is only supported for metadata fields with data types string, integer, date or big text.		
Validation	A string containing a regular expression against which data entered in a string field will be validated. When a user enters information in a metadata field that does not match the specified regular expression, he or she will see the warning message specified in the <code>Message</code> field. For example:  ^[a-zA-Z0-9'_\\-]*@(keyexample\.org keyexample\.com)\$  This regular expression specifies that the data entered in the field must consist of some number of characters prior to the "@" made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly either "@keyexample.org" or "keyexample.com".  This field is only supported for metadata fields with data type <code>string</code> .		

Name	Tip: If a template specific option is set for a given metadata field, that takes precedence over the global options. The template-specific regular expression will be used in PFX and CSR enrollment requests using that template (see GET Templates ID on page 1152).		
Enrollment	An integer indicating how metadata fields should be handled on the PFX and CSR Enrollment pages. Possible values are:		
	Value Description		
	Optional Users have the option to either enter a value or not enter a value in the field.		
	1 Required Users are required to enter data in the field when populating metadata fields on the PFX and CSR Enrollment pages. The field is not required on the certificate details or Add Certificate page.		
	2 Hidden The field is hidden and does not appear on the PFX and CSR Enrollment pages. This field still appears on the certificate details and the Add Certificate page.		
	Tip: If a template-specific handling is set for a given metadata field, it takes precedence over this global setting. The template-specific handling will be used in PFX and CSR enrollment requests using that template (see <a href="GET Templates ID">GET Templates ID</a> on page 1152).		
Message A string containing a message to present when a user enters information in a metada does not match the specified regular expression ( <i>Validation</i> field).			
	Tip: If a template-specific regular expression message is set for a given metadata field, it takes precedence over this global regular expression message. The template-specific message will be used in PFX and CSR enrollment requests using that template (see <a get="" href="https://gen.gen.gen.gen.gen.gen.gen.gen.gen.gen.&lt;/td&gt;&lt;/tr&gt;&lt;tr&gt;&lt;td&gt;Options&lt;/td&gt;&lt;td&gt;An array containing a comma separated list of values that should appear in the field dropdown for multiple choice fields.  This field is only supported for metadata fields with data type &lt;i&gt;multiple choice&lt;/i&gt;.&lt;/td&gt;&lt;/tr&gt;&lt;tr&gt;&lt;td&gt;&lt;/td&gt;&lt;td colspan=3&gt;Tip: If a template-specific options are set for a given metadata field, these takes precedence over these global options. The template-specific options will be used in PFX and CSR enrollment requests using that template (see &lt;a href=" id"="" templates="">GET Templates ID</a> on page 1152).		
DefaultValue	A string containing a default value with which to pre-populate the metadata field for new certificate		

Name	Description
	requests made using PFX or CSR enrollment.  This field is only supported for metadata fields with data types <i>string</i> , <i>integer</i> , <i>Boolean</i> or <i>multiple choice</i> .
	Tip: If a template-specific default is set for a given metadata field, it takes precedence over this global default value. The template-specific default will be used in PFX and CSR enrollment requests using that template (see

## 2.2.17.7 POST MetadataFields

The POST /MetadataFields method is used to create a new metadata field in Keyfactor Command. This method returns HTTP 200 OK on a success with details of the new metadata field.



Table 297: POST MetadataFields Input Parameters

Name	In	Description		
Name	Body	<b>Required</b> . A string indicating the name of the metadata field. This name appears in interfaces where you can use metadata, such as certificate details dialogs, alert dialogs, certificate imports and certificate requests. Once this field has a value associated with it for at least one certificate, you cannot change this name. The metadata name field cannot contain spaces; dashes and underscores are supported.		
Description	Body	Required. A string indicating the des	cription for the metadata field.	
DataType	Body	<b>Required</b> . An integer indicating the data type of the metadata field. Possible values are:		
		Value	Description	
		1	String	
		2	Integer	
		3	Date	
		4	Boolean	
		5	Multiple Choice	
		6	Big Text	
Hint	Body	A string indicating a short hint for the metadata field. This hint appears in unpopulated metadata string, integer, big text and date fields on editing interfaces to provide the user with a clue as to what type of data should be entered in the field.  This field is only supported for metadata fields with data types <i>string</i> , <i>integer</i> , <i>date</i> or <i>big text</i> .		
Validation	Body	A string containing a regular expression against which data entered in a string field will be validated. When a user enters information in a metadata field that does not match the specified regular expression, he or she will see the warning message specified in the <code>Message</code> field. For example:  \[ ^[a-zA-Z0-9'_\.\-]*@(keyexample\.org keyexample\.com)\$  This regular expression specifies that the data entered in the field must consist of some number of characters prior to the "@" made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly either "@keyexample.org" or "keyexample.com".  This field is only supported for metadata fields with data type <code>string</code> .		
			otion is set for a given metadata field, that takes options. The template-specific regular expression	

Name	In	Description	
		will be used in PFX and CSR enrollment requests using that template (see <u>GET Templates ID on page 1152</u> ).	
Enrollment	Body	An integer indicating how metadata fields should be handled on the PFX and CSR Enrollment pages. Possible values are:	
		Value Description	
		O Optional Users have the option to either enter a value or not enter a value in the field.	
		1 Required Users are required to enter data in the field when populating metadata fields on the PFX and CSR Enrollment pages. The field is not required on the certificate details or Add Certificate page.	
		2 Hidden The field is hidden and does not appear on the PFX and CSR Enrollment pages. This field still appears on the certificate details and the Add Certificate page.	
		The default is <i>optional</i> .	
		Tip: If a template-specific handling is set for a given metadata field, it takes precedence over this global setting. The template-specific handling will be used in PFX and CSR enrollment requests using that template (see <a get="" href="https://example.com/get/gen/gen/gen/gen/gen/gen/gen/gen/gen/gen&lt;/td&gt;&lt;/tr&gt;&lt;tr&gt;&lt;td&gt;Message&lt;/td&gt;&lt;td&gt;Body&lt;/td&gt;&lt;td&gt;A string containing a message to present when a user enters information in a metadata field that does not match the specified regular expression (&lt;i&gt;Validation&lt;/i&gt; field).&lt;/td&gt;&lt;/tr&gt;&lt;tr&gt;&lt;td colspan=2&gt;&lt;/td&gt;&lt;td colspan=3&gt;Tip: If a template-specific regular expression message is set for a given metadata field, it takes precedence over this global regular expression message. The template-specific message will be used in PFX and CSR enrollment requests using that template (see &lt;a href=" id"="" templates="">GET Templates ID</a> on page 1152).	
Options	Body	An array containing a comma separated list of values that should appear in the field dropdown for multiple choice fields.  This field is <b>required</b> for metadata fields with data type <i>multiple choice</i> . For other data types, it will be ignored.	
		Tip: If a template-specific options are set for a given metadata field, these	

Name	In	Description
		takes precedence over these global options. The template-specific options will be used in PFX and CSR enrollment requests using that template (see <a href="GET">GET</a> <a href="Templates ID">Templates ID</a> on page 1152).
DefaultValue	Body	A string containing a default value with which to pre-populate the metadata field for new certificate requests made using PFX or CSR enrollment.  This field is only supported for metadata fields with data types <i>string</i> , <i>integer</i> , <i>Boolean</i> or <i>multiple choice</i> .
		Tip: If a template-specific default is set for a given metadata field, it takes precedence over this global default value. The template-specific default will be used in PFX and CSR enrollment requests using that template (see

Table 298: POST MetadataFields Response Data

Name	Description		
ID	An integer indicating the Keyfactor Command reference ID for the metadata field. This ID is automatically set by Keyfactor Command.		
Name	A string indicating the name of the metadata field. This name appears in interfaces where you can use metadata, such as certificate details dialogs, alert dialogs, certificate imports and certificate requests. Once this field has a value associated with it for at least one certificate, you cannot change this name. The metadata name field cannot contain spaces; dashes and underscores are supported.		
Description	A string indicating the description for the	metadata field.	
DataType	An integer indicating the data type of the	metadata field. Possible values are:	
	Value	Description	
	1	String	
	2	Integer	
	3	Date	
	4	Boolean	
	5	Multiple Choice	
	6	Big Text	
Hint	A string indicating a short hint for the metadata field. This hint appears in unpopulated metadata string, integer, big text and date fields on editing interfaces to provide the user with a clue as to what type of data should be entered in the field.  This field is only supported for metadata fields with data types string, integer, date or big text.		
Validation	A string containing a regular expression against which data entered in a string field will be validated. When a user enters information in a metadata field that does not match the specified regular expression, he or she will see the warning message specified in the <code>Message</code> field. For example:  ^[a-zA-Z0-9'_\.\-]*@(keyexample\.org keyexample\.com)\$  This regular expression specifies that the data entered in the field must consist of some number of characters prior to the "@" made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly either "@keyexample.org" or "keyexample.com".  This field is only supported for metadata fields with data type <code>string</code> .		

Name	Description		
	Tip: If a template specific option is set for a given metadata field, that takes precedence over the global options. The template-specific regular expression will be used in PFX and CSR enrollment requests using that template (see <a href="GET Templates ID">GET Templates ID</a> on page 1152).		
Enrollment	An integer indicating how metadata fields should be handled on the PFX and CSR Enrollment pages.  Possible values are:		
	Value Description		
	Optional Users have the option to either enter a value or not enter a value in the field.		
	1 Required Users are required to enter data in the field when populating metadata fields on the PFX and CSR Enrollment pages. The field is not required on the certificate details or Add Certificate page.		
	2 Hidden The field is hidden and does not appear on the PFX and CSR Enrollment pages. This field still appears on the certificate details and the Add Certificate page.		
	Tip: If a template-specific handling is set for a given metadata field, it takes precedence over this global setting. The template-specific handling will be used in PFX and CSR enrollment requests using that template (see <a href="https://example.com/get/GET/Templates/">GET Templates ID on page 1152</a> ).		
Message	A string containing a message to present when a user enters information in a metadata field that does not match the specified regular expression ( <i>Validation</i> field).		
	Tip: If a template-specific regular expression message is set for a given metadata field, it takes precedence over this global regular expression message. The template-specific message will be used in PFX and CSR enrollment requests using that template (see <a get="" href="https://example.com/get/get/get/get/get/get/get/get/get/get&lt;/td&gt;&lt;/tr&gt;&lt;tr&gt;&lt;td&gt;Options&lt;/td&gt;&lt;td colspan=2&gt;An array containing a comma separated list of values that should appear in the field dropdown for multiple choice fields.  This field is only supported for metadata fields with data type &lt;i&gt;multiple choice&lt;/i&gt;.&lt;/td&gt;&lt;/tr&gt;&lt;tr&gt;&lt;td&gt;&lt;/td&gt;&lt;td colspan=3&gt;Tip: If a template-specific options are set for a given metadata field, these takes precedence over these global options. The template-specific options will be used in PFX and CSR enrollment requests using that template (see &lt;a href=" id"="" templates="">GET Templates ID</a> on page 1152).		
DefaultValue	A string containing a default value with which to pre-populate the metadata field for new certificate		

Name	Description
	requests made using PFX or CSR enrollment.  This field is only supported for metadata fields with data types <i>string</i> , <i>integer</i> , <i>Boolean</i> or <i>multiple choice</i> .
	Tip: If a template-specific default is set for a given metadata field, it takes precedence over this global default value. The template-specific default will be used in PFX and CSR enrollment requests using that template (see

#### 2.2.17.8 PUT MetadataFields

The PUT /MetadataFields method is used to update an existing metadata field in Keyfactor Command. This method returns HTTP 200 OK on a success with details of the updated metadata field.



Tip: The following permissions (see Security Overview) are required to use this feature: CertificateMetadataTypes: Modify



Warning: Any previously populated fields that are not submitted with their full existing data using this method will be cleared of their existing data. When using this method, you should first do a GET to retrieve all the values for the record you want to update, enter corrected data into the field(s) you want to update, and then submit all the fields using PUT, including the fields that contain values but which you are not changing.

Table 299: PUT MetadataFields Input Parameters

Name	In	Description		
ID	Body	<b>Required</b> . An integer indicating the Keyfactor Command reference ID for the metadata field. This ID is automatically set by Keyfactor Command.		
Name	Body	<b>Required</b> . A string indicating the name of the metadata field. This name appears in interfaces where you can use metadata, such as certificate details dialogs, alert dialogs, certificate imports and certificate requests. Once this field has a value associated with it for at least one certificate, you cannot change this name. The metadata name field cannot contain spaces; dashes and underscores are supported.		
Description	Body	Required. A string indicating the des	scription for the metadata field.	
DataType	Body	<b>Required</b> . An integer indicating the data type of the metadata field. Possible values are:		
		Value	Description	
		1	String	
		2	Integer	
		3	Date	
		4	Boolean	
		5	Multiple Choice	
		6	Big Text	
Hint	Body	A string indicating a short hint for the metadata field. This hint appears in unpopulated metadata string, integer, big text and date fields on editing interfaces to provide the user with a clue as to what type of data should be entered in the field.  This field is only supported for metadata fields with data types <i>string</i> , <i>integer</i> , <i>date</i> or <i>big text</i> .		
Validation	Body	A string containing a regular expression against which data entered in a string field will be validated. When a user enters information in a metadata field that does not match the specified regular expression, he or she will see the warning message specified in the <code>Message</code> field. For example:  \[ ^[a-zA-Z0-9'_\.\-]*@(keyexample\.org keyexample\.com)\$  This regular expression specifies that the data entered in the field must consist of some number of characters prior to the "@" made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly either "@keyexample.org" or "keyexample.com".  This field is only supported for metadata fields with data type <code>string</code> .		

Name	In	Description		
		Tip: If a template specific option is set for a given metadata field, that takes precedence over the global options. The template-specific regular expression will be used in PFX and CSR enrollment requests using that template (see <a href="MEET_Templates ID">GET_Templates ID on page 1152</a> ).		
Enrollment	Body	An integer indicating how metadata fields should be handled on the PFX and CSR Enrollment pages. Possible values are:		
		Value	Description	
		0	Optional Users have the option to either enter a value or not enter a value in the field.	
		1	Required Users are required to enter data in the field when populating metadata fields on the PFX and CSR Enrollment pages. The field is not required on the certificate details or Add Certificate page.	
		2	Hidden The field is hidden and does not appear on the PFX and CSR Enrollment pages. This field still appears on the certificate details and the Add Certificate page.	
		The default is optional.		
		Tip: If a template-specific handling is set for a given metadata field, it takes precedence over this global setting. The template-specific handling will be used in PFX and CSR enrollment requests using that template (see <a href="https://example.com/get/GET_Templates">GET_Templates ID on page 1152</a> ).		
Message	Body	A string containing a message to present when a user enters information in field that does not match the specified regular expression ( <i>Validation</i> field).  Tip: If a template-specific regular expression message is set for a gi metadata field, it takes precedence over this global regular express message. The template-specific message will be used in PFX and CS ment requests using that template (see <a href="GET Templates ID">GET Templates ID</a> on page 2		
Options	Body	An array containing a comma separated list of values that should appear in the field dropdown for multiple choice fields.  This field is <b>required</b> for metadata fields with data type <i>multiple choice</i> . For other data types, it will be ignored.		

Name	In	Description	
		Tip: If a template-specific options are set for a given metadata field, these takes precedence over these global options. The template-specific options will be used in PFX and CSR enrollment requests using that template (see <a href="GET">GET</a> Templates ID on page 1152).	
DefaultValue	Body	A string containing a default value with which to pre-populate the metadata field for new certificate requests made using PFX or CSR enrollment.  This field is only supported for metadata fields with data types <i>string</i> , <i>integer</i> , <i>Boolean</i> or <i>multiple choice</i> .	
		Tip: If a template-specific default is set for a given metadata field, it takes precedence over this global default value. The template-specific default will be used in PFX and CSR enrollment requests using that template (see <a href="GET Templates ID">GET Templates ID on page 1152</a> ).	
AllowAPI	Body	A Boolean that sets whether methods in the Classic API can be used to manipulate data in the metadata record (true) or not (false). The default is <i>true</i> . This setting does not apply to the Keyfactor API.  This is considered deprecated and may be removed in a future release.	
ExplicitUpdate	Body	A Boolean that sets whether methods in the Classic API must submit an overwrite flag in the request in order to overwrite an existing value in the metadata record (true) or not (false). The default is <i>false</i> . This setting does not apply to the Keyfactor API.  This is considered deprecated and may be removed in a future release.	
DisplayOrder	Body	An integer indicating the order in which the metadata field should be displayed on pages where the metadata fields are displayed (e.g. PFX enrollment, certificate details).	

Table 300: PUT MetadataFields Response Data

Name	Description	
ID	An integer indicating the Keyfactor Command reference ID for the metadata field. This ID is automatically set by Keyfactor Command.	
Name	A string indicating the name of the metadata field. This name appears in interfaces where you can use metadata, such as certificate details dialogs, alert dialogs, certificate imports and certificate requests. Once this field has a value associated with it for at least one certificate, you cannot change this name. The metadata name field cannot contain spaces; dashes and underscores are supported.	
Description	A string indicating the description for the metadata field.	
DataType	An integer indicating the data type of the	metadata field. Possible values are:
	Value	Description
	1	String
	2	Integer
	3	Date
	4	Boolean
	5	Multiple Choice
	6	Big Text
Hint	A string indicating a short hint for the metadata field. This hint appears in unpopulated metadata string, integer, big text and date fields on editing interfaces to provide the user with a clue as to what type of data should be entered in the field.  This field is only supported for metadata fields with data types string, integer, date or big text.	
Validation	A string containing a regular expression against which data entered in a string field will be validated. When a user enters information in a metadata field that does not match the specified regular expression, he or she will see the warning message specified in the <code>Message</code> field. For example:  ^[a-zA-Z0-9'_\\\-]*@(keyexample\.org keyexample\.com)\$  This regular expression specifies that the data entered in the field must consist of some number of characters prior to the "@" made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly either "@keyexample.org" or "keyexample.com".  This field is only supported for metadata fields with data type <code>string</code> .	

Name	Description		
	Tip: If a template specific option is set for a given metadata field, that takes precedence over the global options. The template-specific regular expression will be used in PFX and CSR enrollment requests using that template (see <a href="GET Templates ID">GET Templates ID</a> on page 1152).		
Enrollment	An integer indicating how metadata fields should be handled on the PFX and CSR Enrollment pages. Possible values are:		
	Value Description		
	Optional Users have the option to either enter a value or not enter a value in the field.		
	1 Required Users are required to enter data in the field when populating metadata fields on the PFX and CSR Enrollment pages. The field is not required on the certificate details or Add Certificate page.		
	2 Hidden The field is hidden and does not appear on the PFX and CSR Enrollment pages. This field still appears on the certificate details and the Add Certificate page.		
	Tip: If a template-specific handling is set for a given metadata field, it takes precedence over this global setting. The template-specific handling will be used in PFX and CSR enrollment requests using that template (see <a href="https://example.com/get/GET/Templates/">GET Templates ID on page 1152</a> ).		
Message	A string containing a message to present when a user enters information in a metadata field that does not match the specified regular expression ( <i>Validation</i> field).		
	Tip: If a template-specific regular expression message is set for a given metadata field, it takes precedence over this global regular expression message. The template-specific message will be used in PFX and CSR enrollment requests using that template (see <a href="GET_Templates ID">GET_Templates ID on page 1152</a> ).		
Options	An array containing a comma separated list of values that should appear in the field dropdown for multiple choice fields.		
	This field is only supported for metadata fields with data type <i>multiple choice</i> .  Tip: If a template-specific options are set for a given metadata field, these takes precedence over these global options. The template-specific options will be used in PFX and CSR enrollment requests using that template (see <a href="GET Templates ID">GET Templates ID</a> on page 1152).		
DefaultValue	A string containing a default value with which to pre-populate the metadata field for new certificate		

Name	Description		
	requests made using PFX or CSR enrollment.  This field is only supported for metadata fields with data types <i>string</i> , <i>integer</i> , <i>Boolean</i> or <i>multiple choice</i> .		
	Tip: If a template-specific default is set for a given metadata field, it takes precedence over this global default value. The template-specific default will be used in PFX and CSR enrollment requests using that template (see		

# 2.2.18 Monitoring Revocation

The Monitoring Revocation component of the Keyfactor API provides a set of methods to support management of CRL and OCSP monitoring locations.

Table 301: Monitoring Revocation Endpoints

Endpoint	Method	Description	Link
/{id}	DELETE	Deletes the revocation monitoring location with the specified ID.	DELETE Monitoring Revocation ID on the next page
/{id}	GET	Returns details for the revocation monitoring location with the specified ID.	GET Monitoring Revocation ID on the next page
/	PUT	Edits the revocation monitoring location with the specified ID.	PUT Monitoring Revocation on page 674
/	GET	Returns details for all revocation monitoring location according to the provided filter and output parameters.	GET Monitoring Revocation on page 664

Endpoint	Method	Description	Link
/	POST	Creates a new revocation monitoring location.	POST Monitoring Revocation on page 668
/ResolveOSCP	POST	Resolves the given OCSP certificate authority.	POST Monitoring Resolve OSCP on page 680
/Test	POST	Tests the revocation monitoring alert with the specified ID.	POST Monitoring Revocation Test on page 681
/TestAll	POST	Tests the revocation monitoring alerts.	POST Monitoring Revocation Test All on page 683

## 2.2.18.1 DELETE Monitoring Revocation ID

The DELETE Monitoring/Revocation/{id} method is used to delete the revocation monitoring location with the specified ID. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: WorkflowManagement: *Modify* 

Table 302: DELETE Monitoring Revocation {id} Input Parameters

Name	In	Description
id	Path	Required. An integer that specifies the ID of the revocation monitoring location.  Use the GET /Monitoring/Revocation method (see GET Monitoring Revocation on page 664) to retrieve a list of all the revocation monitoring locations to determine the ID.

## 2.2.18.2 GET Monitoring Revocation ID

The GET /Monitoring/Revocation/{id} method is used to retrieve the revocation monitoring location with the specified ID. This method returns HTTP 200 OK on a success with details of the location.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: WorkflowManagement: *Read* 

Table 303: GET Monitoring Revocation {id} Input Parameters

Name	In	Description
id	Path	Required. An integer that specifies the ID of the revocation monitoring location.  Use the GET /Monitoring/Revocation method (see GET Monitoring Revocation on page 664) to retrieve a list of all the revocation monitoring locations to determine the ID.

Table 304: GET Monitoring Revocation {id} Response Data

Name	Description			
Id	An integer indicating the Keyfactor Command reference ID of the revocation monitoring location.			
Name	A string indicating the name of the revocation monitoring location.			
EndpointType	A string indicating the type of revocation monitoring endpoint: OCSP or CRL.			
Location	A string indicating the location for the revocation monitoring endpoint.  For CRL endpoints, this can be either an HTTP location or an LDAP location. Be sure to monitor the CRL locations that are in use by applications in your environment—if you're monitoring LDAP locations but applications are using an HTTP location, you're not going to receive any warning if a CRL fails to publish to the HTTP location.  For OCSP endpoints, this is the full URL to the OCSP responder servicing this certificate authority's CRL.			
Email	For CRL endpoints only, an array indicating the email recipients and reminder schedule for reminder alerts. Email reminder details are:			
	Value	Description		
	EnableReminder	A Boolean indicating whether to send email reminders for this location (true) or not (false).		
	WarningDays	An integer indicating the number of days before expiration to send the warning email.		
	Recipients	An object containing a list of strings with email addresses to which the email reminders should be sent.		
Dashboard	An array indicating the configuration for display on the dashboard. Dashboard details are:			
	Value	Description		
	Show	A Boolean indicating whether to show this revocation monitoring location on the Revocation Monitoring dashboard (true) or not (false).		
	WarningHours	An integer indicating the number of hours prior to expiration when the location begins to appear in a warning state on the dashboard.  WarningHours is required if Show is set to true and EndpointType is CRL.  WarningHours is not supported for EndpointType OCSP.		

Name	Description			
	Value	D	Description	
			the <i>Days</i> or <i>Weeks</i> value is selected in the Management Portal, it will be onverted to hours when stored in the database.	
Schedule	An array cont		ventory schedule set for the revocation monitoring location. Supported	
	Name	Name Description		
	Off	Turn off a	previously configured schedule.	
	Interval	specified p	parameter. Any interval that is selected in the UI will be converted to when stored in the database.	
		Name	Description	
		Minutes	An integer indicating the number of minutes between each interval.	
		For examp	ole, every hour:	
			rval": { nutes": 60	
	Daily	A dictiona the param	rry that indicates a job scheduled to run every day at the same time with neter:	
		Name	Description	
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
		For examp	ole, daily at 11:30 pm:	
		"Daily "Ti }	": { me": "2022-02-25T23:30:00Z"	

Name	Description		
	Note: Although the Swagger Example Value may show examples of various other schedules, only the schedules shown here—that are available in the Management Portal for this functionality—are valid for this endpoint.		
OCSPParameters	For OCSP endpoints only, an a are:	rray indicating the OCSP endpoint configuration. OCSP endpoint details	
	Value	Description	
	CertificateAuthorityId	An integer indicating the Keyfactor Command reference ID of the CA in the database.  Use the GET /CertificateAuthority method (see GET Certificate Authority on page 283) to retrieve a list of all the CAs to determine the ID.  This value will be null on a response if the endpoint was configured using the CertificateContents option.	
	AuthorityName	A string indicating the distinguished name of the CA. For example: CN=CorpIssuingCA1, DC=keyexample, DC=com	
	AuthorityNameId	A base 64 encoded SHA1 hash of the AuthorityName.	
	AuthorityKeyId	A base 64 encoded SHA1 hash of the CA certificate's public key. This value is found in the CA's certificate as the Subject Key Identifier (SKID).	
	SampleSerialNumber	A string indicating the serial number of the CA.	

# 2.2.18.3 GET Monitoring Revocation

The GET /Monitoring/Revocation method is used to retrieve all revocation monitoring locations. This method returns HTTP 200 OK on a success with details of both OCSP and CRL revocation endpoint configurations.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: WorkflowManagement: *Read* 

Table 305: GET Monitoring Revocation Input Parameters

Name	In	Description	
queryString	Query	A string containing a query to limit the results (e.g. field1 -eq value1 AND field2 -gt value2). The default is to return all records. Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns for the same feature. For querying guidelines, refer to the Keyfactor Command Reference Guide: Certificate Search Page. The query fields supported for this endpoint are:  • DashboardWarningValue (WarningHours value)  • DisplayName (Name)  • EndpointType (1-CRL, 2-OCSP)  • SendWarning (emailreminder) (true, false)  • ShowOnDashboard (true, false)  • Url  • WarningDays  Tip: To return all revocation monitoring locations of type CRL, use the following query:  EndpointType -eq 1  To return locations of type OCSP, use this query:  EndpointType -eq 2	
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.	
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.	
sortField	Query	A string containing the property by which the results should be sorted. Fields availabe for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>Name</i> .	
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.	

Table 306: GET Monitoring Revocation Response Data

Name	Description		
Id	An integer indicating the Keyfactor Command reference ID of the revocation monitoring location.		
Name	A string indicating the name of the revocation monitoring location.		
EndpointType	A string indicating the t	ype of revocation monitoring endpoint: OCSP or CRL.	
Location	A string indicating the location for the revocation monitoring endpoint.  For CRL endpoints, this can be either an HTTP location or an LDAP location. Be sure to monitor the CRL locations that are in use by applications in your environment—if you're monitoring LDAP locations but applications are using an HTTP location, you're not going to receive any warning if a CRL fails to publish to the HTTP location.  For OCSP endpoints, this is the full URL to the OCSP responder servicing this certificate authority's CRL.		
Email	For CRL endpoints only, an array indicating the email recipients and reminder schedule for reminder alerts. Email reminder details are:		
	Value	Description	
	EnableReminder	A Boolean indicating whether to send email reminders for this location (true) or not (false).	
	WarningDays	An integer indicating the number of days before expiration to send the warning email.	
	Recipients	An object containing a list of strings with email addresses to which the email reminders should be sent.	
Dashboard	An array indicating the	configuration for display on the dashboard. Dashboard details are:	
	Value	Description	
	Show	A Boolean indicating whether to show this revocation monitoring location on the Revocation Monitoring dashboard (true) or not (false).	
	WarningHours	An integer indicating the number of hours prior to expiration when the location begins to appear in a warning state on the dashboard.  WarningHours is required if Show is set to true and EndpointType is CRL.  WarningHours is not supported for EndpointType OCSP.	

Name	Description			
	Value	D	Description	
			the <i>Days</i> or <i>Weeks</i> value is selected in the Management Portal, it will be onverted to hours when stored in the database.	
Schedule	An array cont		ventory schedule set for the revocation monitoring location. Supported	
	Name	Name Description		
	Off	Turn off a	previously configured schedule.	
	Interval	specified p	parameter. Any interval that is selected in the UI will be converted to when stored in the database.	
		Name	Description	
		Minutes	An integer indicating the number of minutes between each interval.	
		For examp	ole, every hour:	
			rval": { nutes": 60	
	Daily	A dictiona the param	rry that indicates a job scheduled to run every day at the same time with neter:	
		Name	Description	
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
		For examp	ole, daily at 11:30 pm:	
		"Daily "Ti }	": { me": "2022-02-25T23:30:00Z"	

Name	Description		
	Note: Although the Swagger Example Value may show examples of various other schedules, only the schedules shown here—that are available in the Management Portal for this functionality—are valid for this endpoint.		
OCSPParameters	For OCSP endpoints only, an a are:	rray indicating the OCSP endpoint configuration. OCSP endpoint details	
	Value	Description	
	CertificateAuthorityId	An integer indicating the Keyfactor Command reference ID of the CA in the database.  Use the GET /CertificateAuthority method (see GET Certificate Authority on page 283) to retrieve a list of all the CAs to determine the ID.  This value will be null on a response if the endpoint was configured using the CertificateContents option.	
	AuthorityName	A string indicating the distinguished name of the CA. For example: CN=CorpIssuingCA1, DC=keyexample, DC=com	
	AuthorityNameId	A base 64 encoded SHA1 hash of the <i>AuthorityName</i> .	
	AuthorityKeyId	A base 64 encoded SHA1 hash of the CA certificate's public key. This value is found in the CA's certificate as the Subject Key Identifier (SKID).	
	SampleSerialNumber	A string indicating the serial number of the CA.	

# 2.2.18.4 POST Monitoring Revocation

The POST /Monitoring/Revocation method is used to add a revocation monitoring location. This method returns HTTP 200 OK on a success with details of the location.



**Tip:** The following permissions (see  $\underline{\text{Security Overview}}$ ) are required to use this feature: WorkflowManagement: *Modify* 

Table 307: POST Monitoring Revocation Input Parameters

Name	In	Description				
Name	Body	<b>Required</b> . A string indicating the name of the revocation monitoring location.				
EndpointType	Body	Required. A string indicating the type of revocation monitoring endpoint: OCSP or CRL.				
Location	Body	Required. A string indicating the location for the revocation monitoring endpoint.  For CRL endpoints, this can be either an HTTP location or an LDAP location. Be sure to monitor the CRL locations that are in use by applications in your environment—if you're monitoring LDAP locations but applications are using an HTTP location, you're not going to receive any warning if a CRL fails to publish to the HTTP location.  For OCSP endpoints, this is the full URL to the OCSP responder servicing this certificate authority's CRL.				
Email	Body		points. For CRL endpoints only, an array indicating the email recipedule for reminder alerts. Email reminder details are:			
		Value	Description			
		EnableReminder	A Boolean indicating whether to send email reminders for this location (true) or not (false). The default is false.			
		WarningDays	An integer indicating the number of days before expiration to send the warning email.			
			Recipients	An object containing a list of strings with email addresses to which the email reminders should be sent.		
Dashboard	Body	<b>Required</b> . An array indicating the configuration for display on the dashboard. Dashboard details are:				
		Value	Description			
					Show	<b>Required</b> . A Boolean indicating whether to show this revocation monitoring location on the Revocation Monitoring dashboard (true) or not (false). The default is false.
					WarningHours	Required*. An integer indicating the number of hours prior to expiration when the location begins to appear in a warning state on the dashboard.  WarningHours is required if Show is set to true and EndpointType is CRL.  WarningHours is not supported for EndpointType OCSP.  If the Days or Weeks value is selected in the Management Portal, it will be converted to hours when stored in the database.

Name	In	Description		
Schedule Body	An array containing the inventory schedule set for the revocation monitoring location. Supported schedules are:			
		Name	Description	
		Off	Turn off a previously configured schedule.	
		Interval	A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database.	
			Name Description	
			Minutes An integer indicating the number of minutes between each interval.	
			For example, every hour:	
			"Interval": {     "Minutes": 60 }	
		Daily	A dictionary that indicates a job scheduled to run every day at the same time with the parameter:	
			Name Description	
			Time The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
			For example, daily at 11:30 pm:	
			"Daily": {     "Time": "2022-02-25T23:30:00Z" }	
			Althorate the Common Supported Colors	
			e: Although the Swagger Example Value may show examples of various other dules, only the schedules shown here—that are available in the Management al for this functionality—are valid for this endpoint.	

Name	In	Description		
OCSPPara- meters	Body	<b>Required*.</b> for OCSP endpoints. For OCSP endpoints only, an array indicating the OCSP endpoint configuration. OCSP endpoint details are:		
		Value	Description	
		CertificateContents	A string indicating the certificate contents.	
		CertificateAuthorityId	An integer indicating the Keyfactor Command reference ID of the CA in the database.  Use the GET /CertificateAuthority method (see GET Certificate Authority on page 283) to retrieve a list of all the CAs to determine the ID.	

Table 308: POST Monitoring Revocation Response Data

Name	Description		
Name	A string indicating the name of the revocation monitoring location.		
EndpointType	A string indicating the type of revocation monitoring endpoint: OCSP or CRL.		
Location	A string indicating the location for the revocation monitoring endpoint.  For CRL endpoints, this can be either an HTTP location or an LDAP location. Be sure to monitor the CRL locations that are in use by applications in your environment—if you're monitoring LDAP locations but applications are using an HTTP location, you're not going to receive any warning if a CRL fails to publish to the HTTP location.  For OCSP endpoints, this is the full URL to the OCSP responder servicing this certificate authority's CRL.		
Email	For CRL endpoints only, alerts. Email reminder d	an array indicating the email recipients and reminder schedule for reminder letails are:	
	Value	Description	
	EnableReminder	A Boolean indicating whether to send email reminders for this location (true) or not (false).	
	WarningDays	An integer indicating the number of days before expiration to send the warning email.	
	Recipients	An object containing a list of strings with email addresses to which the email reminders should be sent.	
Dashboard	An array indicating the c	onfiguration for display on the dashboard. Dashboard details are:	
	Value	Description	
	Show	A Boolean indicating whether to show this revocation monitoring location on the Revocation Monitoring dashboard (true) or not (false).	
	WarningHours	An integer indicating the number of hours prior to expiration when the location begins to appear in a warning state on the dashboard.  WarningHours is required if Show is set to true and EndpointType is CRL.  WarningHours is not supported for EndpointType OCSP.  If the Days or Weeks value is selected in the Management Portal, it will be converted to hours when stored in the database.	

Name	Description			
Schedule	An array containing the inventory schedule set for the revocation monitoring location. Supported schedules are:			
	Name	Description		
	Off	Turn off a previ	Turn off a previously configured schedule.	
	Interval	specified paran	A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database.	
		Name	Description	
		Minutes	An integer indicating the number of minutes between each interval.	
		For example, ev	very hour:	
		"Interval" "Minute		
	Daily	A dictionary that the parameter:	at indicates a job scheduled to run every day at the same time with	
		Name	Description	
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
		For example, daily at 11:30 pm:		
		"Daily": {     "Time": }	"2022-02-25T23:30:00Z"	
	Note: Although the Swagger Example Value may show examples of variou only the schedules shown here—that are available in the Management Po tionality—are valid for this endpoint.		vn here—that are available in the Management Portal for this func-	
OCSPParameters	For OCSP end	lpoints only, an arr	ray indicating the OCSP endpoint configuration. OCSP endpoint details	

Name	Description		
	are:		
	Value	Description	
	CertificateAuthorityId	An integer indicating the Keyfactor Command reference ID of the CA in the database.  Use the GET /CertificateAuthority method (see GET Certificate Authority on page 283) to retrieve a list of all the CAs to determine the ID.  This value will be null on a response if the endpoint was configured using the CertificateContents option.	
	AuthorityName	A string indicating the distinguished name of the CA. For example: CN=CorpIssuingCA1, DC=keyexample, DC=com	
	AuthorityNameId	A base 64 encoded SHA1 hash of the AuthorityName.	
	AuthorityKeyId	A base 64 encoded SHA1 hash of the CA certificate's public key. This value is found in the CA's certificate as the Subject Key Identifier (SKID).	
	SampleSerialNumber	A string indicating the serial number of the CA.	

### 2.2.18.5 PUT Monitoring Revocation

The PUT /Monitoring/Revocation method is used to modify the revocation monitoring location. This method returns HTTP 200 OK on a success with details of the location.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: WorkflowManagement: *Modify* 



Warning: Any previously populated fields that are not submitted with their full existing data using this method will be cleared of their existing data. When using this method, you should first do a GET to retrieve all the values for the record you want to update, enter corrected data into the field(s) you want to update, and then submit all the fields using PUT, including the fields that contain values but which you are not changing.

Table 309: PUT Monitoring Revocation {id}Input Parameters

Name	In	Description					
Id	Path	<b>Required</b> . An integer indicating the Keyfactor Command reference ID of the revocation monitoring location.					
Name	Body	Required. A string indic	cating the name of the revocation monitoring location.				
EndpointType	Body	Required. A string indic	cating the type of revocation monitoring endpoint: OCSP or CRL.				
Location	Body	Required. A string indicating the location for the revocation monitoring endpoint.  For CRL endpoints, this can be either an HTTP location or an LDAP location. Be sure to monitor the CRL locations that are in use by applications in your environment—if you're monitoring LDAP locations but applications are using an HTTP location, you're not going to receive any warning if a CRL fails to publish to the HTTP location.  For OCSP endpoints, this is the full URL to the OCSP responder servicing this certificate authority's CRL.					
Email	Body	•	<b>Required</b> *. for CRL endpoints. For CRL endpoints only, an array indicating the email recipients and reminder schedule for reminder alerts. Email reminder details are:				
		Value	Description				
		EnableReminder	A Boolean indicating whether to send email reminders for this location (true) or not (false). The default is false.				
						WarningDays	An integer indicating the number of days before expiration to send the warning email.
		Recipients	An object containing a list of strings with email addresses to which the email reminders should be sent.				
Dashboard	Body	Required. An array indidetails are:	cating the configuration for display on the dashboard. Dashboard				
		Value	Description				
			Show	<b>Required</b> . A Boolean indicating whether to show this revocation monitoring location on the Revocation Monitoring dashboard (true) or not (false). The default is false.			
		WarningHours	Required*. An integer indicating the number of hours prior to expiration when the location begins to appear in a warning state on the dashboard.  WarningHours is required if Show is set to true and EndpointType				

Name	In	Description		
			ı	Description
			V	s CRL.  WarningHours is not supported for EndpointType OCSP.  f the Days or Weeks value is selected in the Management Portal, t will be converted to hours when stored in the database.
Schedule	Body	An array containing the inventory schedule set for the revocation monitoring lo Supported schedules are:		
		Name	Description	on
		Off	Turn off a	previously configured schedule.
		Interval	specified p	ry that indicates a job scheduled to run every x minutes with the parameter. Any interval that is selected in the UI will be converted as when stored in the database.
			Name	Description
			Minutes	An integer indicating the number of minutes between each interval.
			For examp	ole, every hour:
				val": { nutes": 60
		Daily		ry that indicates a job scheduled to run every day at the same the parameter:
			Name	Description
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
			For examp	ole, daily at 11:30 pm:

Name	In	Description		
		Name	Description	
			"Daily": {     "Time": }	"2022-02-25T23:30:00Z"
		sched	Note: Although the Swagger Example Value may show examples of various other schedules, only the schedules shown here—that are available in the Management Portal for this functionality—are valid for this endpoint.	
OCSPPara- meters	Body	<b>Required</b> *. for OCSP endpoints. For OCSP endpoints only, an array indicating the OCSP endpoint configuration. OCSP endpoint details are:		
		Value		Description
		CertificateC	ontents	A string indicating the certificate contents.
		CertificateA	uthorityId	An integer indicating the Keyfactor Command reference ID of the CA in the database.  Use the GET /CertificateAuthority method (see GET Certificate Authority on page 283) to retrieve a list of all the CAs to determine the ID.

Table 310: PUT Monitoring Revocation {id} Response Data

Name	Description			
ld	An integer indicating the Keyfactor Command reference ID of the revocation monitoring location.			
Name	A string indicating the name of the revocation monitoring location.			
EndpointType	A string indicating the t	type of revocation monitoring endpoint: OCSP or CRL.		
Location	A string indicating the location for the revocation monitoring endpoint.  For CRL endpoints, this can be either an HTTP location or an LDAP location. Be sure to monitor the CRL locations that are in use by applications in your environment—if you're monitoring LDAP locations but applications are using an HTTP location, you're not going to receive any warning if a CRL fails to publish to the HTTP location.  For OCSP endpoints, this is the full URL to the OCSP responder servicing this certificate authority's CRL.			
Email	For CRL endpoints only alerts. Email reminder	, an array indicating the email recipients and reminder schedule for reminder details are:		
	Value	Description		
	EnableReminder	A Boolean indicating whether to send email reminders for this location (true) or not (false).		
	WarningDays	An integer indicating the number of days before expiration to send the warning email.		
	Recipients	An object containing a list of strings with email addresses to which the email reminders should be sent.		
Dashboard	An array indicating the	configuration for display on the dashboard. Dashboard details are:		
	Value	Description		
	Show	A Boolean indicating whether to show this revocation monitoring location on the Revocation Monitoring dashboard (true) or not (false).		
	WarningHours	An integer indicating the number of hours prior to expiration when the location begins to appear in a warning state on the dashboard.  WarningHours is required if Show is set to true and EndpointType is CRL.  WarningHours is not supported for EndpointType OCSP.		

Name	Description			
	Value	D	Description	
			the <i>Days</i> or <i>Weeks</i> value is selected in the Management Portal, it will be onverted to hours when stored in the database.	
Schedule	An array cont		ventory schedule set for the revocation monitoring location. Supported	
	Name	Name Description		
	Off	Turn off a	previously configured schedule.	
	Interval	specified p	parameter. Any interval that is selected in the UI will be converted to when stored in the database.	
		Name	Description	
		Minutes	An integer indicating the number of minutes between each interval.	
		For examp	ole, every hour:	
			rval": { nutes": 60	
	Daily	A dictiona the param	rry that indicates a job scheduled to run every day at the same time with neter:	
		Name	Description	
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
		For examp	ole, daily at 11:30 pm:	
		"Daily "Ti }	": { me": "2022-02-25T23:30:00Z"	

Name	Note: Although the Swagger Example Value may show examples of various other schedules, only the schedules shown here—that are available in the Management Portal for this functionality—are valid for this endpoint.		
OCSPParameters	For OCSP endpoints only, an a are:	rray indicating the OCSP endpoint configuration. OCSP endpoint details	
	Value	Description	
	CertificateAuthorityId	An integer indicating the Keyfactor Command reference ID of the CA in the database.  Use the GET /CertificateAuthority method (see GET Certificate Authority on page 283) to retrieve a list of all the CAs to determine the ID.  This value will be null on a response if the endpoint was configured using the CertificateContents option.	
	AuthorityName	A string indicating the distinguished name of the CA. For example: CN=CorpIssuingCA1, DC=keyexample, DC=com	
	AuthorityNameId	A base 64 encoded SHA1 hash of the <i>AuthorityName</i> .	
	AuthorityKeyld	A base 64 encoded SHA1 hash of the CA certificate's public key.  This value is found in the CA's certificate as the Subject Key Identifier (SKID).	
	SampleSerialNumber	A string indicating the serial number of the CA.	

# 2.2.18.6 POST Monitoring Resolve OSCP

The POST /Monitoring/ResolveOCSP method is used to resolve the given OCSP certificate authority. This method returns HTTP 200 OK on a success with details of the location.



Table 311: POST Monitoring Resolve OCSP Input Parameters

Name	In	Description
CertificateContents	Body	Required*. A string indicating the certificate contents of a base-64 encoded PEM issued by the CA that you wish to resolve.  One of either <i>CertificateContents</i> or <i>CertificateAuthorityId</i> is required, but not both.
CertificateAuthorityId	Body	Required*. An integer indicating the Keyfactor Command reference ID of the CA in the database.  Use the GET / Certificate Authority method (see GET Certificate Authority on page 283) to retrieve a list of all the CAs to determine the ID.  One of either Certificate Contents or Certificate Authority Id is required, but not both.

Table 312: POST Monitoring Resolve OCSP Response Data

Name	Description
CertificateAuthorityId	An integer indicating the Keyfactor Command reference ID of the CA in the database.
AuthorityName	A string indicating the resolved certificate authority's name in X.500 format.
AuthorityNameId	A string indicating the hash of the certificate authority's name in hex format.
AuthorityKeyId	A string indicating the public key of the certificate authority's certificate.
SampleSerialNumber	A string indicating the serial number of the certificate authority's certificate.

# 2.2.18.7 POST Monitoring Revocation Test

The POST /Monitoring/Revocation/Test method is used to test email alerts for a single configured revocation monitoring endpoint. This method returns HTTP 200 OK on a success with details about the email message generated for each alert.



**Tip:** Alerts are generated when a CRL is expired or in the warning period as defined by the number of days configured in the *Email Reminder* setting. For example, if you had a CRL that expired on June 30 and configured the email reminder period to 15 days before expiration, the warning status would begin for that CRL on June 15 and CRL alerts would be generated. A warning will also appear for any CRL or OCSP locations that produced an error or couldn't be resolved.

When alerts are tested or sent on a schedule, corresponding message are also written to the system event log on the server where the Keyfactor Command service runs. For testing, this is true regardless of the setting of the *SendAlerts* flag. Information is logged to the event log for both locations that are in a good state (e.g. CRL resolves and is not in a warning or expired state or response from OCSP) and locations that



are in an error state (e.g. CRL resolves but is in the warning period or expired, CRL is expired, CRL or OCSP location does not resolve).



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature:

WorkflowManagement: *Read* WorkflowManagement: *Test* 

Table 313: POST Monitoring Revocation Test Input Parameters

Name	In	Description	
revocation Monitoring Alert Test Request	Body	Required. An array con Alert test detail values	ntaining information for the alert test. are:
		Name	Description
		AlertId	<b>Required</b> . An integer indicating the reference ID of revocation monitoring alert to test.
		EvaluationDate	Required. A string indicating the evaluation date/time for the test, in UTC.  You can use the date to simulate running the alerts a month from now instead of today, for example, or put in a date far in the future to be sure you pick up some expiring CRLs for testing purposes.
		SendAlerts	A Boolean indicating whether to send alert emails with the test (true) or not (false). The default is false.
		For example:	
		<pre>{     "EvaluationDat     "SendAlerts": }</pre>	te": "2022-08-31T20:51:33.528Z" true

Table 314: POST Monitoring Revocation Test Response Data

Parameter	Description		
RevocationMonitoringAlerts	An object containing alert details resulting from the test. Revocation monitoring alert details are:		
	Name	Description	
	Subject	A string indicating the email message subject for each alert. The content of this subject is not user configurable.	
	Message	A string indicating the email message that will be delivered for each alert. The content of this message is not user configurable.	
	Recipients	An object containing the recipient(s) for the alert.	
AlertBuildResult	A string indicating the outcome of the test (e.g. Success).		

### 2.2.18.8 POST Monitoring Revocation Test All

The POST /Monitoring/Revocation/Test method is used to test email alerts for all configured revocation monitoring endpoints. Alerts are generated when a CRL is expired or in the warning period as defined by the number of days configured in the *Email Reminder* setting or when an OCSP endpoint is unreachable. For example, if you had a CRL that expired on June 30 and configured the email reminder period to 15 days before expiration, the warning status would begin for that CRL on June 15 and CRL alerts would be generated. This method returns HTTP 200 OK on a success with details about the email message generated for each alert.



**Tip:** Alerts are generated when a CRL is expired or in the warning period as defined by the number of days configured in the *Email Reminder* setting. For example, if you had a CRL that expired on June 30 and configured the email reminder period to 15 days before expiration, the warning status would begin for that CRL on June 15 and CRL alerts would be generated. A warning will also appear for any CRL or OCSP locations that produced an error or couldn't be resolved.

When alerts are tested or sent on a schedule, corresponding message are also written to the system event log on the server where the Keyfactor Command service runs. For testing, this is true regardless of the setting of the *SendAlerts* flag. Information is logged to the event log for both locations that are in a good state (e.g. CRL resolves and is not in a warning or expired state or response from OCSP) and locations that are in an error state (e.g. CRL resolves but is in the warning period or expired, CRL is expired, CRL or OCSP location does not resolve).



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature:

WorkflowManagement: Read WorkflowManagement: Test

Table 315: POST Monitoring Revocation Test All Input Parameters

Name	In	Description	
revocation Monitoring Alert Test Request	Body	Required. An array con Alert test detail values a	taining information for the alert test.
		Name	Description
		EvaluationDate	Required. A string indicating the evaluation date/time for the test, in UTC.  You can use the date to simulate running the alerts a month from now instead of today, for example, or put in a date far in the future to be sure you pick up some expiring CRLs for testing purposes.
			SendAlerts
		For example:	
		<pre>{     "EvaluationDat     "SendAlerts": }</pre>	e": "2022-08-31T20:51:33.528Z" true

Table 316: POST Monitoring Revocation Test All Response Data

Parameter	Description		
RevocationMonitoringAlerts	An object containi details are:	ng alert details resulting from the test. Revocation monitoring alert	
	Name	Description	
	Subject	A string indicating the email message subject for each alert. The content of this subject is not user configurable.	
	Message	A string indicating the email message that will be delivered for each alert. The content of this message is not user configurable.	
	Recipients	An object containing the recipient(s) for the alert.	
AlertBuildResult	A string indicating the outcome of the test (e.g. Success).		

# 2.2.19 Orchestrator Jobs

The Orchestrator Jobs component of the Keyfactor API includes methods necessary to schedule orchestrator jobs and view the results of jobs.

Table 317: Orchestrator Jobs Endpoints

Endpoint	Method	Description	Link
/JobStatus/Data	GET	Retrieves the results of a custom job using the provided information.	GET Orchestrator Jobs Job Status Data on the next page
/JobHistory	GET	Returns the details of history records on orchestrator jobs, including in-process jobs.	GET Orchestrator Jobs Job History on page 687
/ScheduledJobs	GET	Returns the details of active scheduled jobs, including in-process jobs.	GET Orchestrator Jobs Sched- uled Jobs on page 692
/Custom	POST	Schedules a custom job on the orchestrator using the provided information.	POST Orchestrator Jobs Custom on page 696
/Reschedule	POST	Reschedules a failed orchestrator job.	POST Orchestrator Jobs Reschedule on page 700
/Unschedule	POST	Unschedules an active orchestrator job.	POST Orchestrator Jobs Unschedule on page 702
/Acknowledge	POST	Sets the status of a failed orchestrator job to acknowledged.	POST Orchestrator Jobs Acknowledge on page 703

Endpoint	Method	Description	Link
/Custom/Bulk	POST	Schedules a custom job on multiple orchestrator using the provided information.	POST Orchestrator Jobs Reschedule on page 700

### 2.2.19.1 GET Orchestrator Jobs Job Status Data

The GET /OrchestratorJobs/JobStatus/Data method is used to return the data generated from a completed custom orchestrator (a.k.a. agent) job for a given job ID. This method returns HTTP 200 OK on a success with up to 2 MB of data from the job results.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: AgentManagement: *Read* 



**Tip:** This method is used to return the log results from a Fetch Logs job initiated for the Keyfactor Universal Orchestrator. When used to return results for a Fetch Logs job, the last 2 MB of data from the orchestrator's log file are returned as a string in the Data field.



**Tip:** If jobs for the Keyfactor Universal Orchestrator fail with messages similar to the following: 2021-08-05 10:47:23.1940

Keyfactor.Orchestrators.JobExecutors.OrchestratorJobExecutor [Debug] - Response status code does not indicate success: 413 (Request Entity Too Large).

at System.Net.Http.HttpResponseMessage.EnsureSuccessStatusCode() in /\_ /src/System.Net.Http/src/System/Net/Http/HttpResponseMessage.cs:line 172

at Keyfactor.Orchestrators.Services.HttpService.SendPostAsync[T](String uri, Object requestData, Dictionary`2 headers) in F:\BuildAgents\Default1\\_ work\24\s\src\OrchestratorServices\HttpService.cs:line 38

This indicates that the amount of data being returned on the job is greater than IIS on the Keyfactor Command server is configured to accept. You will need to make modifications to the IIS settings on your Keyfactor Command server to allow it to accept larger incoming pieces of content. See the <a href="Fetch Logs">Fetch Logs</a> section of the Keyfactor Command Reference Guide for more information.

Table 318: GET Orchestrator Jobs Job Status Data Input Parameters

Name	In	Description
jobHistoryId	Query	Required. The Keyfactor Command reference ID of the orchestrator job.  Use the GET /OrchestratorJobs/JobHistory method (see GET Orchestrator Jobs JobHistory on the next page) to retrieve a list of jobs to determine the job's history ID.

Table 319: GET Orchestrator Jobs Job Status Data Response Data

Name	Description
JobHistoryId	An integer indicate the Keyfactor Command reference ID used to track progress during orchestrator jobs.
Data	A string containing up to 2 MB of data returned from the custom job.

# 2.2.19.2 GET Orchestrator Jobs Job History

The GET /OrchestratorJobs/JobHistory method is used to retrieve the status of an in progress or completed orchestrator (a.k.a. agent) job for a given job ID. This method returns HTTP 200 OK on a success with details of the requested orchestrator jobs.



Table 320: GET Orchestrator Jobs Job History Input Parameters

Name	In	Description
queryString	Query	A string containing a query to limit the results (e.g. field1 -eq value1 AND field2 -gt value2). The default is to return all records. Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns for the same feature. For querying guidelines, refer to the Keyfactor Command Reference Guide: Job History Search Feature. The query fields supported for this endpoint are:  • AgentId (The GUID of the orchestrator. Run GET Agents on page 12 to find the ID)  • Agent (ClientMachine)  • JobId  • Result (Job result: 4-Failure, 3-Warning, 2-Success, 0-Unknown)  • Status (Job status: 4-Acknowledged, 3-Completed, 2-InProcess, 1-Waiting, 0-Unknown, 5-CompletedWillRetry)  • JobType (Management, Inventory, Discovery, SsIDiscovery, Reenrollment, Monitoring, Sync, SSHSync)  • Message  • OperationStart (DateTime)  • ScheduleType (Schedule: null (Immediately), I_(Interval), D_(Daily), W_(Weekly),M_(Monthly), O_(Once))
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>JobHistoryId</i> .
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.

Table 321: GET Orchestrator Jobs Job History Response Data

Name	Description		
JobHistoryId	An integer indicating the Keyfactor Command reference ID used to track progress during orchestrator jobs.		
AgentMachine	A string indicating the name of the server on which the agent or orchestrator is installed. This is not necessarily the actual DNS name of the server; the orchestrator may have been installed using an alternative as a reference name.		
JobId	A string indicating	g the Keyfactor Command reference GUID assigned to the job.	
Schedule	The inventory schedule for the most recently run instance of the orchestrator job. Possible values a		
	Name	Description	
	Immediate	A Boolean that indicates a job scheduled to run immediately (true) or not (false).	
		Tip: In some instances, jobs initially scheduled as <i>Immediate</i> will appear on a GET as <i>null</i> .	
	Interval	A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database.	
		Name Description	
		Minutes An integer indicating the number of minutes between each interval.	
		For example, every hour:	
		"Interval": {     "Minutes": 60 }	
	Daily	A dictionary that indicates a job scheduled to run every day at the same time with the parameter:	

Name	Description			
	Name	Description		
		Name	Description	
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
		For example, da	ily at 11:30 pm:	
		"Daily": {     "Time": }	"2022-02-25T23:30:00Z"	
	Weekly	A dictionary that indicates a job scheduled to run on a specific day or days every week at the same time with the parameters:		
		Name	Description	
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
		Days	An array of values representing the days of the week on which to run the job. These can either be entered as integers (0 for Sunday, 1 for Monday, etc.) or as days of the week (e.g. "Sunday").	
		"Weekly": {     "Days":     "Mond     "Wedn     "Frid	[ day", nesday",	
	Monthly		t indicates a job scheduled to run on a specific day or days every me time with the parameters:	

Name	Description			
	Name Description			
		Name	Description	
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
		Day	The number of the day, in the month, to run the job.	
		"Monthly": "Day": 1		
	ExactlyOnce	A dictionary that parameter:	at indicates a job scheduled to run at the time specified with the	
		Name	Description	
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
		"ExactlyOnd	cactly once at 11:45 am: ce": { "2022-02-27T11:45:00Z"	
			some instances, jobs initially scheduled as <i>Immediate</i> will appear T as <i>ExactlyOnce</i> .	
JobType	A string indicating	the job type (e.g.	IISInventory).	
OperationStart	The time, in UTC,	The time, in UTC, at which the orchestrator job started.		
OperationEnd	The time, in UTC,	The time, in UTC, at which the orchestrator job finished.		
Message	A string providing	the error message	e for the operation, if any.	
Result	A string indicating  • Unknown	the result of the	orchestrator job. Possible values are:	

Name	Description
	<ul><li>Success</li><li>Warning</li><li>Failure</li></ul>
Status	A string indicating the status of the orchestrator job. Possible values are:  Unknown  Waiting  In Process  Completed  Acknowledged  Completed Will Retry
StorePath	A string indicating the path to the certificate store on the target. The format for this path will vary depending on the certificate store type. For example, for a Java keystore, this will be a file path (e.g. /opt/myapp/store.jks), but for an F5 device, this will be a partition name on the device (e.g. Common). See the Adding or Modifying a Certificate Store section of the Keyfactor Command Reference Guide for more information.
ClientMachine	A string indicating the name of the client machine. The value for this will vary depending on the certificate store type. For example, for a Java keystore or an F5 device, it is the hostname of the machine on which the store is located, but for an Amazon Web Services store, it is the FQDN of the Keyfactor Command Windows Orchestrator. See the Adding or Modifying a Certificate Store section of the Keyfactor Command Reference Guide for more information.

#### 2.2.19.3 GET Orchestrator Jobs Scheduled Jobs

The GET /OrchestratorJobs/ScheduledJobs method is used to retrieve orchestrator (a.k.a. agent) jobs that have active schedules. This includes jobs with ongoing schedules, such as inventory jobs that run periodically, and jobs that have been scheduled but have not yet been completed, such as management or discovery jobs. Both jobs that have not yet started and in-progress jobs are returned by this method. This method returns HTTP 200 OK on a success with details of the scheduled orchestrator jobs.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: AgentManagement: *Read* 

Table 322: GET Orchestrator Jobs Scheduled Jobs Input Parameters

Name	In	Description
queryString	Query	A string containing a query to limit the results (e.g. field1 -eq value1 AND field2 -gt value2). The default is to return all records. Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns for the same feature. For querying guidelines, refer to the Keyfactor Command Reference Guide: Job History Search Feature. The query fields supported for this endpoint are:  • AgentId (The GUID of the orchestrator. Run GET Agents on page 12 to find the ID)  • Agent Machine (ClientMachine)  • AgentPlatform (Platform types: 0-Unknown, 1NET, 2-Java, 3-Mac, 4-Android, 5-Native, 6-Bash, 7-Universal Orchestrator)  • JobType (Management, Inventory, Discovery, SsIDiscovery, Reenrollment, Monitoring, Sync, SSHSync)  • AgentType *Use -contains comparison (Capabilities in GET Agents on page 12)  • Requested (DateTime)  • ScheduleType (Schedule: null (Immediately), I_(Interval), D_(Daily), W_(Weekly),M_(Monthly), O_(Once))
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>Requested</i> .
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.

Table 323: GET Orchestrator Jobs Scheduled Jobs Response Data

Name	Description
ld	A string indicating the Keyfactor Command reference GUID assigned to the job.
ClientMachine	A string indicating the name of the client machine. The value for this will vary depending on the certificate store type. For example, for a Java keystore or an F5 device, it is the hostname of the machine on which the store is located, but for an Amazon Web Services store, it is the FQDN of the Keyfactor Command Windows Orchestrator. See the Adding or Modifying a Certificate Store section of the Keyfactor Command Reference Guide for more information.
Target	A string indicating the server name and path to the certificate store on the target (e.g. appsr-vr162.keyexample.com - /opt/app/store.cer). The server name included in the <i>Target</i> is the value from the <i>ClientMachine</i> . The format for the path will vary depending on the certificate store type. For example, for a Java keystore, this will be a file path (e.g. /opt/myapp/store.jks), but for an F5 device, this will be a partition name on the device (e.g. Common). Some types of jobs (e.g. discovery) have no path. See the <a href="Adding or Modifying a Certificate Store">Adding or Modifying a Certificate Store</a> section of the <i>Keyfactor Command Reference Guide</i> for more information.

Name	Description	
Schedule		
KEÝFACTO	R 10.1 Keyfactor Web APIs Reference Guide 6	95

Name	Description
Requested	The time, in UTC, at which the orchestrator job was initiated and added to the job queue.
JobType	A string indicating the job type (e.g. IISInventory).

### 2.2.19.4 POST Orchestrator Jobs Custom

The POST /OrchestratorJobs/Custom method is used to schedule a job with a custom job type on an orchestrator. This method returns HTTP 200 OK on a success with the GUID for the scheduled job.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: AgentManagement: *Modify* 



**Tip:** Data returned from a custom job once the job completes (e.g. a FetchLogs job) is stored in the Keyfactor Command database. To retrieve the data, use the *GET/OrchestratorJobs/JobHistory* method (see <u>GET Orchestrator Jobs Job History on page 687</u>) to determine the *JobHistoryId* of the completed job and then use the *GET/OrchestratorJobs/JobStatus/Data* method (see <u>GET Orchestrator Jobs Job Status Data on page 686</u>) to retrieve the data.

Table 324: POST Orchestrator Jobs Custom Input Parameters

Name	In	Description			
AgentId	Body	Required. A string indicating the Keyfactor Command reference GUID of the orchestrator that will execute this job.  To schedule a Fetch Logs job, use the GET /Agents method (see GET Agents on page 12) with a query of Status -eq 2 and Capabilities -contains "LOGS" to retrieve a list of your approved orchestrators with the LOGS capability to determine the ID of the orchestrator for which you want to retrieve logs.  To schedule a job using your custom job type, use the GET /Agents method (see GET Agents on page 12) with a query of Status -eq 2 to retrieve a list of your approved orchestrators to determine the ID of the orchestrator for which you want to schedule a custom job with your custom job type.			
JobTypeName	Body	<b>Required</b> . A string indicating the reference name for the custom job type for the job.  Use the <i>GET /JobTypes/Custom</i> method (see <u>GET Custom Job Types on page 556</u> ) to retrieve a list of your defined custom job types to determine the job type name to use.			
Schedule	Body	An object containing the schedule for the custom job. The following schedule types are supported:			
		Name Description			
		Off	Turn off a previously configured schedule.		
		Immediate	A Boolean that indicates a job scheduled to run immediately (true) or not (false).		
			Tip: In some instances, jobs initially scheduled as Immediate will appear on a GET as null.		
		Weekly	A dictionary that indicates a job scheduled to run on a specific day or days every week at the same time with the parameters:		
			Name	Description	
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	

Name	In	Description		
		Name	Description	
			Name	Description
			Days	An array of values representing the days of the week on which to run the job. These can either be entered as integers (0 for Sunday, 1 for Monday, etc.) or as days of the week (e.g. "Sunday").
			For example, every Monday, Wednesday and Friday at 5:30 pm:	
			<pre>"Weekly": {     "Days": [         "Monday",         "Wednesday",         "Friday" ],     "Time": "2022-02-27T17:30:00Z" }</pre>	
		Monthly	A dictionary that indicates a job scheduled to run on a specific day or days every month at the same time with the parameters:	
			Name	Description
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
			Day	The number of the day, in the month, to run the job.
			"Monthly": "Day": 1	

Name	In	Description				
		Name	Description			
		ExactlyOnce	A dictionary that indicates a job scheduled to run at the time specified with the parameter:			
			Name	Description		
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).		
			For example, ex	xactly once at 11:45 am:		
			_	"ExactlyOnce": {     "Time": "2022-02-27T11:45:00Z"		
			N/Z	some instances, jobs initially scheduled as iate will appear on a GET as ExactlyOnce.		
		Note: Although the Swagger Example Value may show examples of various other schedules, only the schedules shown here—that are available in the Management Portal for this functionality—are valid for this endpoint.				
		The default is <i>Imme</i>	diate.			
JobFields	Body	An array of key/value pairs that set the values for any optional job fields configured for the custom job type. The <i>key</i> is the field name and the <i>value</i> is the value for the field. For example:				
		"Favorite T	"JobFields": {     "Favorite Type of Pet": "Rat",     "Mother's Birthday": "1952-05-21" }			
		accept the o	default value, the f OrchestratorJobs/C	configured with a default value and you wish to field does not need to be submitted along with Custom request. The default value will be set immand. Submitting a value overrides the default		

Name	In	Description
		Use the <i>GET /JobTypes/Custom</i> method (see <u>GET Custom Job Types on page 556</u> ) to retrieve a list of your defined custom job types to determine the job fields defined for the job type.
		Tip: The built-in Fetch Logs job does not have any optional job fields.

Table 325: POST Orchestrator Jobs Custom Response Data

Name	Description
Jobid	A string indicating the Keyfactor Command reference GUID for the job.
OrchestratorId	A string indicating the Keyfactor Command reference GUID of the orchestrator that will execute this job.
JobTypeName	A string indicating the reference name for the custom job type for the job.
Schedule	An object containing the schedule for the custom job.
JobFields	An array of key/value pairs that set the values for any optional job fields configured for the custom job type.
RequestTimestmap	The date, in UTC, when the custom job was submitted.

#### 2.2.19.5 POST Orchestrator Jobs Reschedule

The POST /OrchestratorJobs/Reschedule method is used to reschedule a failed orchestrator job to retry. Jobs must have a result of Failed and a status of Completed or Acknowledged to be eligible for rescheduling. This endpoint returns 204 with no content upon success.

Only select types of jobs are eligible for rescheduling, including:

- Certificate Store Management
- Reenrollment
- Mac Auto-enrollment
- JKS, PEM and F5 Certificate Store Discovery
- SSH Synchronization
- Custom Jobs scheduled to run Weekly or Monthly

The following types of jobs cannot be rescheduled with this method:

Certificate Store Inventory
 Change the inventory schedule on certificate stores using POST /CertificateStores/Schedule (see <u>POST</u>

#### Certificate Stores Schedule on page 475).

- Custom Jobs scheduled to run Immediately or Exactly Once
  A new custom job should be scheduled after the problem is resolved using POST /OrchestratorJobs/Custom
  (see POST Orchestrator Jobs Custom on page 696).
- Fetch Logs
   A new fetch logs job should be scheduled after the problem is resolved using POST /OrchestratorJobs/Custom (see POST Orchestrator Jobs Custom on page 696).
- SSL Discovery and Monitoring Change the schedule on these using PUT /SSL/Networks (see PUT SSL Networks on page 1127).
- CA Synchronization for Remote CAs Managed with the Keyfactor Universal Orchestrator or Keyfactor Windows Orchestrator

Change the schedule on these using PUT /CertificateAuthority (see PUT Certificate Authority on page 322).



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: AgentManagement: *Modify* 

CertificateStoreManagement: Schedule

The required permissions will vary depending on the job type being rescheduled. The permissions shown above are appropriate for a certificate store management job.

Permissions for certificate stores can be set at either the global or certificate store container level. See *Container Permissions* in the *Keyfactor Command Reference Guide* for more information about global vs container permissions.



Tip: Be sure to resolve the problem that caused the job to fail before rescheduling it.

Table 326: POST Orchestrator Jobs Reschedule Input Parameters

Name	In	Description
JobAuditIds	Body	Required*. An array of integers indicating the job IDs of the failed jobs that should be scheduled to retry.  Use the GET /OrchestratorJobs/JobHistory method (see GET Orchestrator Jobs Job History on page 687) with a query similar to the following to retrieve a list of all orchestrator jobs potentially eligible for rescheduling:  JobType -ne "Inventory" AND Result -eq "4" AND (Status -eq "4" OR Status -eq "3")  Either a list of one or more JobAuditIds or a Query is required, but not both.
Query	Body	Required*. A string containing a query to identify the jobs to reschedule (e.g. field1 -eq value1 AND field2 -gt value2). Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns for the same feature. For querying guidelines, refer to the Keyfactor Command Reference Guide Job History Search Feature section.  Either a list of one or more JobAuditIds or a Query is required, but not both.

#### 2.2.19.6 POST Orchestrator Jobs Unschedule

The POST /OrchestratorJobs/Unschedule method is used to unschedule a scheduled orchestrator job. This endpoint returns 204 with no content upon success.

Only select types of jobs are eligible for unscheduling, including:

- Certificate Store Discovery and Management
- Reenrollment
- Mac Auto-enrollment
- Fetch Logs
- Custom Jobs

The following types of jobs cannot be unscheduled with this method:

- Certificate Store Inventory
   Change the inventory schedule on certificate stores using POST /CertificateStores/Schedule (see POST Certificate Stores Schedule on page 475).
- SSH Synchronization
   Change the schedule on these using PUT /SSH/ServerGroups (see <u>PUT SSH Server Groups on page 1010</u>).
- SSL Discovery and Monitoring Change the schedule on these using PUT /SSL/Networks (see PUT SSL Networks on page 1127).
- CA Synchronization for Remote CAs Managed with the Keyfactor Universal Orchestrator or Keyfactor Windows Orchestrator
  - Change the schedule on these using PUT /CertificateAuthority (see PUT Certificate Authority on page 322).



**Tip:** The following permissions (see Security Overview) are required to use this feature:

AgentManagement: *Modify* 

CertificateStoreManagement: Schedule

The required permissions will vary depending on the job type being unscheduled. The permissions shown above are appropriate for a certificate store management job.

Permissions for certificate stores can be set at either the global or certificate store container level. See *Container Permissions* in the *Keyfactor Command Reference Guide* for more information about global vs container permissions.

Table 327: POST Orchestrator Jobs Unschedule Input Parameters

Name	In	Description
Jobids	Body	Required*. An array of GUIDs indicating the job IDs of the jobs that should be unscheduled.  Use the GET /OrchestratorJobs/ScheduledJobs method (see GET Orchestrator Jobs Scheduled Jobs on page 692) with a query similar to the following to retrieve a list of all orchestrator jobs potentially eligible for unscheduling:  JobType -notcontains "SslDiscovery" AND JobType -notcontains "Monitoring" AND JobType -notcontains "Sync" AND JobType -notcontains "Sync" AND JobType - notcontains "Inventory"  Either a list of one or more JobIds or a Query is required, but not both.
Query	Body	Required*. A string containing a query to identify the jobs to unschedule (e.g. field1 -eq value1 AND field2 -gt value2). Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns for the same feature. For querying guidelines, refer to the Keyfactor Command Reference Guide Orchestrator Scheduled Job Search Feature section.  Either a list of one or more Joblds or a Query is required, but not both.

## 2.2.19.7 POST Orchestrator Jobs Acknowledge

The POST /OrchestratorJobs/Acknowledge method is used to set an orchestrator job to a status of acknowledged. Jobs must have a result of Failed or Warning and a status of Completed or CompletedWillRetry to be eligible for acknowledgment. Jobs that are in process or that have completed successfully cannot be set to a status of acknowledged. Setting a job to a status of acknowledged removes it from the count on the job history tab in the Keyfactor Command Management Portal (if the job falls within the count period defined by the Job Failures and Warnings Age Out (days) application setting—see Application Settings: Agents Tab in the Keyfactor Command Reference Guide). This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: AgentManagement: *Modify* 

Table 328: POST Orchestrator Jobs Acknowledge Input Parameters

Name	In	Description	
JobAuditIds	Body	Required*. An array of integers indicating the job IDs of the jobs that should be set to a status of acknowledged.  Use the GET /OrchestratorJobs/JobHistory method (see GET Orchestrator Jobs Job History on page 687) with a query similar to the following to retrieve a list of all orchestrator jobs potentially eligible for acknowledgement:  (Result -eq "4" OR Result -eq "3") AND (Status -eq "3" OR Status -eq "5")  Either a list of one or more JobAuditIds or a Query is required, but not both.	
Query	Body	Required*. A string containing a query to identify the jobs to acknowledge (e.g. field1 -e value1 AND field2 -gt value2). Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search drouwns for the same feature. For querying guidelines, refer to the Keyfactor Command Reference Guide Job History Search Feature section.  Either a list of one or more JobAuditIds or a Query is required, but not both.	

#### 2.2.19.8 POST Orchestrator Jobs Custom Bulk

The POST /OrchestratorJobs/Custom/Bulk method is used to schedule a job with a specified custom job type on multiple orchestrators at once. This method returns HTTP 200 OK on a success with the GUIDs for the scheduled jobs.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: AgentManagement: *Modify* 



**Tip:** Data returned from a custom job once the job completes (e.g. a FetchLogs job) is stored in the Keyfactor Command database. To retrieve the data, use the *GET/OrchestratorJobs/JobHistory* method (see <u>GET Orchestrator Jobs Job History on page 687</u>) to determine the *JobHistoryId* of the completed job and then use the *GET/OrchestratorJobs/JobStatus/Data* method (see <u>GET Orchestrator Jobs Job Status Data on page 686</u>) to retrieve the data.

Table 329: POST Orchestrator Jobs Custom Bulk Input Parameters

Name	In	Description			
Orches- tratorIds	Body	Required. A string indicating the Keyfactor Command referenced GUIDs of the orchestrators what will execute the jobs.  To schedule a Fetch Logs job, use the GET / Agents method (see GET Agents on page 12) with a query of Status -eq 2 and Capabilities -contains "LOGS" to retrieve a list of your approved orchestrators with the LOGS capability to determine the ID of the orchestrators for which you want to retrieve logs.  To schedule a job using your custom job type, use the GET / Agents method (see GET Agents on page 12) with a query of Status -eq 2 to retrieve a list of your approved orchestrators to determine the ID of the orchestrators for which you want to schedule a custom job with your custom job type.			
JobTypeName	Body	bulk operation c Use the GET /Job	Required. A string indicating the reference name for the custom job type for the job. A single bulk operation can only execute one job type.  Use the GET /JobTypes/Custom method (see GET Custom Job Types on page 556) to retrieve a list of your defined custom job types to determine the job type name to use.		
Schedule	Body	An object contai supported:  Name  Off  Immediate	Description  Turn off a previously configured schedule.  A Boolean that indicates a job scheduled to run immediately (true) or not (false).  Tip: In some instances, jobs initially scheduled as Immediate will appear on a GET as null.  A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database.  Name  Description  Minutes  An integer indicating the number of minutes between each interval.		

Name	In	Description		
		Name	Description	
			"Interval":     "Minutes	
		Daily	A dictionary tha	t indicates a job scheduled to run every day at the same arameter:
			Name	Description
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
			For example, da	ily at 11:30 pm:
			"Daily": {     "Time": }	"2022-02-25T23:30:00Z"
		Weekly		t indicates a job scheduled to run on a specific day or days ne same time with the parameters:
			Name	Description
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
			Days	An array of values representing the days of the week on which to run the job. These can either be entered as integers (0 for Sunday, 1 for Monday, etc.) or as days of the week (e.g. "Sunday").
			For example, ev "Weekly": {     "Days":     "Mond	1

Name	In	Description			
		Name	Description		
			"Frid	esday", ay" "2022-02-27T17:30:00Z"	
		Monthly	A dictionary that indicates a job scheduled to run on a specific day or days every month at the same time with the parameters:		
			Name	Description	
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
			Day	The number of the day, in the month, to run the job.	
			For example, on	the first of every month at 5:30 pm:	
		ExactlyOnce	"Monthly":  "Day": 1  "Time": }		
			A dictionary that indicates a job scheduled to run at the time specified with the parameter:		
			Name	Description	
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
			For example, exa	actly once at 11:45 am:	
			"ExactlyOnce": "Time": }	e": { "2022-02-27T11:45:00Z"	
			N/	ome instances, jobs initially scheduled as <i>Immediate</i> will on a GET as <i>ExactlyOnce</i> .	

Name	In	Description
		Note: Although the Swagger Example Value may show examples of various other schedules, only the schedules shown here—that are available in the Management Portal for this functionality—are valid for this endpoint.
		The default is <i>Immediate</i> .
JobFields	Body	An array of key/value pairs that set the values for any optional job fields configured for the custom job type. The <i>key</i> is the field name and the <i>value</i> is the value for the field. For example:
		"JobFields": {     "Favorite Type of Pet": "Rat",     "Mother's Birthday": "1952-05-21" }
		Note: If a job field has been configured with a default value and you wish to accept the default value, the field does not need to be submitted along with the POST /OrchestratorJobs/Custom request. The default value will be set automatically by Keyfactor Command. Submitting a value overrides the default value.
		Use the <i>GET /JobTypes/Custom</i> method (see <u>GET Custom Job Types on page 556</u> ) to retrieve a list of your defined custom job types to determine the job fields defined for the job type.
		Tip: The built-in Fetch Logs job does not have any optional job fields.

Table 330: POST Orchestrator Jobs Custom Bulk Response Data

Name	Description		
OrchestratorJobPairs	An array containing identifying information for each orchestrator on which the job will be run. Orchestrator job pair parameters include:		
	Value	Description	
	Jobid	A string indicating the Keyfactor Command reference GUID for the job.	
	OrchestratorId A string indicating the Keyfactor Command reference GUID of the orchestrator that will execute this job.		
JobTypeName	A string indicating the reference name for the custom job type for the job.		
Schedule	An object containing the schedule for the custom job.		
JobFields	An array of key/value pairs that set the values for any optional job fields configured for the custom job type.		
RequestTimestmap	The date, in UTC, when the custom job was submitted.		

## 2.2.20 PAM Providers

Privileged Access Management (PAM) functionality in Keyfactor Web APIs allows for configuration of third party PAM providers to secure certificate stores. In the current release, both CyberArk and Delinea (formerly Thycotic) are supported. The PAM component of the Keyfactor API includes methods necessary to programmatically create, delete, edit, and list PAM Providers.

Table 331: PamProviders Endpoints

Endpoint	Method	Description	Link
/{id}	DELETE	Deletes a PAM provider.	DELETE PAM Providers ID on the next page
/{id}	GET	Returns information for the specified PAM provider.	GET PAM Providers ID on the next page
/Types	GET	Returns a list of all available PAM provider types.	GET PAM Providers Types on page 718
/Types	POST	Creates a new PAM provider type.	POST PAM Providers Types on page 721
/	GET	Returns a list of all the configured PAM	GET PAM Providers on page 724

Endpoint	Method	Description	Link
		providers.	
/	POST	Creates a new PAM provider.	POST PAM Providers on page 733
/	PUT	Updates a PAM provider.	PUT PAM Providers on page 749

#### 2.2.20.1 DELETE PAM Providers ID

The DELETE /PamProviders/{id} method is used to delete a PAM provider by ID. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: PrivilegedAccessManagement: *Modify* 

Table 332: DELETE PamProviders {id} Input Parameters

Name	In	Description
id	Path	<b>Required</b> . The Keyfactor Command reference ID for the PAM provider to be deleted.  Use the <i>GET /PamProviders</i> method (see <u>GET PAM Providers on page 724</u> ) to retrieve a list of all the PAM providers to determine the PAM provider's ID.

### 2.2.20.2 GET PAM Providers ID

The GET /PamProviders/{id} method is used to return a PAM provider by ID. This method returns HTTP 200 OK on a success with details about the specified PAM provider.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: PrivilegedAccessManagement: *Read* 

Table 333: GET PamProviders {id} Input Parameters


Name	In	Description
id	Path	Required. The Keyfactor Command reference ID of the PAM provider to retrieve.  Use the GET /PAM/Providers method (see GET PAM Providers on page 724) to retrieve a list of all the PAM providers to determine the provider's ID.

Table 334: GET PamProviders {id} Response Data

Name	Description	Description			
ID	An integer indicating the Keyfactor Command reference ID for the PAM provider. This ID is automatically set by Keyfactor Command.				
Name		A string indicating the name of the PAM provider. This name used to identify the PAM provider throughout Keyfactor.			
Area	_	•	Command the provider is used for. PAM providers are used for certificate stores.		
ProviderType	An array containing details about the provider type for the provider. Provider type details include:		der type for the provider. Provider type details		
	Value	Description			
	Id	A string indicating provider type.	A string indicating the Keyfactor Command reference GUID for the provider type.		
	Name	A string indicating	A string indicating the name of the provider type.		
	Provider- TypeParams	Keyfactor Comma	neters that the provider type uses for data input in nd when creating new PAM provider and certi- ds. Provider type parameters values include:		
		Value	Description		
		Id	An integer indicating the Keyfactor Command reference ID for the PAM provider type parameter.		
		Name	A string indicating the internal name for the PAM provider type parameter.		
		DisplayName	A string indicating the display name for the PAM provider type parameter. For parameters with an <i>InstanceLevel</i> of <i>False</i> , this name appears on the PAM provider dialog for the parameter when a user creates a new PAM provider. For parameters with an		

Name	Description		
	Value	Description	
		Value	Description
			InstanceLevel of True, this name appears on the Server dialog for the parameter when a user creates a new PAM provider.
		DataType	An integer indicating the data type for the parameter. Possible values are:  • 1 = String  • 2 = Secret
		InstanceLevel	A Boolean that sets whether the parameter is used to define the underlying PAM provider (False) or a field that needs to be set to a value when configuring a certificate store to use the PAM provider (True).
			Example: For CyberArk when defining a PAM provider, you configure two CyberArk-specific fields:  • PrivateArk Safe: The name of the safe in CyberArk containing the certificate store password you wish to use.  • Application ID: The name of the application created in CyberArk for use with
			Keyfactor Command.  Because these fields are configured on the PAM provider definition, they appear as InstanceLevel=False like so:  {     "Id": 1,

Name	Description			
	Value	Description		
		Value	Description	
			"Name": "Safe",    "DisplayName": "PrivateArk Safe",    "DataType": 1,    "InstanceLevel": false,    "ProviderType": null }, {    "Id": 4,    "Name": "AppId",    "DisplayName": "Application ID",    "DataType": 1,    "InstanceLevel": false,    "ProviderType": null }  When you configure a certificate store to use CyberArk as a credential provider, you enter the name of the folder in the CyberArk safe where the protected object is stored and you enter the name of the projected object in the CyberArk safe containing the username or password used to access the certificate store. Because these fields are configured on the certificate store level, they appear as InstanceLevel-l=True like so:  {    "Id": 2,    "Name": "Folder",    "DisplayName": "PrivateArk Folder Name",    "DataType": 1,	



Name	Description				
	Value	Description			
		Value	Description		
			Value	Description	
				for the PAM provider type parameter.	
			ProviderTypeParams	An array of parameters that the provider type uses for data input in Keyfactor Command when creating new PAM provider and certificate store records.	
Provider- TypeParamValues	An array containing the Provider type paramet		der types specified by Provid	der Type Params.	
	Value	Description			
	Id	An integer indicating the Keyfactor Command reference ID for the PAM provider type parameter.			
	Value	A string indicating the value set for the parameter (e.g. the name of the CyberArk folder where the protected object that stores the user- name or password resides).			
	InstanceId		ng the Keyfactor Command e attaching to something wi		
	InstanceGuid		the Keyfactor Command rei		

Name	Description			
	Value	Description		
		be used.		
	Provider	An array containin	g information about the provider.	
	Provider- TypeParams	Keyfactor Comma	eters that the provider type uses for data input in and when creating new PAM provider and certise. Provider type parameters values include:	
		Value	Description	
		Id	An integer indicating the Keyfactor Command reference ID for the PAM provider type parameter.	
		Name	A string indicating the internal name for the PAM provider type parameter.	
		DisplayName	A string indicating the display name for the PAM provider type parameter. For parameters with an <i>InstanceLevel</i> of <i>False</i> , this name appears on the PAM provider dialog for the parameter when a user creates a new PAM provider. For parameters with an <i>InstanceLevel</i> of <i>True</i> , this name appears on the Server dialog for the parameter when a user creates a new PAM provider.	
		DataType	An integer indicating the data type for the parameter. Possible values are:  • 1 = String  • 2 = Secret	
		InstanceLevel	A Boolean that sets whether the parameter is used to define the underlying PAM provider (False) or a field that needs to be set to a value when configuring a certificate store to use the PAM provider (True).  See example, above.	
		ProviderType	An array containing details for the provider	

Name	Description			
	Value	Description		
		Value	Description	
			type. Provider type param	neters include:
			Value	Description
			Id	The Keyfactor Command reference GUID for the PAM provider type para- meter.
			Name	A string indicating the internal name for the PAM provider type parameter.
			ProviderTypeParams	An array of parameters that the provider type uses for data input in Keyfactor Command when creating new PAM provider and certificate store records.
SecureAreald	the PAM provider is ass You can create a single have opted to organize providers to match you	sociated with, if any.  PAM provider for each your certificate store or container organizat	d reference ID for the certif ch provider type (e.g. Cyber/ es into containers, you will n ion structure. The container e is supplied when creating a	Ark), however, if you eed to create multiple field in the PAM

Name	Description
	PAM provider can only be used with certificate stores in the matching container. Likewise, a PAM provider defined with no container would be available for selection when setting passwords for any certificate store that also did not specify a container. A PAM provider configured in this way could be used across a variety of certificate stores (e.g. both JKS and F5) as long as they were not in containers.

# 2.2.20.3 GET PAM Providers Types

The GET /PamProviders/Types method returns a list of all the PAM provider types that have been configured in Keyfactor Command. This method returns HTTP 200 OK on a success with details about each PAM provider type. This method has no input parameters.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature:

PrivilegedAccessManagement: Read

Table 335: GET PamProviders Types Response Data

Name	Description
Id	A string containing the Keyfactor Command reference GUID for the PAM provider type.
Name	A string containing the name of the PAM provider type.

## Name Description

ProviderTypeParams

An array containing parameters set for the PAM provider type.

Value	Description	Description	
Id	An integer indicating the ID of the type. Possible values are:		
	Value	Description	
	1	Private Ark Safe	
	2	PrivateArk Folder Name	
	3	PrivateArk Protected Password Name	
	4	Application ID	
	5	Secret Server Url	
	6	Rule Name	
	7	Thycotic Secret ID	
	8	Rule Key	
Name	A string indicative type paramet	ating the internal name for the PAM provider er.	
DisplayName	type paramet False, this nar parameter wh parameters w	ating the display name for the PAM provider er. For parameters with an <i>InstanceLevel</i> of me appears on the PAM provider dialog for the nen a user creates a new PAM provider. For with an <i>InstanceLevel</i> of <i>True</i> , this name appear dialog for the parameter when a user creates vider.	
DataType	An integer included ible values are  • 1 = Strii  • 2 = Seco	ng	
InstanceLevel	the underlyin	at sets whether the parameter is used to define g PAM provider (False) or a field that needs to lue when configuring a certificate store to use rider (True).	
	PAM fields	ple: For CyberArk when defining a provider, you configure two CyberArk-specific: PrivateArk Safe: The name of the safe in	

 Application ID: The name of the application created in CyberArk for use with Keyfactor Command.

# 2.2.20.4 POST PAM Providers Types

The POST /PamProviders/Types method creates a new PAM provider type. This method returns HTTP 200 OK on a success with details about the PAM provider type.




**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature:

PrivilegedAccessManagement: Modify

Table 336: POST PamProviders Types Input Parameters

Name	Description			
Name	A string containing the name of the PAM provider type.			
Parameters	An array containing pa	arameters for the provider type. Parameter details include:		
	Value	Description		
	Name	A string indicating the internal name for the PAM provider type parameter.		
	DisplayName	A string indicating the display name for the PAM provider type parameter. For parameters with an <i>InstanceLevel</i> of <i>False</i> , this name appears on the PAM provider dialog for the parameter when a user creates a new PAM provider. For parameters with an <i>InstanceLevel</i> of <i>True</i> , this name appears on the Server dialog for the parameter when a user creates a new PAM provider.		
	DataType	An integer indicating the data type for the parameter.  Possible values are:  1 = String  2 = Secret		
	InstanceLevel	A Boolean that sets whether the parameter is used to define the underlying PAM provider (False) or a field that needs to be set to a value when configuring a certificate store to use the PAM provider (True).		
		Example: For CyberArk when defining a PAM provider, you configure two CyberArk- specific fields:  • PrivateArk Safe: The name of the safe in CyberArk containing the certificate store password you wish to use.  • Application ID: The name of the application created in CyberArk for use with Keyfactor Command.  Because these fields are configured on the		
		PAM provider definition, they appear as InstanceLevel=False like so:		

Name	Description		
	Value	Description	
		{     "Id": 1,     "Name": "Safe",     "DisplayName": "PrivateArk     Safe",     "DataType": 1,     "InstanceLevel": false     "ProviderType": null },  {     "Id": 4,     "Name": "AppId",     "DisplayName": "Application  ID",     "DataType": 1,     "InstanceLevel": false     "ProviderType": null }  When you configure a certificate store to use CyberArk as a credential provider, you enter the name of the folder in the CyberArk safe where the protected object is stored and you enter the name of the projected object in the CyberArk safe containing the username or password used to access the certificate store. Because these fields are configured on the certificate store level, they appear as InstanceLevel=True like so:  {     "Id": 2,     "Name": "Folder",     "DisplayName": "PrivateArk Folder Name",     "DataType": 1,     "InstanceLevel": true     "ProviderType": null }, {     "Id": 3,     "Name": "Object",     "DisplayName": "PrivateArk	



### 2.2.20.5 GET PAM Providers

The GET /PamProviders method returns a list of all the PAM providers that have been configured in Keyfactor Command. This method returns HTTP 200 OK on a success with details about each PAM provider.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature:

PrivilegedAccessManagement: Read

Table 337: GET PamProviders Input Parameters


Name	In	Description
queryString	Query	A string containing a query to limit the results (e.g. field1 -eq value1 AND field2 -gt value2). The default is to return all records. Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns for the same feature. For querying guidelines, refer to the Keyfactor Command Reference Guide: Certificate Search Page. The query fields supported for this endpoint are:  • Area  • Name  • ProviderType  • SecuredAreald
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>Name</i> .
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.

Table 338: GET PamProviders Response Data

Name	Description	Description			
ID	An integer indicating the Keyfactor Command reference ID for the PAM provider. This ID is automatically set by Keyfactor Command.				
Name	A string indicating the throughout Keyfactor		ovider. This name used to identify the PAM provider		
Area		•	Command the provider is used for. PAM providers are used for certificate stores.		
ProviderType	An array containing details about the provider type for the provider. Provider type detail include:				
	Value	Description			
	Id	A string indicating the Keyfactor Command reference GUID for the provider type.			
	Name	A string indicating the name of the provider type.			
	Provider- TypeParams	An array of parameters that the provider type uses for data input in Keyfactor Command when creating new PAM provider and certificate store records. Provider type parameters values include:			
		Value	Description		
		Id	An integer indicating the Keyfactor Command reference ID for the PAM provider type parameter.		
		Name	A string indicating the internal name for the PAM provider type parameter.		
		DisplayName	A string indicating the display name for the PAM provider type parameter. For parameters with an <i>InstanceLevel</i> of <i>False</i> , this name appears on the PAM provider dialog for the parameter when a user creates a new PAM provider. For parameters with an		

Name	Description	Description			
	Value	Description			
		Value	Description		
			InstanceLevel of True, this name appears on the Server dialog for the parameter when a user creates a new PAM provider.		
		DataType	An integer indicating the data type for the parameter. Possible values are:  • 1 = String  • 2 = Secret		
		InstanceLevel	A Boolean that sets whether the parameter is used to define the underlying PAM provider (False) or a field that needs to be set to a value when configuring a certificate store to use the PAM provider (True).		
			Example: For CyberArk when defining a PAM provider, you configure two CyberArk-specific fields:  • PrivateArk Safe: The name of the safe in CyberArk containing the certificate store password you wish to use.  • Application ID: The name of the application created in CyberArk for use with Keyfactor Command.		
			Because these fields are configured on the PAM provider definition, they appear as InstanceLevel=False like so:		
			{     "Id": 1,		

Name	Description		
	Value	Description	
		Value	Description
			"Name": "Safe",    "DisplayName": "PrivateArk Safe",    "DataType": 1,    "InstanceLevel": false,    "ProviderType": null }, {    "Id": 4,    "Name": "AppId",    "DisplayName": "Application ID",    "DataType": 1,    "InstanceLevel": false,    "ProviderType": null }  When you configure a certificate store to use CyberArk as a credential provider, you enter the name of the folder in the CyberArk safe where the protected object is stored and you enter the name of the projected object in the CyberArk safe containing the username or password used to access the certificate store. Because these fields are configured on the certificate store level, they appear as InstanceLevel-l=True like so:  {    "Id": 2,    "Name": "Folder",    "DisplayName": "PrivateArk Folder Name",    "DataType": 1,



Name	Description					
	Value	Description	Description			
		Value	Description			
			Value	Description		
				for the PAM provider type parameter.		
			ProviderTypeParams	An array of parameters that the provider type uses for data input in Keyfactor Command when creating new PAM provider and certificate store records.		
Provider- TypeParamValues	An array containing the Provider type parameter		der types specified by Provid	der Type Params.		
	Value	Description				
	Id	An integer indicating the Keyfactor Command reference ID for the PAM provider type parameter.				
	Value	A string indicating the value set for the parameter (e.g. the name of the CyberArk folder where the protected object that stores the username or password resides).				
	InstanceId		An integer indicating the Keyfactor Command reference ID for the provider. If you are attaching to something with an integer Id, this will be used.			
	InstanceGuid		the Keyfactor Command rei e attaching to something wi			

Name	Description			
	Value	Description		
		be used.		
	Provider	An array containin	g information about the provider.	
	Provider- TypeParams	An array of parameters that the provider type uses for data input in Keyfactor Command when creating new PAM provider and certificate store records. Provider type parameters values include:		
		Value	Description	
		Id	An integer indicating the Keyfactor Command reference ID for the PAM provider type parameter.	
		Name	A string indicating the internal name for the PAM provider type parameter.	
		DisplayName	A string indicating the display name for the PAM provider type parameter. For parameters with an <i>InstanceLevel</i> of <i>False</i> , this name appears on the PAM provider dialog for the parameter when a user creates a new PAM provider. For parameters with an <i>InstanceLevel</i> of <i>True</i> , this name appears on the Server dialog for the parameter when a user creates a new PAM provider.	
		DataType	An integer indicating the data type for the parameter. Possible values are:  • 1 = String • 2 = Secret	
		InstanceLevel	A Boolean that sets whether the parameter is used to define the underlying PAM provider (False) or a field that needs to be set to a value when configuring a certificate store to use the PAM provider (True).  See example, above.	
		ProviderType	An array containing details for the provider	

Name	Description			
	Value	Description		
		Value	Description	
			type. Provider type param	neters include:
			Value	Description
			Id	The Keyfactor Command reference GUID for the PAM provider type para- meter.
			Name	A string indicating the internal name for the PAM provider type parameter.
			ProviderTypeParams	An array of parameters that the provider type uses for data input in Keyfactor Command when creating new PAM provider and certificate store records.
SecureAreald	the PAM provider is ass You can create a single have opted to organize providers to match you	sociated with, if any.  PAM provider for each your certificate store r container organizat	nd reference ID for the certif ch provider type (e.g. Cyber/ es into containers, you will n ion structure. The container e is supplied when creating a	Ark), however, if you eed to create multiple field in the PAM

Name	Description
	PAM provider can only be used with certificate stores in the matching container. Likewise, a PAM provider defined with no container would be available for selection when setting passwords for any certificate store that also did not specify a container. A PAM provider configured in this way could be used across a variety of certificate stores (e.g. both JKS and F5) as long as they were not in containers.

### 2.2.20.6 POST PAM Providers

The POST /PamProviders method creates a new PAM provider. This method returns HTTP 200 OK on a success with details for the new provider.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature:

CertificateStoreManagement: *Modify* PrivilegedAccessManagement: *Modify* 

Table 339: POST PamProviders Input Parameters

Name	In	Description			
Name	Body	<b>Required</b> . A string indicating the name of the PAM provider. This name used to identify the PAM provider throughout Keyfactor.			
Area	Body	An integer indicating the area of Keyfactor Command the provider is used for. PAM providers generally have a value of 1, indicating they are used for certificate stores.			
ProviderType	Body	An array containing details about the provider type for the provider. Provider type details include:			
		Value	Description		
		Id	A string indicating the Keyfactor Command reference GUID for the provider type.		
		Name	A string indicating the name of the provider type.		
		Provider- TypeParams	An array of parameters that the provider type uses for data input in Keyfactor Command when creating new PAM provider and certificate store records. Provider type parameters values include:		
			Value	Description	
			Id	An integer indicating the Keyfactor Command reference ID for the PAM provider type parameter.	
			Name	A string indicating the internal name for the PAM provider type parameter.	
		DisplayNam- e	A string indicating the display name for the PAM provider type parameter. For parameters with an <i>InstanceLevel</i> of <i>False</i> , this name appears on the PAM provider dialog for the parameter when a user creates a new PAM provider. For parameters with an <i>InstanceLevel</i> of <i>True</i> , this name appears on the Server dialog for the parameter when a user creates a new PAM provider.		

Name	In	Description			
		Value	Description		
			Value	Description	
			DataType	An integer indicating the data type for the parameter. Possible values are:  • 1 = String  • 2 = Secret	
			InstanceLev- el	A Boolean that sets whether the parameter is used to define the underlying PAM provider (False) or a field that needs to be set to a value when configuring a certificate store to use the PAM provider (True).	
				Example: For CyberArk when defining a PAM provider, you configure two CyberArk-specific fields:  • PrivateArk Safe: The name of the safe in CyberArk containing the certificate store password you wish to use.  • Application ID: The name of the application created in CyberArk for use with Keyfactor Command.  Because these fields are configured on the PAM provider definition, they appear as InstanceLevel=False like so:	
				{     "Id": 1,     "Name": "Safe",     "DisplayName":	

Name	In	Description		
		Value	Description	
			Value	Description
				"PrivateArk Safe",     "DataType": 1,     "InstanceLevel": false,     "ProviderType": null }, {     "Id": 4,     "Name": "AppId",     "DisplayName":     "Application ID",     "DataType": 1,     "InstanceLevel": false,     "ProviderType": null }  When you configure a certificate store to use CyberArk as a credential provider, you enter the name of the folder in the CyberArk safe where the protected object is stored and you enter the name of the projected object in the CyberArk safe containing the username or password used to access the certificate store. Because these fields are configured on the certi- ficate store level, they appear as InstanceLevel=True like so:  {     "Id": 2,

Name	In	Description				
		Value	Description	Description		
			Value	Description		
			"Disp "Private Name", "Data "Inst true, "Prov null }, { "Id": "Name "Disp "Private Password "Data "Inst true, "Prov null }  In both case fields (e.g. th the object in	": "Object", layName": Ark Protected Name", Type": 1, anceLevel": iderType":  s, the values for the he actual name of CyberArk where d is stored) are		
				stored in the TypeParamV		
			Provider- Type	An array containing of provider type. Provider include:		
				Value	Description	
				Id	The Keyfactor	

Name	In	Description			
		Value	Description		
			Value	Description	
				Value	Description
					Command reference GUID for the PAM provider type para- meter.
				Name	A string indicating the internal name for the PAM provider type parameter.
				Provider- TypeParams	An array of parameters that the provider type uses for data input in Keyfactor Command when creating new PAM provider and certificate store records.
Provider- TypeParamValues	Body	An array containing the Provider type parame		ovider types specified b	y ProviderTypeParams.

Name	In	Description			
		Value	Description		
		Id		er type parameter.	
		Value	name of the Cyb	ng the value set for the parameter (e.g. the erArk folder where the protected object that ame or password resides).	
		InstanceId	_	oting the Keyfactor Command reference ID for ou are attaching to something with an integer ed.	
		InstanceGuid		g the Keyfactor Command reference GUID for ou are attaching to something with a GUID ID,	
		Provider	An array containing information about the provider.		
		Provider- TypeParams	input in Keyfacto	meters that the provider type uses for data or Command when creating new PAM provider tore records. Provider type parameters values	
			Value	Description	
			Id	An integer indicating the Keyfactor Command reference ID for the PAM provider type parameter.	
			Name	A string indicating the internal name for the PAM provider type parameter.	
			DisplayNam- e	A string indicating the display name for the PAM provider type parameter. For parameters with an <i>InstanceLevel</i> of <i>False</i> , this name appears on the PAM provider dialog for the parameter when a user creates a new PAM provider. For parameters with an <i>InstanceLevel</i> of <i>True</i> , this name appears on the Server dialog for the parameter when a user	

Name	In	Description			
		Value	Description		
			Value	Description	
				creates a new PAM pro	vider.
			DataType	An integer indicating the the parameter. Possible  • 1 = String  • 2 = Secret	
			InstanceLev- el	A Boolean that sets wh meter is used to define PAM provider (False) o to be set to a value who certificate store to use (True). See example, above.	the underlying r a field that needs en configuring a
			Provider- Type	An array containing det provider type. Provider include:	
				Value	Description
				ld	The Keyfactor Command reference GUID for the PAM provider type para- meter.
				Name	A string indicating the internal name for the PAM provider type parameter.


Name	In	Description			
		Value	Description		
			Value	Description	
				Value	Description
				Provider- TypeParams	An array of parameters that the provider type uses for data input in Keyfactor Command when creating new PAM provider and certificate store records.
SecureAreald	Body	container the PAM pr You can create a singly you have opted to org create multiple provided field in the PAM provider, the Pamatching container. Lable for selection who specify a container. A	rovider is associated le PAM provider for ganize your certificaters to match your ider definition is no PAM provider can outlikewise, a PAM provider consetting password PAM provider consetting password PAM provider consetting password provider consetting password password provider consetting password provider password provider consetting password provider passwor	mand reference ID for the d with, if any.  If each provider type (e.g. ate stores into containers container organization stor required, but if one is solved by the used with certificate ovider defined with no colds for any certificate store figured in this way could be a with the colds and F5) as long as they were discounted to the container or the colds.	CyberArk), however, if , you will need to ructure. The container upplied when creating te stores in the ntainer would be available that also did not be used across a

Table 340: POST PamProviders Response Data

Name	Description				
ID	_	An integer indicating the Keyfactor Command reference ID for the PAM provider. This ID is automatically set by Keyfactor Command.			
Name	A string indicating t throughout Keyfact		ovider. This name used to identify the PAM provider		
Area	_	•	Command the provider is used for. PAM providers are used for certificate stores.		
ProviderType	An array containing include:	An array containing details about the provider type for the provider. Provider type details include:			
	Value	Description			
	Id	A string indicating provider type.	the Keyfactor Command reference GUID for the		
	Name	A string indicating	A string indicating the name of the provider type.		
	Provider- TypeParams	An array of parameters that the provider type uses for data input in Keyfactor Command when creating new PAM provider and certificate store records. Provider type parameters values include:			
		Value	Description		
		Id	An integer indicating the Keyfactor Command reference ID for the PAM provider type parameter.		
		Name	A string indicating the internal name for the PAM provider type parameter.		
		DisplayName	A string indicating the display name for the PAM provider type parameter. For parameters with an <i>InstanceLevel</i> of <i>False</i> , this name appears on the PAM provider dialog for the parameter when a user creates a new PAM provider. For parameters with an		

Name	Description				
	Value	Description	Description		
		Value	Description		
			InstanceLevel of True, this name appears on the Server dialog for the parameter when a user creates a new PAM provider.		
		DataType	An integer indicating the data type for the parameter. Possible values are:  • 1 = String  • 2 = Secret		
		InstanceLevel	A Boolean that sets whether the parameter is used to define the underlying PAM provider (False) or a field that needs to be set to a value when configuring a certificate store to use the PAM provider (True).		
			Example: For CyberArk when defining a PAM provider, you configure two CyberArk-specific fields:  • PrivateArk Safe: The name of the safe in CyberArk containing the certificate store password you wish to use.  • Application ID: The name of the application created in CyberArk for use with		
			Keyfactor Command.  Because these fields are configured on the PAM provider definition, they appear as InstanceLevel=False like so:  {     "Id": 1,		

Name	Description		
	Value	Description	
		Value	Description
			"Name": "Safe",    "DisplayName": "PrivateArk Safe",    "DataType": 1,    "InstanceLevel": false,    "ProviderType": null }, {    "Id": 4,    "Name": "AppId",    "DisplayName": "Application ID",    "DataType": 1,    "InstanceLevel": false,    "ProviderType": null }  When you configure a certificate store to use CyberArk as a credential provider, you enter the name of the folder in the CyberArk safe where the protected object is stored and you enter the name of the projected object in the CyberArk safe containing the username or password used to access the certificate store. Because these fields are configured on the certificate store level, they appear as InstanceLevel-l=True like so:  {    "Id": 2,    "Name": "Folder",    "DisplayName": "PrivateArk Folder Name",    "DataType": 1,



Name	Description						
	Value	Description					
		Value	Description	Description			
			Value	Description			
				for the PAM provider type parameter.			
	An array containing	the values for the nr.	ProviderTypeParams  Divider types specified by Provider types specified by Provider	An array of parameters that the provider type uses for data input in Keyfactor Command when creating new PAM provider and certificate store records.			
Provider- TypeParamValues		meter values include:	ovider types specified by Frovid	act typer arams.			
	Value	Description					
	Id	An integer indicating the Keyfactor Command reference I PAM provider type parameter.					
	Value	the CyberArk fo	A string indicating the value set for the parameter (e.g. the the CyberArk folder where the protected object that store name or password resides).				
	InstanceId		cating the Keyfactor Command are attaching to something wi				
	InstanceGuid		ing the Keyfactor Command re are attaching to something wi				

Name	Description		
	Value	Description	
		be used.	
	Provider	An array containin	g information about the provider.
	Provider- TypeParams	Keyfactor Comma	eters that the provider type uses for data input in and when creating new PAM provider and certise. Provider type parameters values include:
		Value	Description
		Id	An integer indicating the Keyfactor Command reference ID for the PAM provider type parameter.
		Name	A string indicating the internal name for the PAM provider type parameter.
		DisplayName	A string indicating the display name for the PAM provider type parameter. For parameters with an <i>InstanceLevel</i> of <i>False</i> , this name appears on the PAM provider dialog for the parameter when a user creates a new PAM provider. For parameters with an <i>InstanceLevel</i> of <i>True</i> , this name appears on the Server dialog for the parameter when a user creates a new PAM provider.
		DataType	An integer indicating the data type for the parameter. Possible values are:  • 1 = String  • 2 = Secret
		InstanceLevel	A Boolean that sets whether the parameter is used to define the underlying PAM provider (False) or a field that needs to be set to a value when configuring a certificate store to use the PAM provider (True).  See example, above.
		ProviderType	An array containing details for the provider

Name	Description			
	Value	Description		
		Value	Description	
			type. Provider type param	neters include:
			Value	Description
			Id	The Keyfactor Command reference GUID for the PAM provider type para- meter.
			Name	A string indicating the internal name for the PAM provider type parameter.
			ProviderTypeParams	An array of parameters that the provider type uses for data input in Keyfactor Command when creating new PAM provider and certificate store records.
SecureAreald	the PAM provider is ass You can create a single have opted to organize providers to match you	sociated with, if any.  PAM provider for each your certificate store r container organizat	nd reference ID for the certif ch provider type (e.g. Cyber/ es into containers, you will n ion structure. The container e is supplied when creating a	Ark), however, if you eed to create multiple field in the PAM

Name	Description
	PAM provider can only be used with certificate stores in the matching container. Likewise, a PAM provider defined with no container would be available for selection when setting passwords for any certificate store that also did not specify a container. A PAM provider configured in this way could be used across a variety of certificate stores (e.g. both JKS and F5) as long as they were not in containers.

## 2.2.20.7 PUT PAM Providers

The PUT /PamProviders method updates an existing PAM provider. This method returns HTTP 200 OK on a success with details for the updated provider.



**Tip:** The following permissions (see Security Overview) are required to use this feature:

CertificateStoreManagement: *Modify* PrivilegedAccessManagement: Modify

SystemSettings: Read




Warning: Any previously populated fields that are not submitted with their full existing data using this method will be cleared of their existing data. When using this method, you should first do a GET to retrieve all the values for the record you want to update, enter corrected data into the field(s) you want to update, and then submit all the fields using PUT, including the fields that contain values but which you are not changing.

Table 341: PUT PamProviders Input Parameters

Name	In	Description									
ID	Body	<b>Required</b> . An integer indicating the Keyfactor Command reference ID for the PAM provider. This ID is automatically set by Keyfactor Command.									
Name	Body	Required. A string ind the PAM provider thr		f the PAM provider. This name used to identify							
Area	Body			or Command the provider is used for. PAM dicating they are used for certificate stores.							
ProviderType	Body	An array containing details about the provider type for the provider.									
		Value	Description								
		Id	A string indicating the Keyfactor Command reference GUID for the provider type.								
		Name	A string indicating	ng the name of the provider type.							
		Provider- TypeParams		meters that the provider type uses for data or Command when creating new PAM provider tore records.							
			Value	Description							
				Id	An integer indicating the Keyfactor Command reference ID for the PAM provider type parameter.						
										Name	A string indicating the internal name for the PAM provider type parameter.
			DisplayNam- e	A string indicating the display name for the PAM provider type parameter. For parameters with an <i>InstanceLevel</i> of <i>False</i> , this name appears on the PAM provider dialog for the parameter when a user creates a new PAM provider. For parameters with an <i>InstanceLevel</i> of <i>True</i> , this name appears on the Server dialog for the parameter when a user creates a new PAM provider.							

Name In	Description		
	Value	Description	
		Value	Description
		DataType	An integer indicating the data type for the parameter. Possible values are:  • 1 = String  • 2 = Secret
		InstanceLev- el	A Boolean that sets whether the parameter is used to define the underlying PAM provider (False) or a field that needs to be set to a value when configuring a certificate store to use the PAM provider (True).
			Example: For CyberArk when defining a PAM provider, you configure two CyberArk-specific fields:  • PrivateArk Safe: The name of the safe in CyberArk containing the certificate store password you wish to use.  • Application ID: The name of the application created in CyberArk for use with Keyfactor Command.  Because these fields are configured on the PAM provider definition, they appear as InstanceLevel=False like so:  {     "Id": 1,     "Name": "Safe",     "DisplayName":

Name	In	Description		
		Value	Description	
			Value	Description
				"PrivateArk Safe",     "DataType": 1,     "InstanceLevel":     false,         "ProviderType":     null     },     {         "Id": 4,         "Name": "AppId",         "DisplayName":         "Application ID",         "DataType": 1,         "InstanceLevel":         false,             "ProviderType":         null     }  When you configure a certificate store to use CyberArk as a credential provider, you enter the name of the folder in the CyberArk safe where the protected object is stored and you enter the name of the projected object in the CyberArk safe containing the username or password used to access the certificate store. Because these fields are configured on the certificate store level, they appear as InstanceLevel=True like so:



Name	In	Description			
		Value	Description		
			Value	Description	
				Value	Description
					reference GUID for the PAM provider type para- meter.
				Name	A string indicating the internal name for the PAM provider type parameter.
				Provider- TypeParams	An array of parameters that the provider type uses for data input in Keyfactor Command when creating new PAM provider and certificate store records.
Provider- TypeParamValues	Body	An array containing t	he values for the p	rovider types specified l	by ProviderTypeParams.
		Id		ating the Keyfactor Comer type parameter.	nmand reference ID for

Name	In	Description		
		Value	Description	
		Value	name of the Cyb	ng the value set for the parameter (e.g. the perArk folder where the protected object that ame or password resides).
		InstanceId	_	ating the Keyfactor Command reference ID for you are attaching to something with an integer sed.
		InstanceGuid	_	ng the Keyfactor Command reference GUID for you are attaching to something with a GUID ID,
		Provider Provider- TypeParams	An array contain	ning information about the provider.
				meters that the provider type uses for data or Command when creating new PAM provider tore records.
			Value	Description
			Id	An integer indicating the Keyfactor Command reference ID for the PAM provider type parameter.
			Name	A string indicating the internal name for the PAM provider type parameter.
			DisplayNam- e	A string indicating the display name for the PAM provider type parameter. For parameters with an <i>InstanceLevel</i> of <i>False</i> , this name appears on the PAM provider dialog for the parameter when a user creates a new PAM provider. For parameters with an <i>InstanceLevel</i> of <i>True</i> , this name appears on the Server dialog for the parameter when a user creates a new PAM provider.
			DataType	An integer indicating the data type for the parameter. Possible values are:

Name	In	Description			
		Value	Description		
			Value	Description	
				<ul><li>1 = String</li><li>2 = Secret</li></ul>	
			InstanceLev- el	A Boolean that sets who meter is used to define PAM provider (False) of to be set to a value who certificate store to use (True).  See example, above.	the underlying r a field that needs en configuring a
		Provider- Type	An array containing det provider type.	ails for the	
				Value	Description
				ld	The Keyfactor Command reference GUID for the PAM provider type para- meter.
				Name	A string indicating the internal name for the PAM provider type parameter.
				Provider- TypeParams	An array of parameters that the


Name	In	Description			
		Value	Description		
			Value	Description	
				Value	Description
					provider type uses for data input in Keyfactor Command when creating new PAM provider and certi- ficate store records.
SecureAreald	Body	container the PAM pr You can create a singlyou have opted to orgete eater multiple provided in the PAM provider, the Patching container. Lable for selection whe specify a container. A	ovider is associated e PAM provider for ganize your certificaters to match your dider definition is no PAM provider can or ikewise, a PAM proen setting password PAM provider conf	nand reference ID for the with, if any. each provider type (e.g. te stores into containers container organization st trequired, but if one is so ally be used with certificate vider defined with no colors for any certificate store igured in this way could land F5) as long as they was a single provider with the colors for any certificate store igured in this way could land F5) as long as they was a single provider with the colors of t	CyberArk), however, if , you will need to ructure. The container upplied when creating te stores in the ntainer would be avail- e that also did not be used across a

Table 342: PUT PamProviders Response Data

Name	Description				
ID		An integer indicating the Keyfactor Command reference ID for the PAM provider. This ID is automatically set by Keyfactor Command.			
Name	A string indicating the throughout Keyfactor		ovider. This name used to identify the PAM provider		
Area		•	Command the provider is used for. PAM providers are used for certificate stores.		
ProviderType	An array containing de include:	An array containing details about the provider type for the provider. Provider type details include:			
	Value	Description			
	Id	A string indicating the Keyfactor Command reference GUID for the provider type.			
	Name	A string indicating	A string indicating the name of the provider type.		
	Provider- TypeParams	An array of parameters that the provider type uses for data input in Keyfactor Command when creating new PAM provider and certificate store records. Provider type parameters values include:			
		Value	Description		
		Id	An integer indicating the Keyfactor Command reference ID for the PAM provider type parameter.		
		Name	A string indicating the internal name for the PAM provider type parameter.		
		DisplayName	A string indicating the display name for the PAM provider type parameter. For parameters with an <i>InstanceLevel</i> of <i>False</i> , this name appears on the PAM provider dialog for the parameter when a user creates a new PAM provider. For parameters with an		

Name	Description		
	Value	Description	
		Value	Description
			InstanceLevel of True, this name appears on the Server dialog for the parameter when a user creates a new PAM provider.
		DataType	An integer indicating the data type for the parameter. Possible values are:  • 1 = String  • 2 = Secret
		InstanceLevel	A Boolean that sets whether the parameter is used to define the underlying PAM provider (False) or a field that needs to be set to a value when configuring a certificate store to use the PAM provider (True).
			Example: For CyberArk when defining a PAM provider, you configure two CyberArk-specific fields:  • PrivateArk Safe: The name of the safe in CyberArk containing the certificate store password you wish to use.  • Application ID: The name of the application created in CyberArk for use with
			Keyfactor Command.  Because these fields are configured on the PAM provider definition, they appear as InstanceLevel=False like so:  {     "Id": 1,

Name	Description		
	Value	Description	
		Value	Description
			"Name": "Safe",    "DisplayName": "Priv- ateArk Safe",    "DataType": 1,    "InstanceLevel": false,    "ProviderType": null }, {    "Id": 4,    "Name": "AppId",    "DisplayName": "Applic- ation ID",    "DataType": 1,    "InstanceLevel": false,    "ProviderType": null }  When you configure a certificate store to use CyberArk as a credential provider, you enter the name of the folder in the CyberArk safe where the protected object is stored and you enter the name of the projected object in the CyberArk safe containing the username or pass- word used to access the certificate store. Because these fields are configured on the certificate store level, they appear as InstanceLevel- l=True like so:  {    "Id": 2,    "Name": "Folder",    "DisplayName": "Priv- ateArk Folder Name",    "DataType": 1,



Name	Description					
	Value	Description				
		Value	Description			
			Value	Description		
				for the PAM provider type parameter.		
Provider-	An array containing	y the values for the nr.	ProviderTypeParams  Divider types specified by Provider types specified by Provider	An array of parameters that the provider type uses for data input in Keyfactor Command when creating new PAM provider and certificate store records.		
TypeParamValues		meter values include:				
	Value	Description				
	Id		An integer indicating the Keyfactor Command reference ID for the PAM provider type parameter.  A string indicating the value set for the parameter (e.g. the name of the CyberArk folder where the protected object that stores the use name or password resides).			
	Value	the CyberArk fo				
	InstanceId		cating the Keyfactor Command are attaching to something wi			
	InstanceGuid		ing the Keyfactor Command re are attaching to something wi			

Name	Description			
	Value	Description		
		be used.		
	Provider	An array containin	g information about the provider.	
	Provider- TypeParams	An array of parameters that the provider type uses for data input in Keyfactor Command when creating new PAM provider and certificate store records. Provider type parameters values include:		
		Value	Description	
		Id	An integer indicating the Keyfactor Command reference ID for the PAM provider type parameter.	
		Name	A string indicating the internal name for the PAM provider type parameter.	
		DisplayName	A string indicating the display name for the PAM provider type parameter. For parameters with an <i>InstanceLevel</i> of <i>False</i> , this name appears on the PAM provider dialog for the parameter when a user creates a new PAM provider. For parameters with an <i>InstanceLevel</i> of <i>True</i> , this name appears on the Server dialog for the parameter when a user creates a new PAM provider.	
		DataType	An integer indicating the data type for the parameter. Possible values are:  • 1 = String  • 2 = Secret	
		InstanceLevel	A Boolean that sets whether the parameter is used to define the underlying PAM provider (False) or a field that needs to be set to a value when configuring a certificate store to use the PAM provider (True).  See example, above.	
		ProviderType	An array containing details for the provider	

Name	Description			
	Value	Description		
		Value	Description	
			type. Provider type param	neters include:
			Value	Description
			Id	The Keyfactor Command reference GUID for the PAM provider type para- meter.
			Name	A string indicating the internal name for the PAM provider type parameter.
			ProviderTypeParams	An array of parameters that the provider type uses for data input in Keyfactor Command when creating new PAM provider and certificate store records.
SecureAreald	the PAM provider is ass You can create a single have opted to organize providers to match you	ociated with, if any. PAM provider for eac your certificate store r container organizat	d reference ID for the certification of the certifi	Ark), however, if you eed to create multiple field in the PAM

Name	Description
	PAM provider can only be used with certificate stores in the matching container. Likewise, a PAM provider defined with no container would be available for selection when setting passwords for any certificate store that also did not specify a container. A PAM provider configured in this way could be used across a variety of certificate stores (e.g. both JKS and F5) as long as they were not in containers.

## 2.2.21 Reports

The Reports component of the Keyfactor API includes methods necessary to list, update, and schedule built-in reports as well as methods to create, update, list and delete custom reports.

Table 343: Reports Endpoints

Endpoint	Method	Description	Link
/{id}	GET	Returns the built-in report with the specified ID.	GET Reports ID on the next page
/Custom/{id}	DELETE	Deletes the custom report with the specified ID.	DELETE Reports Custom ID on page 773
/Custom/{id}	GET	Returns the custom report with the specified ID.	GET Reports Custom ID on page 773
/Schedules/{id}	DELETE	Deletes the schedule for the built-in report with the specified schedule ID.	DELETE Reports Sched- ules ID on page 774
/Schedules/{id}	GET	Returns the schedule for the built-in report with the specified schedule ID.	GET Reports Schedules ID on page 775
/{id}/Parameters	GET	Returns the parameters for the built-in report with the specified report ID.	GET Reports ID Para- meters on page 779
/{id}/Parameters	PUT	Updates the parameters for the built-in report with the specified report ID.	PUT Reports ID Para- meters on page 780
/	GET	Returns all built-in reports with filtering and output options.	GET Reports on page 782
/	PUT	Updates the built-in report with the specified ID. Only some fields can be updated.	PUT Reports on page 785
/Custom	GET	Returns all custom reports with filtering and output options.	GET Reports Custom on page 788
/Custom	POST	Creates a custom report.	POST Reports Custom on

Endpoint	Method	Description	Link
			page 790
/Custom	PUT	Updates the custom report with the specified ID.	PUT Reports Custom on page 792
/{id}/Schedules	GET	Returns the schedule for the built-in report with the specified report ID.	GET Reports ID Schedules on page 793
/{id}/Schedules	POST	Creates a schedule for the built-in report with the specified report ID.	POST Reports ID Schedules on page 797
/{id}/Schedules	PUT	Updates a schedule for the built-in report with the specified report ID.	PUT Reports ID Schedules on page 806

## 2.2.21.1 GET Reports ID

The GET /Reports/{id} method is used to return the built-in report with the specified ID. This method returns HTTP 200 OK on a success with the details of the report.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: Reports: *Read* 

Table 344: GET Reports {id} Input Parameters

Name	In	Description
id	Path	<b>Required</b> . An integer containing the Keyfactor Command reference ID for the report that should be retrieved.
		Use the $GET/Reports$ method (see $\underline{GET\ Reports\ on\ page\ 782}$ ) to retrieve a list of your built-in reports to determine the report ID to use.

Table 345: GET Reports {id} Response Data

Name	Description		
Id	An integer containing the Keyfactor Command reference ID for the report.		
DisplayName	A string containing the display name for the report. This appears in the Keyfactor Command Management Portal on the Report Manager page, at the top of the page for the generated report, and on the menu.  Tip: Exported reports use built-in names; modifying this value will not change the name that appears at the top of the exported version of a report (e.g. a PDF).		
Description	A string containing the description for the report. This appears in the Keyfactor Command Management Portal on the Report Manager page and at the top of the page for the generated report.		
ReportPath	A string containing the name of the report as referenced when retrieving it via Logi Analytics.		
VersionNumber	A string containing the version number for the report.		
Categories	A string containing the report category or categories in which the report is found on the report manager page in the Keyfactor Command Management Portal. The possible values are:  CertificateCounts CertificateLifecycle CertificateLocations PKIOperations SecurityVulnerability SSHKeys		
ShortName	A string containing the short reference name for the report.		
InNavigator	A Boolean that indicates whether the report has been configured to display on the Keyfactor Command Management Portal menu (true) or not (false).		
Favorite	A Boolean that indicates whether the report has been marked as a favorite (true) or not (false).		
RemoveDuplicates	A Boolean that indicates whether the report uses certificate de-duping logic in producing output (true) or not (false).		
	Tip: When de-duplication is enabled for a report, the report results will include only the most recently issued certificate if there is more than one certificate that matches the deduplication criteria. De-duplication can only be enabled for reports that use certificate collections—the <i>UsesCollection</i> parameter. The <i>UsesCollection</i> parameter is not user-configurable.		

Name	Description			
	Certificate de-duping is configured on a certificate collection using the <i>DuplicationField</i> parameter (see <u>POST Certificate Collections on page 357</u> ). This corresponds to the Keyfactor Command Management Portal "Ignore renewed certificate results by" option on a certificate collection. Certificate collections may be configured to be de-duplicated based on the certificate common name, distinguished name, or principal name (or not at all). Only certificates that share all the EKUs (e.g. Client Authentication and Server Authentication) as well as the same CN, DN or UPN will be eliminated as duplicates. If a certificate has more than one EKU and at least one EKU does not match an otherwise similar certificate with matching CN, DN or UPN, it will not be eliminated.			
UsesCollection	A Boolean that indicates whether the report uses a certificate collection as input for reporting (true) or not (false).			
ReportParameter	An array containing the par	rameters for the report Report parameters include:		
	Name	Description		
	Id	The Keyfactor Command reference ID of the report <b>parameter</b> .		
	ParameterName	A string containing the short reference name for the report parameter (e.g. EvalDate).		
	ParameterType	A string containing the type of the parameter. Possible values include:  Bool CertAuth (certificate authorities) Int Metadata OrchestratorPool RelativeDate SingleCA SingleMetadata SSHKeyType Templates TimePeriod		
	DisplayName	A string containing the display name for the parameter (e.g. Evaluation Date (UTC)).		
	Description	A string containing the description for the parameter.		

Name	Description			
	Name	Description		
	DefaultValue	A string containing the default value for the parameter.		
		Tip: Default values that are integers are also stored as strings in this parameter.		
	DisplayOrder	An integer indicating the order in which the parameters should be displayed on the scheduling page in Keyfactor Command, beginning with 0.		
	ParameterVisibili	A string indicating whether the parameter should be displayed in the Keyfactor Command Management Portal. The default value is <i>Visible</i> . The alternative setting is <i>Hidden</i> .		
Schedules	An array containing following informati	g the configured schedules for running the report, if any. Schedules include the ion:		
	Name	Description		
	Id	The Keyfactor Command reference ID of the report <b>schedule</b> .		
	SendReport	A Boolean indicating whether the report will be sent to the email recipients configured in <i>EmailRecipients</i> (true) or not (false).		
	SaveReport	A Boolean indicating whether the report will be saved to the UNC path defined by <i>SaveReportPath</i> (true) or not (false).		
	SaveRe- portPath	A string containing the UNC path to which the report will be written, if configured.		
	ReportFormat	A string containing the report format selected for the scheduled report run.  Supported values vary depending on the selected report and include:  PDF  Excel  CSV		
	KeyfactorSche- dule	An array providing the schedule for the report. The schedule can be one of:		

Name	Description				
	Name	Descriptio	Description		
		Name	Description		
		Off	Turn off a prev	viously configured schedule.	
		Daily		nat indicates a job scheduled to run every day at with the parameter:	
			Name	Description	
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
			For example, o	daily at 11:30 pm:	
			"Daily": {     "Time": }	{ : "2022-02-25T23:30:00Z"	
		Weekl- y		nat indicates a job scheduled to run on a specific ery week at the same time with the para-	
			Name	Description	
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
			Days	An array of values representing the days of the week on which to run the job.  These can either be entered as integers (0 for Sunday, 1 for Monday, etc.) or as days of the week (e.g. "Sunday").	

Name	Description			
	Name	Description		
		Name	Description	
			<pre>pm:   "Weekly": {     "Days":         "Mono         "Wedr         "Frice ],</pre>	[ day", nesday",
		Month-		ry month at the same time with the para-
			Name	Description
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
			Day	The number of the day, in the month, to run the job.
			For example, or	n the first of every month at 5:30 pm:
			"Monthly":  "Day": 1  "Time": }	
		var ava	ious other schedu	Swagger Example Value may show examples of les, only the schedules shown here—that are agement Portal for this functionality—are valid

Name	Description			
	Name	Description		
	EmailRe- cipients	An array containing the email addresses of users configured as recipients of the scheduled report, if any.		
	RuntimePara- meters	Any array containing the parameters to be used at run time configured in the report schedule. Runtime parameters will vary depending on the report selected. Runtime parameters may include things such as:		
		Name	Description	
		CertAuth	The certificate authority or authorities selected to report on.	
		EndDate	The end date selected for the reporting period to report on. This is configured as a certain number of days, weeks or months before or after the current date (e.g. 0 days before today—meaning today).	
		EvalDate	The evaluation date selected for the reporting period to report on. This is configured as a certain number of days, weeks or months before or after the current date (e.g. 30 days before today).	
		Metadata	The custom metadata fields selected to include in the report.	
		MinCertCount	The minimum number of certificates that must have been issued for the given template before the template will be included in the report.	
		OrchestratorPool	The orchestrator pool selected to report on.	
		PeriodCount	The number of days, weeks or months selected to report on.	
		PeriodSize	The selected reporting period (day, weeks or months).	
		Requesters	The certificate requesters selected to include in the report.	

Name	Description			
	Name	Description		
		Name	Description	
		SSHKeyType	The SSH key type(s) selected to report on.	
		StartDate	The start date selected for the reporting period to report on. This is configured as a certain number of days, weeks or months before or after the current date (e.g. 30 days before today).	
		Templatelds	The Keyfactor Command identifiers for the templates to include in the report.	
Accep- tedSched- uleFormats	· ·	g the report formats suppor ect reports support CSV forr	rted for the report. Typically supported formats are nat.	

## 2.2.21.2 DELETE Reports Custom ID

The DELETE /Reports/Custom/{id} method is used to delete the custom report link with the specified ID. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: Reports: *Modify* 

Table 346: DELETE Reports Custom {id} Input Parameters

Name	In	Description
id	Path	<b>Required</b> . An integer containing the Keyfactor Command reference ID for the report link to be deleted.
		Use the <i>GET /Reports/Custom</i> method (see <u>GET Reports Custom on page 788</u> ) to retrieve a list of your custom report links to determine the report ID to use.

#### 2.2.21.3 GET Reports Custom ID

The GET /Reports/Custom/{id} method is used to return the custom report link with the specified ID. This method returns HTTP 200 OK on a success with the details of the report linkage.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: Reports: *Read* 

Table 347: GET Reports Custom {id} Input Parameters

Name	In	Description
id	Path	<b>Required</b> . An integer containing the Keyfactor Command reference ID for the report link that should be retrieved.

Table 348: GET Reports Custom {id} Response Data

Name	Description
CustomURL	A string containing the URL users should click from within Keyfactor Command to display the custom report (e.g. https://mywebserver.keyexample.com/mycustomreport/).
	Tip: Custom reports are automatically opened in a new browser tab.
Id	An integer containing the Keyfactor Command reference ID for the report link.
DisplayName	A string containing the display name for the report. This appears in the Keyfactor Command Management Portal on the Report Manager page and on the menu.
Description	A string containing the description for the report. This appears in the Keyfactor Command Management Portal on the Report Manager page.
InNavigator	A Boolean that indicates whether the report has been configured to display on the Keyfactor Command Management Portal menu (true) or not (false).
Favorite	A Boolean that indicates whether the report has been marked as a favorite (true) or not (false).

## 2.2.21.4 DELETE Reports Schedules ID

The DELETE /Reports/Schedules/{id} method is used to delete the schedule for the built-in report with the specified schedule ID. This endpoint returns 204 with no content upon success.



Table 349: DELETE Reports Schedules {id} Input Parameters

Name	In	Description
id	Path	Required. The Keyfactor Command reference ID of the report schedule.  Use the GET /Reports method (see GET Reports on page 782) to retrieve a list of your built-in reports to determine the report ID and then GET /Reports /{id} (see GET Reports ID on page 766) to retrieve the details for that report to determine the schedule ID to use.

## 2.2.21.5 GET Reports Schedules ID

The GET /Reports/Schedules/{id} method is used to return the schedule for the built-in report with the specified **schedule** ID. This method returns HTTP 200 OK on a success with the details of the report schedule. Use the *GET* /*Reports/*{*id*}/*Schedules* method to return the schedule based on the **report** ID (see <u>GET Reports ID Schedules on page 793</u>).



Table 350: GET Reports Schedules {id} Input Parameters

Name	In	Description
id	Path	Required. The Keyfactor Command reference ID of the report schedule.  Use the GET /Reports method (see GET Reports on page 782) to retrieve a list of your built-in reports to determine the report ID and then GET /Reports /{id} (see GET Reports ID on page 766) to retrieve the details for that report to determine the schedule ID to use.

Table 351: GET Reports Schedules {id} Response Data

Name	Description			
Id	The Keyfactor Command reference ID of the report <b>schedule</b> .			
SendReport	A Boolean indicating whether the report will be sent to the email recipients configured in <i>EmailRecipients</i> (true) or not (false).			
SaveReport	A Boolean indicating whether the report will be saved to the UNC path defined by SaveReportPath (true) or not (false).			
SaveReportPath	A string contai	ning the UNC path	to which the report will be written, if configured.	
ReportFormat	A string containing the report format selected for the scheduled report run. Supported values vary depending on the selected report and include:  • PDF  • Excel  • CSV			
KeyfactorSchedule	An array provi	ding the schedule f	or the report. The schedule can be one of:	
	Name	Description		
	Off	Turn off a previo	usly configured schedule.	
	Daily	A dictionary that with the parame	indicates a job scheduled to run every day at the same time ter:	
		Name	Description	
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
		For example, dai	ly at 11:30 pm:	
		"Daily": { "Time": ' }	"2022-02-25T23:30:00Z"	
	Weekly	A dictionary that	indicates a job scheduled to run on a specific day or days every	

Description	Description			
Name	Description			
	week at the sa	week at the same time with the parameters:		
	Name	Description		
	Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).		
	Days	An array of values representing the days of the week on which to run the job. These can either be entered as integers (0 for Sunday, 1 for Monday, etc.) or as days of the week (e.g. "Sunday").		
	"Weekly": "Days": "Mor "Wee			
Monthly		nat indicates a job scheduled to run on a specific day or days every same time with the parameters:		
	Name	Description		
	Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).		
	Day	The number of the day, in the month, to run the job.		
	"Monthly":			

Name	Description		
	Note: Although the Swagger Example Value may show examples of various other schedules, only the schedules shown here—that are available in the Management Portal for this functionality—are valid for this endpoint.		
EmailRecipients	An array containing the email addresses of users configured as recipients of the scheduled report, if any.		
RuntimePara- meters		parameters to be used at run time configured in the report schedule. vary depending on the report selected. Runtime parameters may include	
	Name	Description	
	CertAuth	The certificate authority or authorities selected to report on.	
	EndDate	The end date selected for the reporting period to report on. This is configured as a certain number of days, weeks or months before or after the current date (e.g. 0 days before today—meaning today).	
	EvalDate	The evaluation date selected for the reporting period to report on.  This is configured as a certain number of days, weeks or months before or after the current date (e.g. 30 days before today).	
	Metadata	The custom metadata fields selected to include in the report.	
	MinCertCount	The minimum number of certificates that must have been issued for the given template before the template will be included in the report.	
	OrchestratorPool	The orchestrator pool selected to report on.	
	PeriodCount	The number of days, weeks or months selected to report on.	
	PeriodSize	The selected reporting period (day, weeks or months).	
	Requesters	The certificate requesters selected to include in the report.	
	SSHKeyType	The SSH key type(s) selected to report on.	
	StartDate	The start date selected for the reporting period to report on. This is configured as a certain number of days, weeks or months before or after the current date (e.g. 30 days before today).	
	TemplateIds	The Keyfactor Command identifiers for the templates to include in the report.	

## 2.2.21.6 GET Reports ID Parameters

The GET /Reports/{id}/Parameters method is used to return the parameters for the built-in report with the specified report ID. This method returns HTTP 200 OK on a success with the details of the report parameters.



Table 352: GET Reports {id} Parameters Input Parameters

Name	In	Description
id	Path	<b>Required</b> . The Keyfactor Command reference ID of the built-in <b>report</b> the parameter is associated with.
		Use the $GET$ /Reports method (see $GET$ Reports on page 782) to retrieve a list of your built-in reports to determine the report ID to use.

Table 353: GET Reports {id} Parameters Response Data

Name	Description	
Id	The Keyfactor Command reference ID of the report parameter.	
ParameterName	A string containing the short reference name for the report parameter (e.g. EvalDate).	
ParameterType	A string containing the type of the parameter. Possible values include:  Bool  CertAuth (certificate authorities)  Int  Metadata  OrchestratorPool  RelativeDate  SingleCA  SingleMetadata  SSHKeyType  Templates  TimePeriod	
DisplayName	A string containing the display name for the parameter (e.g. Evaluation Date (UTC)).	
Description	A string containing the description for the parameter.	
DefaultValue	A string containing the default value for the parameter.  Tip: Default values that are integers are also stored as strings in this parameter.	
DisplayOrder	An integer indicating the order in which the parameters should be displayed on the scheduling page in Keyfactor Command, beginning with 0.	
ParameterVisibility	A string indicating whether the parameter should be displayed in the Keyfactor Command Management Portal. The default value is <i>Visible</i> . The alternative setting is <i>Hidden</i> .	

## 2.2.21.7 PUT Reports ID Parameters

The PUT /Reports/{id}/Parameters method is used to update the parameters for the built-in report with the specified report ID. Only some fields can be updated. This method returns HTTP 200 OK on a success with the details of the report parameters.



Table 354: PUT Reports {id} Parameters Input Parameters

Name	In	Description
id	Path	Required. The Keyfactor Command reference ID of the built-in report the parameter is associated with.  Use the GET /Reports method (see GET Reports on the next page) to retrieve a list of your built-in reports to determine the report ID to use.
Id	Body	Required. The Keyfactor Command reference ID of the report parameter.  Use the GET /Reports/{id} (see GET Reports ID on page 766) to retrieve the details for the desired report to determine the parameter ID to use.
DisplayName	Body	A string containing the display name for the parameter (e.g. Evaluation Date (UTC)).
Description	Body	A string containing the description for the parameter.
DefaultValue	Body	A string containing the default value for the parameter.  Tip: Default values that are integers are also stored as strings in this parameter.

Table 355: PUT Reports {id} Parameters Response Data

Name	Description	
Id	The Keyfactor Command reference ID of the report <b>parameter</b> .	
ParameterName	A string containing the short reference name for the report parameter (e.g. EvalDate).	
ParameterType	A string containing the type of the parameter. Possible values include:  Bool  CertAuth (certificate authorities)  Int  Metadata  OrchestratorPool  RelativeDate  SingleCA  SingleMetadata  SSHKeyType  Templates  TimePeriod	
DisplayName	A string containing the display name for the parameter (e.g. Evaluation Date (UTC)).	
Description	A string containing the description for the parameter.	
DefaultValue	A string containing the default value for the parameter.  Tip: Default values that are integers are also stored as strings in this parameter.	
DisplayOrder	An integer indicating the order in which the parameters should be displayed on the scheduling page in Keyfactor Command, beginning with 0.	
ParameterVisibility	A string indicating whether the parameter should be displayed in the Keyfactor Command Management Portal. The default value is <i>Visible</i> . The alternative setting is <i>Hidden</i> .	

# 2.2.21.8 GET Reports

The GET /Reports method is used to return all built-in reports with filtering and output options. This method returns HTTP 200 OK on a success with selected details of the reports. To view details of schedules and parameters for a report, use the GET /Reports/{id} method (see GET Reports ID on page 766).



Table 356: GET Reports Input Parameters

Name	In	Description
queryString	Query	A string containing a query to limit the results (e.g. field1 -eq value1 AND field2 -gt value2). The default is to return all records. Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns for the same feature. For querying guidelines, refer to the Keyfactor Command Reference Guide: Certificate Search Page. The query fields supported for this endpoint are:  • Categories (CertificateCounts, CertificateLifecycle, Certificate Locations, PKIOperations, SecurityVulnerability,SSHKeys)  • Custom  • Favorite (true, false)  • InNavigator (true, false)  • Scheduled (Number of schedules)  Tip: This method offers limited searchable fields. The most useful search is probably by category. For example, to return all the reports tagged with the PKI Operations category:  Categories -contains "PKIOperations"
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>DisplayName</i> .
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.

Table 357: GET Reports Response Data

Name	Description		
Id	An integer containing the Keyfactor Command reference ID for the report.		
Scheduled	An integer indicating the number of schedules configured for the report.		
DisplayName	A string containing the display name for the report. This appears in the Keyfactor Command Management Portal on the Report Manager page, at the top of the page for the generated report, and on the menu.		
	<b>Tip:</b> Exported reports use built-in names; modifying this value will not change the name that appears at the top of the exported version of a report (e.g. a PDF).		
Description	A string containing the description for the report. This appears in the Keyfactor Command Management Portal on the Report Manager page and at the top of the page for the generated report.		
ReportPath	A string containing the name of the report as referenced when retrieving it via Logi Analytics.		
VersionNumber	A string containing the version number for the report.		
Categories	A string containing the report category or categories in which the report is found on the report manager page in the Keyfactor Command Management Portal. The possible values are:  • CertificateCounts  • CertificateLifecycle  • CertificateLocations  • PKIOperations  • SecurityVulnerability  • SSHKeys		
ShortName	A string containing the short reference name for the report.		
InNavigator	A Boolean that indicates whether the report has been configured to display on the Keyfactor Command Management Portal menu (true) or not (false).		
Favorite	A Boolean that indicates whether the report has been marked as a favorite (true) or not (false).		
RemoveDuplicates	A Boolean that indicates whether the report uses certificate de-duping logic in producing output (true) or not (false).		
	Tip: When de-duplication is enabled for a report, the report results will include only the most recently issued certificate if there is more than one certificate that matches		

Name	Description		
	the de-duplication criteria. De-duplication can only be enabled for reports that use certificate collections—the <i>UsesCollection</i> parameter. The <i>UsesCollection</i> parameter is not user-configurable.  Certificate de-duping is configured on a certificate collection using the <i>DuplicationField</i> parameter (see <a href="POST Certificate Collections on page 357">POST Certificate Collections on page 357</a> ). This corresponds to the Keyfactor Command Management Portal "Ignore renewed certificate results by" option on a certificate collection. Certificate collections may be configured to be de-duplicated based on the certificate common name, distinguished name, or principal name (or not at all). Only certificates that share all the EKUs (e.g. Client Authentication and Server Authentication) as well as the same CN, DN or UPN will be eliminated as duplicates. If a certificate has more than one EKU and at least one EKU does not match an otherwise similar certificate with matching CN, DN or UPN, it will not be eliminated.		
UsesCollection	A Boolean that indicates whether the report uses a certificate collection as input for reporting (true) or not (false).		

#### 2.2.21.9 PUT Reports

The PUT /Reports method is used to update the built-in report with the specified report ID. Only some fields can be updated. To create or update a report schedule, use the POST /Reports/{id}Schedules (see POST Reports ID Schedules on page 797) or PUT /Reports/{id}Schedules (see PUT Reports ID Schedules on page 806) method. To update parameters for a built-in report, use the PUT /Reports/{id}/Parameters method (see PUT Reports ID Parameters on page 780). This method returns HTTP 200 OK on a success with the details of the report.



Table 358: PUT Reports Input Parameters

Name	In	Description
Id	Body	Required. The Keyfactor Command reference ID of the built-in report that should be updated.  Use the GET /Reports method (see GET Reports on page 782) to retrieve a list of your built-in reports to determine the report ID to use.
InNavigator	Body	A Boolean that indicates whether the report has been configured to display on the Keyfactor Command Management Portal menu (true) or not (false).
Favorite	Body	A Boolean that indicates whether the report has been marked as a favorite (true) or not (false).
RemoveDuplicates	Body	A Boolean that indicates whether the report uses certificate de-duping logic in producing output (true) or not (false).  Tip: When de-duplication is enabled for a report, the report results will include only the most recently issued certificate if there is more than one certificate that matches the de-duplication criteria. De-duplication can only be enabled for reports that use certificate collections—the UsesCollection parameter. The UsesCollection parameter is not user-configurable. Certificate de-duping is configured on a certificate collection using the DuplicationField parameter (see POST Certificate Collections on page 357). This corresponds to the Keyfactor Command Management Portal "Ignore renewed certificate results by" option on a certificate collection. Certificate collections may be configured to be de-duplicated based on the certificate common name, distinguished name, or principal name (or not at all). Only certificates that share all the EKUs (e.g. Client Authentication and Server Authentication) as well as the same CN, DN or UPN will be eliminated as duplicates. If a certificate has more than one EKU and at least one EKU does not match an otherwise similar certificate with matching CN, DN or UPN, it will not be eliminated.

Table 359: PUT Reports Response Data

Name	Description		
Id	An integer containing the Keyfactor Command reference ID for the report.		
DisplayName	A string containing the display name for the report. This appears in the Keyfactor Command Management Portal on the Report Manager page, at the top of the page for the generated report, and on the menu.		
	Tip: Exported reports use built-in names; modifying this value will not change the name that appears at the top of the exported version of a report (e.g. a PDF).		
Description	A string containing the description for the report. This appears in the Keyfactor Command Management Portal on the Report Manager page and at the top of the page for the generated report.		
ReportPath	A string containing the name of the report as referenced when retrieving it via Logi Analytics.		
VersionNumber	A string containing the version number for the report.		
Categories	A string containing the report category or categories in which the report is found on the report manager page in the Keyfactor Command Management Portal. The possible values are:  CertificateCounts CertificateLifecycle CertificateLocations PKIOperations SecurityVulnerability SSHKeys		
ShortName	A string containing the short reference name for the report.		
InNavigator	A Boolean that indicates whether the report has been configured to display on the Keyfactor Command Management Portal menu (true) or not (false).		
Favorite	A Boolean that indicates whether the report has been marked as a favorite (true) or not (false).		
RemoveDuplicates	A Boolean that indicates whether the report uses certificate de-duping logic in producing output (true) or not (false).		
	Tip: When de-duplication is enabled for a report, the report results will include only the most recently issued certificate if there is more than one certificate that matches the de-duplication criteria. De-duplication can only be enabled for reports that use certificate collections—the <i>UsesCollection</i> parameter. The <i>UsesCollection</i> parameter is not		

Name	Description		
	user-configurable. Certificate de-duping is configured on a certificate collection using the <i>DuplicationField</i> parameter (see <u>POST Certificate Collections on page 357</u> ). This corresponds to the Keyfactor Command Management Portal "Ignore renewed certificate results by" option on a certificate collection. Certificate collections may be configured to be de-duplicated based on the certificate common name, distinguished name, or principal name (or not at all). Only certificates that share all the EKUs (e.g. Client Authentication and Server Authentication) as well as the same CN, DN or UPN will be eliminated as duplicates. If a certificate has more than one EKU and at least one EKU does not match an otherwise similar certificate with matching CN, DN or UPN, it will not be eliminated.		
UsesCollection	A Boolean that indicates whether the report uses a certificate collection as input for reporting (true) or not (false).		

# 2.2.21.10 GET Reports Custom

The GET /Reports/Custom method is used to return all custom report links with filtering and output options. This method returns HTTP 200 OK on a success with the details of the report linkages.



Table 360: GET Reports Custom Input Parameters

Name	In	Description
queryString	Query	A string containing a query to limit the results (e.g. field1 -eq value1 AND field2 -gt value2). The default is to return all records. Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns for the same feature. For querying guidelines, refer to the Keyfactor Command Reference Guide: Certificate Search Page. The query fields supported for this endpoint are:  • Categories (CertificateCounts, CertificateLifecycle, Certificate Locations, PKIOperations, SecurityVulnerability,SSHKeys)  • Custom  • Favorite (true, false)  • InNavigator (true, false)  • Scheduled (Number of schedules)
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>DisplayName</i> .
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.

Table 361: GET Reports Custom Response Data

Name	Description		
CustomURL	A string containing the URL users should click from within Keyfactor Command to display the custom report (e.g. https://mywebserver.keyexample.com/mycustomreport/).		
	Tip: Custom reports are automatically opened in a new browser tab.		
Id	An integer containing the Keyfactor Command reference ID for the report link.		
DisplayName	A string containing the display name for the report. This appears in the Keyfactor Command Management Portal on the Report Manager page and on the menu.		
Description	A string containing the description for the report. This appears in the Keyfactor Command Management Portal on the Report Manager page.		
InNavigator	A Boolean that indicates whether the report has been configured to display on the Keyfactor Command Management Portal menu (true) or not (false).		
Favorite	A Boolean that indicates whether the report has been marked as a favorite (true) or not (false).		

## 2.2.21.11 POST Reports Custom

The POST /Reports/Custom method is used to add a link within Keyfactor Command to an externally hosted custom report. This method returns HTTP 200 OK on a success with the details of the report linkage.



Table 362: POST Reports Custom Input Parameters

Name	In	Description
CustomURL Body	Body	<b>Required</b> . A string containing the URL users should click from within Keyfactor Command to display the custom report (e.g. https://my-webserver.keyexample.com/mycustomreport/).
		Tip: Custom reports are automatically opened in a new browser tab.
DisplayName	Body	<b>Required</b> . A string containing the display name for the report. This appears in the Keyfactor Command Management Portal on the Report Manager page and on the menu.
Description	Body	A string containing the description for the report. This appears in the Keyfactor Command Management Portal on the Report Manager page.
InNavigator	Body	A Boolean that indicates whether the report has been configured to display on the Keyfactor Command Management Portal menu (true) or not (false). The default is <i>false</i> .
Favorite	Body	A Boolean that indicates whether the report has been marked as a favorite (true) or not (false). The default is <i>false</i> .

Table 363: POST Reports Custom Response Data

Name	Description
CustomURL	A string containing the URL users should click from within Keyfactor Command to display the custom report (e.g. https://mywebserver.keyexample.com/mycustomreport/).
	Tip: Custom reports are automatically opened in a new browser tab.
Id	An integer containing the Keyfactor Command reference ID for the report link.
DisplayName	A string containing the display name for the report. This appears in the Keyfactor Command Management Portal on the Report Manager page and on the menu.
Description	A string containing the description for the report. This appears in the Keyfactor Command Management Portal on the Report Manager page.
InNavigator	A Boolean that indicates whether the report has been configured to display on the Keyfactor Command Management Portal menu (true) or not (false).
Favorite	A Boolean that indicates whether the report has been marked as a favorite (true) or not (false).

# 2.2.21.12 PUT Reports Custom

The PUT /Reports/Custom method is used to update the custom report link with the specified ID. This method returns HTTP 200 OK on a success with the details of the report linkage.



Table 364: PUT Reports Custom Input Parameters

Name	In	Description
CustomURL	Body	<b>Required</b> . A string containing the URL users should click from within Keyfactor Command to display the custom report (e.g. https://my-webserver.keyexample.com/mycustomreport/).
		Tip: Custom reports are automatically opened in a new browser tab.
Id	Body	<b>Required</b> . An integer containing the Keyfactor Command reference ID for the report link. Use the <i>GET /Reports/Custom</i> method (see <u>GET Reports Custom on page 788</u> ) to retrieve a list of your custom report links to determine the report ID to use.
DisplayName	Body	<b>Required</b> . A string containing the display name for the report. This appears in the Keyfactor Command Management Portal on the Report Manager page and on the menu.
Description	Body	A string containing the description for the report. This appears in the Keyfactor Command Management Portal on the Report Manager page.
InNavigator	Body	A Boolean that indicates whether the report has been configured to display on the Keyfactor Command Management Portal menu (true) or not (false). The default is <i>false</i> .
Favorite	Body	A Boolean that indicates whether the report has been marked as a favorite (true) or not (false). The default is <i>false</i> .

Table 365: PUT Reports Custom Response Data

Name	Description
CustomURL	A string containing the URL users should click from within Keyfactor Command to display the custom report (e.g. https://mywebserver.keyexample.com/mycustomreport/).
	Tip: Custom reports are automatically opened in a new browser tab.
Id	An integer containing the Keyfactor Command reference ID for the report link.
DisplayName	A string containing the display name for the report. This appears in the Keyfactor Command Management Portal on the Report Manager page and on the menu.
Description	A string containing the description for the report. This appears in the Keyfactor Command Management Portal on the Report Manager page.
InNavigator	A Boolean that indicates whether the report has been configured to display on the Keyfactor Command Management Portal menu (true) or not (false).
Favorite	A Boolean that indicates whether the report has been marked as a favorite (true) or not (false).

## 2.2.21.13 GET Reports ID Schedules

The GET /Reports/{id}/Schedules method is used to return the schedule for the built-in report with the specified **report** ID. This method returns HTTP 200 OK on a success with the details of the report schedule. Use the *GET* /*Reports/Schedules/{id}* method to return the schedule based on the **schedule** ID (see <u>GET Reports Schedules ID on page 775</u>).



Table 366: GET Reports {id} Schedules Input Parameters

Name	In	Description
id	Path	<b>Required</b> . The Keyfactor Command reference ID of the built-in <b>report</b> the schedule is associated with.
		Use the $GET/Reports$ method (see $GET$ Reports on page 782) to retrieve a list of your built-in reports to determine the report ID to use.

Table 367: GET Reports {id} Schedules Response Data

Name	Description				
Id	The Keyfactor Command reference ID of the report <b>schedule</b> .				
SendReport	A Boolean indicating whether the report will be sent to the email recipients configured in <i>EmailRecipients</i> (true) or not (false).				
SaveReport	A Boolean indicating whether the report will be saved to the UNC path defined by SaveReportPath (true) or not (false).				
SaveReportPath	A string contai	ning the UNC pat	th to which the report will be written, if configured.		
ReportFormat	A string containing the report format selected for the scheduled report run. Supported values vary depending on the selected report and include:  • PDF  • Excel  • CSV				
KeyfactorSchedule	An array provi	ding the schedule	e for the report. The schedule can be one of:		
	Name	ame Description			
	Off	Turn off a prev	viously configured schedule.		
	Daily	A dictionary th	nat indicates a job scheduled to run every day at the same time neter:		
		Name	Description		
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).		
		For example, o	laily at 11:30 pm:		
		"Daily": {     "Time": }	[ : "2022-02-25T23:30:00Z"		
	Weekly	A dictionary th	nat indicates a job scheduled to run on a specific day or days every		

Name	Description				
	Name	Description			
		week at the sar	week at the same time with the parameters:		
		Name	Description		
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).		
		Days	An array of values representing the days of the week on which to run the job. These can either be entered as integers (0 for Sunday, 1 for Monday, etc.) or as days of the week (e.g. "Sunday").		
		"Weekly": "Days": "Mono "Wedr	[ day", nesday",		
	Monthly		at indicates a job scheduled to run on a specific day or days every ame time with the parameters:		
		Name	Description		
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).		
		Day	The number of the day, in the month, to run the job.		
		"Monthly": "Day":			

Name	Note: Although the Swagger Example Value may show examples of various other schedules, only the schedules shown here—that are available in the Management Portal for this functionality—are valid for this endpoint.				
EmailRecipients	An array containing the email addresses of users configured as recipients of the scheduled report, if any.				
RuntimePara- meters		parameters to be used at run time configured in the report schedule. vary depending on the report selected. Runtime parameters may include			
	Name	Description			
	CertAuth	The certificate authority or authorities selected to report on.			
	EndDate	The end date selected for the reporting period to report on. This is configured as a certain number of days, weeks or months before or after the current date (e.g. 0 days before today—meaning today).			
	EvalDate	The evaluation date selected for the reporting period to report on.  This is configured as a certain number of days, weeks or months before or after the current date (e.g. 30 days before today).			
	Metadata	The custom metadata fields selected to include in the report.			
	MinCertCount	The minimum number of certificates that must have been issued for the given template before the template will be included in the report.			
	OrchestratorPool	The orchestrator pool selected to report on.			
	PeriodCount	The number of days, weeks or months selected to report on.			
	PeriodSize	The selected reporting period (day, weeks or months).			
	Requesters	The certificate requesters selected to include in the report.			
	SSHKeyType	The SSH key type(s) selected to report on.			
	StartDate	The start date selected for the reporting period to report on. This is configured as a certain number of days, weeks or months before or after the current date (e.g. 30 days before today).			
	TemplateIds	The Keyfactor Command identifiers for the templates to include in the report.			

# 2.2.21.14 POST Reports ID Schedules

The POST /Reports/{id}/Schedules method is used to create a schedule for the built-in report with the specified report ID. This method returns HTTP 200 OK on a success with the details of the report schedule.



Table 368: POST Reports {id} Schedules Input Parameters

Name	In	Description		
id	Path	Required. The Keyfactor Command reference ID of the built-in report the schedule is associated with.  Use the GET /Reports method (see GET Reports on page 782) to retrieve a list of your built-in reports to determine the report ID to use.		
SendReport	Body	A Boolean indicating whether the report will be sent to the email recipients configured in <i>EmailRecipients</i> (true) or not (false). The default is <i>false</i> .		
SaveReport	Body	A Boolean indicating whether the report will be saved to the UNC path defined by SaveReportPath (true) or not (false). The default is false.		
SaveReportPath	Body	<b>Required</b> *. A string containing the UNC path to which the report will be written, if configured.		
		<ul> <li>Note: The path for saved reports must be provided in UNC format (\\servername\sharename\path) and must be accessible from the Keyfactor Command administration server. In addition:         <ul> <li>Do not use a trailing "\" in the report path.</li> </ul> </li> <li>Ensure that the application pool service account has permission to write to the location where you want the outputted report to be saved.</li> <li>When scheduling a report, schedule it for at least 10 minutes in advance of the current time if you wish it to run soon. If you want to run it faster than that, the Keyfactor Command Service will need to be restarted.</li> </ul>		
		This field is <b>required</b> if <i>SaveReport</i> is set to <i>true</i> .		
ReportFormat	Body	Required. A string containing the report format selected for the scheduled report run.  Supported values vary depending on the selected report and include:  PDF  Excel  CSV		
KeyfactorSchedul-	Body	<b>Required</b> . An array providing the schedule for the report. The schedule can be one of:		
		Name Description		
		Off Turn off a previously configured schedule.		
		Daily A dictionary that indicates a job scheduled to run every day at the same time with the parameter:		

Name	In	Description		
		Name	Description	
			Name	Description
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
			For example, d	laily at 11:30 pm:
			"Daily": { "Time": }	"2022-02-25T23:30:00Z"
		Weekly	A dictionary that indicates a job scheduled to run on a specific day or days every week at the same time with the parameters:	
			Name	Description
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
			Days	An array of values representing the days of the week on which to run the job. These can either be entered as integers (0 for Sunday, 1 for Monday, etc.) or as days of the week (e.g. "Sunday").
			"Weekly": "Days": "Mon "Wed "Fri	
		Monthly		nat indicates a job scheduled to run on a specific day or nth at the same time with the parameters:

Name	In	Description		
		Name	Description	
			Name	Description
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
			Day	The number of the day, in the month, to run the job.
			"Monthly": "Day": 1	
		sched	lules, only the sch	ragger Example Value may show examples of various other edules shown here—that are available in the Management ality—are valid for this endpoint.
		For example:		
		"Month "Da	orSchedule": { uly": { uy": 1, me": "2021-07-0	01T17:00:00Z"
		Or:		
		"Weekl "Da	orSchedule": { .y": { .ys": [ "Monday", "Thursday" .me": "2021-07-0	01T17:00:00Z"
EmailRecipients	Body	<b>Required</b> *. An array containing the email addresses of users configured as recipients of the		

Name	In	Description				
		scheduled report, if any. I	For example:			
		"EmailRecipients":     "pkiadmins@keyex     "john.smith@keye	cample.com",			
		This field is <b>required</b> if <i>SendReport</i> is set to <i>true</i> .				
RuntimePara- meters	Body	<b>Required</b> *. Any array containing the parameters to be used at run time configured in the report schedule. Runtime parameters will vary depending on the report selected. Runtime parameters may include things such as:				
		Name	Description			
		CertAuth	The certificate authority or authorities selected to report on.			
		EndDate	The end date selected for the reporting period to report on.  This is configured as a certain number of days, weeks or months before or after the current date (e.g. 0 days before today—meaning today).			
		EvalDate	The evaluation date selected for the reporting period to report on. This is configured as a certain number of days, weeks or months before or after the current date (e.g. 30 days before today).			
		Metadata	The custom metadata fields selected to include in the report.			
					MinCertCount	The minimum number of certificates that must have been issued for the given template before the template will be included in the report.
		OrchestratorPool	The orchestrator pool selected to report on.			
		PeriodCount	The number of days, weeks or months selected to report on.			
		PeriodSize	The selected reporting period (day, weeks or months).			
			Requesters	The certificate requesters selected to include in the report.		
		SSHKeyType	The SSH key type(s) selected to report on.			
		StartDate	The start date selected for the reporting period to report on.			

Name	In	Description		
	For	Name	Description	
			This is configured as a certain number of days, weeks or months before or after the current date (e.g. 30 days before today).	
		TemplateIds	The Keyfactor Command identifiers for the templates to include in the report.	
		For example:		
		"RuntimeParameters"  "StartDate": "60  "EndDate": "7-Da  "Metadata": "App  "Requesters": "j  }	O-Day-Before", By-Before", OwnerFirstName, AppOwnerLastName",	
		This field is <b>required</b> for r	eports that have runtime parameters.	

Table 369: POST Reports {id} Schedules Response Data

Name	Description			
Id	The Keyfactor Command reference ID of the report <b>schedule</b> .			
SendReport	A Boolean indicating whether the report will be sent to the email recipients configured in <i>EmailRecipients</i> (true) or not (false).			
SaveReport	A Boolean indicating whether the report will be saved to the UNC path defined by SaveReportPath (true) or not (false).			
SaveReportPath	A string containing the UNC path to which the report will be written, if configured.			
ReportFormat	A string containing the report format selected for the scheduled report run. Supported values vary depending on the selected report and include:  • PDF  • Excel  • CSV			
KeyfactorSchedule	An array providing the schedule for the report. The schedule can be one of:			
	Name	Name Description		
	Off	Turn off a previously configured schedule.		
	Daily	A dictionary that indicates a job scheduled to run every day at the same time with the parameter:		
		Name Description		
		Time The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).		
		For example, daily at 11:30 pm:		
		"Daily": {     "Time": "2022-02-25T23:30:00Z" }		
	Weekly	A dictionary that indicates a job scheduled to run on a specific day or days every		

Name	Description	Description		
	Name	Description		
		week at the same time with the parameters:		
		Name	Description	
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
		Days	An array of values representing the days of the week on which to run the job. These can either be entered as integers (0 for Sunday, 1 for Monday, etc.) or as days of the week (e.g. "Sunday").	
		"Weekly": "Days": "Mon "Wed "Fri	[ day", nesday",	
	Monthly		at indicates a job scheduled to run on a specific day or days every ame time with the parameters:	
		Name	Description	
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
		Day	The number of the day, in the month, to run the job.	
		"Monthly": "Day":		

Name	Description			
	Note: Although the Swagger Example Value may show examples of various other schedules, only the schedules shown here—that are available in the Management Portal for t functionality—are valid for this endpoint.			
EmailRecipients	An array containing the email addresses of users configured as recipients of the scheduled report, if any.			
RuntimeParameters	Any array containing the parameters to be used at run time configured in the report schedule.  Runtime parameters will vary depending on the report selected. Runtime parameters may include things such as:			
	Name	Description		
	CertAuth	The certificate authority or authorities selected to report on.		
	EndDate	The end date selected for the reporting period to report on. This is configured as a certain number of days, weeks or months before or after the current date (e.g. 0 days before today—meaning today).		
	EvalDate	The evaluation date selected for the reporting period to report on.  This is configured as a certain number of days, weeks or months before or after the current date (e.g. 30 days before today).		
	Metadata	The custom metadata fields selected to include in the report.		
	MinCertCount	The minimum number of certificates that must have been issued for the given template before the template will be included in the report.		
	OrchestratorPool	The orchestrator pool selected to report on.		
	PeriodCount	The number of days, weeks or months selected to report on.		
	PeriodSize	The selected reporting period (day, weeks or months).		
	Requesters	The certificate requesters selected to include in the report.		
	SSHKeyType	The SSH key type(s) selected to report on.		
	StartDate	The start date selected for the reporting period to report on. This is configured as a certain number of days, weeks or months before or after the current date (e.g. 30 days before today).		
	TemplateIds	The Keyfactor Command identifiers for the templates to include in the report.		

# 2.2.21.15 PUT Reports ID Schedules

The PUT /Reports/{id}/Schedules method is used to update the schedule for the built-in report with the specified report ID. This method returns HTTP 200 OK on a success with the details of the report schedule.



Table 370: PUT Reports {id} Schedules Input Parameters

Name	In	Description	
id	Path	<b>Required</b> . The Keyfactor Command reference ID of the built-in <b>report</b> the schedule is associated with.  Use the <i>GET /Reports</i> method (see <u>GET Reports on page 782</u> ) to retrieve a list of your built-in reports to determine the report ID to use.	
Id	Body	Required. The Keyfactor Command reference ID of the report schedule.  Use the GET /Reports/{id} (see GET Reports ID on page 766) to retrieve the details for the desired report to determine the schedule ID to use.	
SendReport	Body	A Boolean indicating whether the report will be sent to the email recipients configured in <i>EmailRecipients</i> (true) or not (false). The default is <i>false</i> .	
SaveReport	Body	A Boolean indicating whether the report will be saved to the UNC path defined by SaveReportPath (true) or not (false). The default is false.	
SaveReportPath	Body	Required*. A string containing the UNC path to which the report will be written, if configured.  Note: The path for saved reports must be provided in UNC format (\\servername\\sharename\\path) and must be accessible from the Keyfactor Command administration server. In addition:  Do not use a trailing "\" in the report path.  Ensure that the application pool service account has permission to write to the location where you want the outputted report to be saved.  When scheduling a report, schedule it for at least 10 minutes in advance of the current time if you wish it to run soon. If you want to run it faster than that, the Keyfactor Command Service will need to be restarted.  This field is required if SaveReport is set to true.	
ReportFormat	Body	Required. A string containing the report format selected for the scheduled report run.  Supported values vary depending on the selected report and include:  PDF  Excel  CSV	
KeyfactorSchedul- e	Body	Required. An array providing the schedule for the report.  Name Description  Off Turn off a previously configured schedule.	

Name	In	Description	1	
		Name	Description	
		Daily	A dictionary tha	it indicates a job scheduled to run every day at the same arameter:
			Name	Description
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
			For example, da	aily at 11:30 pm:
			"Daily": {     "Time": }	"2022-02-25T23:30:00Z"
		Weekly	A dictionary that indicates a job scheduled to run on a specific day or days every week at the same time with the parameters:	
			Name	Description
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
			Days	An array of values representing the days of the week on which to run the job. These can either be entered as integers (0 for Sunday, 1 for Monday, etc.) or as days of the week (e.g. "Sunday").
			For example, ev	very Monday, Wednesday and Friday at 5:30 pm:
			"Fric	[ day", nesday", day"
			"Time": }	"2022-02-27T17:30:00Z"

Name	In	Description		
		Name	Description	
		Monthly	A dictionary that indicates a job scheduled to run on a specific day or days every month at the same time with the parameters:	
			Name	Description
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
			Day	The number of the day, in the month, to run the job.
		For example:  "Keyfactc "Month" "Da	"Monthly":  "Day": 1  "Time": }  Although the Sw	"2022-02-27T17:30:00Z"  agger Example Value may show examples of various other edules shown here—that are available in the Management slity—are valid for this endpoint.
		},		
		Or:		
		"Week] "Da	orSchedule": {	01T17:00:00Z"

Name	In	Description									
		},									
EmailRecipients	Body	Required*. An array conta scheduled report, if any. I	aining the email addresses of users configured as recipients of the For example:								
		"EmailRecipients": "pkiadmins@keyex "john.smith@keye	cample.com",								
		This field is <b>required</b> if Se	ndReport is set to true.								
RuntimePara- meters	Body		taining the parameters to be used at run time configured in the parameters will vary depending on the report selected.								
		Name	Description								
		CertAuth	The certificate authority or authorities selected to report on.								
		EndDate	The end date selected for the reporting period to report on.  This is configured as a certain number of days, weeks or months before or after the current date (e.g. 0 days before today—meaning today).								
									EvalDate	The evaluation date selected for the reporting period to report on. This is configured as a certain number of days, weeks or months before or after the current date (e.g. 30 days before today).	
		Metadata	The custom metadata fields selected to include in the report.								
					MinCertCount	The minimum number of certificates that must have been issued for the given template before the template will be included in the report.					
		OrchestratorPool	The orchestrator pool selected to report on.								
										PeriodCount	The number of days, weeks or months selected to report on.
								PeriodSize	The selected reporting period (day, weeks or months).		
									Requesters	The certificate requesters selected to include in the report.	

Name	In	Description	
		Name	Description
		SSHKeyType	The SSH key type(s) selected to report on.
	StartDate	The start date selected for the reporting period to report on. This is configured as a certain number of days, weeks or months before or after the current date (e.g. 30 days before today).	
		Templatelds	The Keyfactor Command identifiers for the templates to include in the report.
		For example:	
		"RuntimeParameters"  "StartDate": "60  "EndDate": "7-Da  "Metadata": "App  "Requesters": "j  }	-Day-Before", y-Before", OwnerFirstName, AppOwnerLastName",
		This field is <b>required</b> for re	eports that have runtime parameters.

Table 371: PUT Reports {id} Schedules Response Data

Name	Description		
Id	The Keyfactor	Command reference ID of the report <b>schedule</b> .	
SendReport	A Boolean indicating whether the report will be sent to the email recipients configured in <i>EmailRecipients</i> (true) or not (false).		
SaveReport	A Boolean indicating whether the report will be saved to the UNC path defined by SaveReportPath (true) or not (false).		
SaveReportPath	A string contai	ning the UNC path to which the report will be written, if configured.	
ReportFormat	A string containing the report format selected for the scheduled report run. Supported values vary depending on the selected report and include:  • PDF  • Excel  • CSV		
KeyfactorSchedule	An array providing the schedule for the report. The schedule can be one of:		
	Name	Description	
	Off	Turn off a previously configured schedule.	
	Daily	A dictionary that indicates a job scheduled to run every day at the same time with the parameter:	
		Name Description	
		Time The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
		For example, daily at 11:30 pm:	
		"Daily": {     "Time": "2022-02-25T23:30:00Z" }	
	Weekly	A dictionary that indicates a job scheduled to run on a specific day or days every	

Name	Description		
	Name	Description	
		week at the sar	me time with the parameters:
		Name	Description
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
		Days	An array of values representing the days of the week on which to run the job. These can either be entered as integers (0 for Sunday, 1 for Monday, etc.) or as days of the week (e.g. "Sunday").
		"Weekly": "Days": "Mono "Wedr	[ day", nesday",
	Monthly		at indicates a job scheduled to run on a specific day or days every ame time with the parameters:
		Name	Description
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
		Day	The number of the day, in the month, to run the job.
		"Monthly": "Day":	

Name	Description		
	Note: Although the Swagger Example Value may show examples of various other scheules, only the schedules shown here—that are available in the Management Portal for functionality—are valid for this endpoint.		
EmailRecipients	An array containing the email addresses of users configured as recipients of the scheduled report, if any.		
RuntimePara- meters		parameters to be used at run time configured in the report schedule. vary depending on the report selected. Runtime parameters may include	
	Name	Description	
	CertAuth	The certificate authority or authorities selected to report on.	
	EndDate	The end date selected for the reporting period to report on. This is configured as a certain number of days, weeks or months before or after the current date (e.g. 0 days before today—meaning today).	
	EvalDate	The evaluation date selected for the reporting period to report on.  This is configured as a certain number of days, weeks or months before or after the current date (e.g. 30 days before today).	
	Metadata	The custom metadata fields selected to include in the report.	
	MinCertCount	The minimum number of certificates that must have been issued for the given template before the template will be included in the report.	
	OrchestratorPool	The orchestrator pool selected to report on.	
	PeriodCount	The number of days, weeks or months selected to report on.	
	PeriodSize	The selected reporting period (day, weeks or months).	
	Requesters	The certificate requesters selected to include in the report.	
	SSHKeyType	The SSH key type(s) selected to report on.	
	StartDate	The start date selected for the reporting period to report on. This is configured as a certain number of days, weeks or months before or after the current date (e.g. 30 days before today).	
	TemplateIds	The Keyfactor Command identifiers for the templates to include in the report.	

## 2.2.22 Security Identities

The Security Identities component of the Keyfactor API includes methods necessary to list, add, and delete security identities. The permissions set with these methods are used to control access to all aspects of Keyfactor Command.

Table 372: Security Identities Endpoints

Endpoint	Method	Description	Link
/{id}	DELETE	Deletes the security identity with the specified ID.	DELETE Security Identities ID below
/{id}	GET	Returns permission details for the security identity with the specified ID.	GET Security Identities ID on the next page
/Lookup	GET	Validates that the identity with the specified name exists.	GET Security Identities Lookup on page 819
/	GET	Returns all security identities with filtering and output options.	GET Security Identities on page 820
/	POST	Adds a new security identity into Keyfactor Command.	POST Security Identities on page 839

### 2.2.22.1 DELETE Security Identities ID

The DELETE /Security/Identities/{id} method is used to delete the security identity with the specified ID from Keyfactor Command. Use the *GET* /Security/Identities method (see <u>GET Security Identities on page 820</u>) to determine the ID of the security identity you wish to delete. This endpoint returns 204 with no content upon success.



Table 373: DELETE Security Identities {id} Input Parameters

Name	In	Description
id	Path	<b>Required</b> . The ID of the security identity that should be deleted from Keyfactor Command.

## 2.2.22.2 GET Security Identities ID

The GET /Security/Identities/{id} method is used to return the security identities configured in Keyfactor Command with the specified ID. This method returns HTTP 200 OK on a success with the details of the security identity's permissions.



Table 374: GET Security Identities {id} Input Parameters

Name	In	Description
id	Path	<b>Required</b> . An integer indicating the Keyfactor Command reference ID of the security identity to retrieve.
		Use the <i>GET /Security/Identities</i> method (see <u>GET Security Identities on page 820</u> ) to retrieve a list of all the security identities to determine the identity's ID.

Table 375: GET Security Identities {id} Response Data

Name	Description			
Identity	A string containing the account name for the security identity. For Active Directory users and groups, this will be in the form DOMAIN\\user or group name. For example: KEYEXAMPLE\\PKI Administrators			
SecuredAreaPermissions	An object containing a series of arrays with information about the global permissions granted to the security identity. Global permission information includes:			
	Name	Description		
	Permission	A string indicating the permission granted. In the case of global permissions, this is the name of the role followed by the level of permission granted, the choices for which vary depending on the role.		
	GrantedByRoles	An object containing a list of roles that grant that permission.		
	For example:			
	"SecuredAreaPermissions": [  {     "Permission": "AdminPortal:Read",     "GrantedByRoles": [         "Read Only",         "Staff"      ] }, {     "Permission": "Reports:Read",     "GrantedByRoles": [         "Read Only"     ] }, ]			
	For more information about global permissions, see the <u>Security Roles and Identities</u> page in the <i>Keyfactor Command Reference Guide</i> .			
CollectionPermissions	An object containing information about the certificate collection permissions granted to the security identity. Collection permission information includes:			

Name	Description			
	Name	Description		
	Permission	A string indicating the permission granted. In the case of collection permissions, this is the name of the certificate collection followed by the level of permission granted.		
	GrantedByRoles	An array containing a list of roles that grant that permission.		
	For example:			
	<pre>"CollectionPermissions": [     {           "Permission": "Issued in the Last Week:Certificates_Read",           "GrantedByRoles": [</pre>			
	For more information about collection permissions, see the <u>Certificate Permissions</u> page in the <i>Keyfactor Command Reference Guide</i> .			
ContainerPermissions		ormation about the global permissions granted to the security nission information includes:		
	Name	Description		
	Permission  A string indicating the permission granted. In the case of container permissions, this is the name of the certificate container followed by the level of permission granted (reschedule or modify).			
	GrantedByRoles An array containing a list of roles that grant that permission.			
	For example:			
	"ContainerPermissions": [			

Name	Description
	<pre>{     "Permission": "IIS Personal:CertificateStoreManagement_Read",     "GrantedByRoles": [         "Power Users",         "Staff"     ] }, {     "Permission": "F5 SSL Profiles REST:CertificateStoreManagement_ Schedule",     "GrantedByRoles": [         "Power Users"     ] }, ]</pre>
	For more information about container permissions, see the <u>Container Permissions</u> page in the <u>Keyfactor Command Reference Guide</u> .

### 2.2.22.3 GET Security Identities Lookup

The GET /Security/Identities/Lookup method is used to confirm that the security identity specified is valid for the environment—the Active Directory forest in which Keyfactor Command is installed and any forests in a two-way trust (or one-way trust in a direction that allows the lookup to occur). It can be used to query an identity in the source identity store (Active Directory) to confirm its validity before using POST /Security/Identities (see POST Security Identities on page 839) to create a new identity in Keyfactor Command with that user or group. This method returns HTTP 200 OK on a success with a response of true or false.



Table 376: GET Security Identities Lookup Input Parameters

Name	In	Description
Name	Query	<b>Required</b> . The identity name in the source identity store. For Active Directory users and groups, this can be given either as DOMAIN\name or name@domain.com. For users in the local domain (the domain in which the Keyfactor Command server is installed), the lookup may be done without a domain name.

Table 377: GET Security Identities Lookup Response Data

Name	Description
Valid	A Boolean that indicates whether the provided name is valid (true) or not (false).

### 2.2.22.4 GET Security Identities

The GET /Security/Identities method is used to return the list of security identities configured in Keyfactor Command. This method returns HTTP 200 OK on a success with the details of the security identities.



Table 378: GET Security Identities Input Parameters

Name	In	Description
validate	Query	A boolean that specifies whether the optional parameter of <i>validate</i> is <b>false</b> , which allows the AuditXML validation to be skipped when loading records, or <b>true</b> (or not specified) in which case validation will occur. The default is <b>true</b> .
queryString		Not used.
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>Id</i> .
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.

Table 379: GET Security Identities Response Data

Name	Description					
Id	An integer c	ontainin	g the Keyfactor Command reference ID for the security identity.			
Accoun- tName	be in the for	m DOM	he account name for the security identity. For Active Directory users and groups, this will AIN\\user or group name. For example: \\PKI Administrators			
Iden- tityType	A string indi	cating th	ne type of identity—User or Group.			
Roles	An array cor includes:	ntaining	information about the security roles assigned to the security identity. Role information			
	Name	In	Description			
	Id	Id Bo- Required. An integer containing the Keyfactor Command identifier for the security role. Use the GET /Security/Roles method (see GET Security Roles on page 898) to retrieve a list of all the security roles to determine the role's ID.				
	Name	Bo- <b>Required</b> . A string containing the short reference name for the security role.				
	Descrip- tion	Bo- dy	Required. A string containing the description for the security role.			
	Enabled	Bo- dy	A Boolean that indicates whether the security role is enabled (true) or not (false). Security roles that have been disabled cannot be assigned to security identities. The default is <i>true</i> .  This is considered deprecated and may be removed in a future release.			
	Immut- Bo- A Boolean that indicates whether the security role has been marked as editable able or not (false). Internal Keyfactor Command roles are not editable. This setting reserved for Keyfactor Command internal use.					
	Valid	A Boolean that indicates whether the security role's audit XML is valid (true) or n dy (false). A security role may become invalid if Keyfactor Command determines the appears to have been tampered with. This setting is not end-user configurable.				
	Private	Bo- dy	A Boolean that indicates whether the security role has been marked private (true) or not (false). The default is <i>false</i> .  This is considered deprecated and may be removed in a future release.			

Name	Description													
	Name	In	Description											
	Iden- tities		An array containing in role. Identity details i		about the security ide	ntities assigned to the security								
			Name	Descri	ption									
			Id		ger containing the Keyl security identity.	factor Command identifier								
		Accour		tity. For	Active Directory users	nt name for the security iden- s and groups, this will be in oup name. For example: ninistrators								
				IdentityType	A string	; indicating the type of	identity—User or Group.							
			SID			y identifier from the source ctory) for the security iden-								
	Permis- sions		An object containing to of Name:Value pairs.			ole in a comma-separated list								
											Name		Value	Description
												AdminPortal (a.k.a. Management	: Portal)	Read
			AgentAutoRegistrat	ion	Read	Users can view the agent auto-registration settings; Users must also have Read permissions for Agent Management.								
									A			AgentAutoRegistrat	ion	Modify

Name	Description					
	Name	In	n Description			
			Name	Value	Description	
			AgentManagement	Read	Users can access the Management Portal areas and API endpoints to:  • View orchestrators, including filtering the orchestrator management grid  • View orchestrator jobs, including status, schedules, failures and warnings	
			AgentManagement	Modify	Users can access the Management Portal areas and API endpoints to:  • Manage orches- trators, including approving and disap- proving them  • Unschedule and reschedule orchestrator jobs	
			АРІ	Read	Users can call the Classic (CMS) API endpoints.	
			ApplicationSettings	Read	Users can view the applic-	

Name	Descriptio	n			
	Name	In	Description		
			Name	Value	Description
					ation settings.
			ApplicationSettings	Modify	Users can modify the application settings.
			Auditing	Read	Users can access the Audit Log page in the Management Portal, and will be able to make API requests to obtain data from the audit log (query, etc.). The System Settings drop-down menu will display the Audit Log option to users with the Auditing Read permission.
			CertificateCollections	Modify	Users can add or edit certificate collections. See Certificate Permissions in the Keyfactor Command Reference Guide for more information.
			CertificateEnrollment	EnrollPFX	Users can use the PFX Enrollment page in the Management Portal and use the PFX enrollment related API endpoints.
			CertificateEnrollment	EnrollCSR	Users can use the CSR Enrollment page in the Management Portal and use the CSR enrollment related API endpoints.
			CertificateEnrollment	CsrGeneration	Users can use the CSR

Name	Description					
	Name	In	Description			
			Name	Value	Description	
					Generation page in the Management Portal and use the CSR generation related API endpoints.	
			CertificateEnrollment	PendingCsr	Users can use manage pending CSRs.	
			Certificate Metadata Types	Read	Users can read custom metadata attribute definitions on the Certificate Metadata page in the Management Portal and with related API endpoints.	
			CertificateMetadataTypes	Modify	Users can add, edit, and delete custom metadata attribute definitions on the Certificate Metadata page in the Management Portal and with related API endpoints.	
			Certi- ficateStoreManagement	Read	Users can view certificate stores—including the stores and containers but not discovery records—and certificate store types. Users who also have Read permissions for <i>Certificates</i> can view inventory for a certificate store.	
					See Container Permissions in the Keyfactor Command Reference Guide for more inform-	

Name	Descriptio	n						
	Name	In	Description					
			Name	Value	Description			
					ation.			
						Certi- ficateStoreManagement	Modify	Users can manage certificate stores—including the stores, containers, and discovery process—and certificate store types. Note that this permission does not control additions of certificates to certificate stores.
			Certi- ficateStoreManagement	Schedule	Users can add certificates to certificate stores, renew/reissue certificates, and remove certificates from certificate stores.			
			Certificates	Read	Users can view certificates in certificate search and certificate collections in the Management Portal and with related API endpoints, including certificate history, and can download certificates. Users who also have Read permissions for Certificate Store Management or container permissions can add certificates to certificate stores.  See Certificate Permissions in the Keyfactor Command Reference			

Name	Description						
	Name	In	Description				
			Name	Value	Description		
					Guide for more information.		
			Certificates	Import	Users can import certificates through Add Certificate in the Management Portal and with related API endpoints. Users who also have Read permissions for <i>Certificate Store Management</i> or container permissions can add certificates to certificate stores from Add Certificate.		
			Certificates	Recover	Users can download the certificates with their private key.		
			Certificates	Revoke	Users can revoke certificates through Certificate Search and Certificate Collections in the Management Portal and with related API endpoints.		
			Certificates	Delete	Users can delete certificates and, if applicable, the private keys of the certificates from the Keyfactor Command database.		
			Certificates	ImportPrivateKey	Users can save the private key for the certificate in the Keyfactor Command database.		

Name	Description	n			
	Name	In	Description		
			Name	Value	Description
			Certificates	EditMetadata	Users can modify certificate metadata for certificates accessed through Certificate Search and Certificate Collections in the Management Portal and with related API endpoints.
			Dashboard	Read	Users can view the panels on their personalized dashboard and add and remove them.
			Dashboard	RiskHeader	Users can view the risk header at the top of the dashboard.
			EventHandlerRegistration	Read	Users can view the event handler registration settings.
			EventHandlerRegistration	Modify	Users can modify the event handler registration settings.
			MacAutoEn- rollManagement	Read	Users can view the Mac Auto-Enroll Management settings.
			MacAutoEn- rollManagement	Modify	Users can modify the Mac Auto-Enroll Management settings.
			Monitoring	Read	Users can view the expiration alerts in the Certificate Alerts in the Management Portal and with related

Name	Descriptio	n			
	Name	In	Description		
			Name	Value	Description
					API endpoints, including the alert schedule.
		Monitoring	Modify	Users can modify the expiration alerts, including the alert text, recipients and event handlers. Users can also add new alerts, delete alerts and configure the expiration alert delivery schedule.	
			Monitoring	Test	Users can test the expiration alerts, including sending email to recipients. Users must also have Read permissions for <i>Monitoring</i> .
			PkiManagement	Read	Users can view the Keyfactor Command PKI management settings within the following Management Portal areas and use related endpoints:
			PkiManagement	Modify	Users can modify the Keyfactor Command PKI management settings:

Name	Descriptio	n			
	Name	In	Description		
			Name	Value	Description
					<ul> <li>Import, add, edit, and delete certificate authorities</li> <li>Import certificate templates</li> <li>Add, edit, delete, and test revocation monitoring endpoints</li> <li>Configure revocation monitoring schedule</li> <li>Configure revocation monitoring recipients</li> </ul>
			Priv- ilegedAccessManagement	Read	Users can view PAM providers.
			Priv- ileged Access Management	Modify	Users can add, edit, and delete PAM providers.
			Reports	Read	Users can generate and view reports.
			Reports	Modify	Users can modify the delivery schedule for reports in Report Manager in the Management Portal and add, edit,

Name	Description	on			
	Name	In	Description		
			Name	Value	Description
					and delete custom reports.
					Note: Report scheduling is limited by collection permissions. Users in roles that have Reports: Read and Modify permissions will also need to have Read collection permissions on individual collections to have the ability to add, edit and delete schedules associated with collections. The user will not have access to add, edit and delete schedules for any collections for which they do not have collection Read permissions in addition to Reports permissions.
			SecuritySettings	Read	Users can view the settings for Security Roles

Name	Descriptio	n			
	Name	In	Description		
			Name	Value	Description
					and Security Identities. Users must also have the Read permission for System Settings.
			SecuritySettings	Modify	Users can modify the settings for Security Roles and Security Identities in the Management Portal and with related API endpoints.
			SSH	User	Users can generate their own SSH keys.
			SSH	ServerAdmin	Users can use all SSH functions, except creating server groups and assigning server group owners. Users have limited access to some functions based on server group ownership.  See SSH Permissions in the Keyfactor Command Reference Guide for more information.
			SSH	EnterpriseAdmin	Users can use all SSH functions. See SSH Permissions in the Keyfactor Command Reference Guide for more information.
			SslManagement	Read	Users can view the SSL Network Discovery and

Name	Descriptio	n			
	Name	In	Description		
			Name	Value	Description
					Monitoring area in the Management Portal and with related API endpoints, including defined networks and the network ranges configured for them, agent pools, and scan results. Users can use the query tool on the Results tab to find discovered endpoints and then view the discovered endpoints, including the details for the endpoints.
			SslManagement	Modify	Users can modify the SSL Network Discovery and Monitoring settings:

Name	Descriptio	on			
	Name	In	Description		
			Name	Value	Description
					discovered endpoints from monit- oring
			SystemSettings	Read	Users can view the System Settings for:  • Application Settings • Event Handler Registration to view built-in or custom event hand- lers • API Applications allowed to use the APIs for certificate lifecycle management • SMTP Configuration for email delivery of reports and alerts • Installed components • Licensing • Alerts and Warnings about the health of the

Name	Description	n			
	Name	In	Description		
			Name	Value	Description
					Keyfactor Command system
			SystemSettings	Modify	Users can modify the System Settings for:  • Application Settings to configure many options for Keyfactor Command • Event Handler Registration to add or remove built-in or custom event handlers • Update SMTP Configuration for email delivery of reports and alerts • Installed components, including removing servers from use • Licensing, including the option to replace the existing license file

Name	Description	n			
	Name	In	Description		
			Name	Value	Description
			WorkflowDefinitions	Read	Users can view the configured workflow definitions.
		WorkflowDefinitions	Modify	Users can modify both the built-in and any custom workflow definitions, including the name and description and the configuration for the steps. Users can also add new workflow definitions, delete workflow definitions, publish workflow definitions, and import and export workflow definitions.	
			WorkflowInstances	Manage	Users can manage initiated workflow instances, including stopping, restarting, and deleting them.
		WorkflowInstances	ReadAssignedToM- e	Users can view the work- flow instances that have been initiated and are awaiting input from them.	
					Tip: There is not a security permission at this level that controls whether users can provide

Name	Descriptio	n			
	Name	In	Description		
			Name	Value	Description
					input (a signal) to a workflow instance. This is controlled using the security roles configured on the specific workflow definition.  Any user who holds one of the roles configured in the workflow step that requires a signal may provide the necessary input. The user does not need to hold the ReadAssignedTo-Me WorkflowInstances permission in order to provide the input.
			WorkflowInstances	ReadAll	Users can view all the workflow instances that have been initiated.
			WorkflowInstances	ReadMy	Users can view the work- flow instances that have been initiated by them (e.g. because they enrolled for a certificate).
			WorkflowManagement	Read	Users can view the

Name	Descriptio	n			
	Name	In	Description		
			Name	Value	Description
			(a.k.a. Alerts)		pending, issued, and denied workflow alerts.
		WorkflowManagement (a.k.a. Alerts)	Modify	Users can modify the pending, issued, and denied workflow alerts, including the alert text, recipients, and event handlers. Users can also add new alerts, delete alerts, and configure the pending alert delivery schedule.	
			WorkflowManagement (a.k.a. Alerts)	Test	Users can test the pending alerts, including sending email to recipients. Users must also have Read permissions for <i>Workflow</i> .
			WorkflowManagement (a.k.a. Certificate Requests)	Participate	Users can participate in the pending, issued and denied workflow process by approving or denying certificate requests from the Certificate Requests page or from the individual pages reached from links included in alerts in the Management Portal and with related API endpoints.
			For example:		
			"Permissions": [ "AdminPortal:Read",		

Name	Descriptio	Description					
	Name	Name In Description					
			"Dashboard:Read" ],				
Valid		A Boolean indicating whether the security identity's audit XML is valid (true) or not (false). A security identity may become invalid if Keyfactor Command determines that it appears to have been tampered with.					

#### 2.2.22.5 POST Security Identities

The POST /Security/Identities method is used to create a new security identity in Keyfactor Command. Use the *GET /Security/Identities/Lookup* method (see <u>GET Security Identities Lookup on page 819</u>) before creating the new identity to confirm that the identity you plan to create is valid. This method returns HTTP 200 OK on a success with the details of the new security identity.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: SecuritySettings: *Modify* 



**Tip:** This method cannot be used to assign roles to an identity. Use the *PUT /Security/Roles* method (see PUT Security Roles on page 918) to assign roles to an identity.

Table 380: POST Security Identities Input Parameters

Name	In	Description
AccountName	Body	Required. A string containing the account name for the security identity. For Active Directory user and groups, this will be in the form DOMAIN\\user or group name. For example:  KEYEXAMPLE\\PKI Administrators

Table 381: POST Security Identities Response Data

Name	Description	
Id	An integer containing the Keyfactor Command identifier for the security identity.	
AccountName	A string containing the account name for the security identity. For Active Directory user and groups, this will be in the form DOMAIN\user or group name. For example:  KEYEXAMPLE\\PKI Administrators	
IdentityType	A string indicating the type of identity—User or Group.	
Roles	An array containing information about the security roles assigned to the security identity. For new security identities, this will be blank.	
Valid	A Boolean that indicates whether the security identity's audit XML is valid (true) or not (false). A security identity may become invalid if Keyfactor Command determines that it appears to have been tampered with.	

# 2.2.23 Security Roles Permissions

The Security Roles Permissions component of the Keyfactor API includes methods necessary to list, add, and update security roles permissions at the role, global, container and collection-level.

Table 382: Security Roles Permissions Endpoints

Endpoint	Method	Description	Link
/{id}/Permisssions	GET	Returns all permissions associated with the security role that matches the id	GET Security Roles ID Permissions on the next page
/{id}/Permisssions/Global	GET	Returns all global permissions associated with the security role that matches the ID.	GET Security Roles ID Permissions Global on page 843
/{id}/Permisssions/Global	POST	Adds global permissions to the security role that matches the id. Note that the Areas <i>Certificates</i> and <i>CertificateStoreManagement</i> are reserved for collection and container permissions, respectively.	POST Security Roles ID Permissions Global on page 844
/{id}/Permisssions/Global	PUT	Sets global permissions of the security role that matches the ID. Note that the Areas <i>Certificates</i> and <i>CertificateStoreManagement</i> are reserved for collection and container permissions, respectively.	PUT Security Roles ID Permissions Global on page 864
/{id}/Permisssions/Containers	GET	Returns all container permissions associated with the security role that matches the ID.	GET Security Roles ID Permissions Containers on page 885
/{id}/Permisssions/Containers	POST	Adds container permissions to the security role that matches the ID.	POST Security Roles ID Permissions Containers on page 886
/{id}/Permisssions/Containers	PUT	Sets container permissions to the security role that matches the ID.	PUT Security Roles ID Permissions Containers on page 887
/{id}/Permisssions/Collections	GET	Returns all collection permissions associated with the security role that matches the ID.	GET Security Roles ID Permissions Collections on

Endpoint	Method	Description	Link
			page 889
/{id}/Permisssions/Collections	POST	Adds collection permissions to the security role that matches the ID.	POST Security Roles ID Permissions Collections on page 890
/{id}/Permisssions/Collections	PUT	Sets collection permissions to the security role that matches the ID.	PUT Security Roles ID Permissions Collections on page 891

#### 2.2.23.1 GET Security Roles ID Permissions

The GET /Security/Roles/{id}/Permissions method is used to return all permissions associated with the security role that matches the ID. This method returns HTTP 200 OK on a success with certificate store container permission details for the specified security role.



Table 383: GET Security Roles {id} Permissions Input Parameters

Name	In	Description
id	Path	<b>Required</b> . The Keyfactor Command reference ID of the security role for which to retrieve permissions.
		Use the <i>GET /Security/Roles</i> method (see <u>GET Security Roles on page 898</u> ) to retrieve a list of all the security roles to determine the role's ID.

Table 384: GET Security Roles {id} Permissions Response Data

Name	Description			
	An object containing information about the permissions granted to the security role. Details include			
	Name	Description		
	Туре	A string containing the area at which the permission is applied to (global, container, or collection).		
	Area	A string containing the name of the permission (e.g. "Certificates").		
	Permission	A string indicating the permission level granted in the area for this role (e.g. "Read").		

## 2.2.23.2 GET Security Roles ID Permissions Global

The GET /Security/Roles/{id}/Permissions/Global method is used to return all global permissions associated with the security role that matches the ID. This method returns HTTP 200 OK on a success with certificate store container permission details for the specified security role.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: SecuritySettings: *Read* 

Table 385: GET Security Roles {id} Global Permissions Input Parameters

Name	In	Description
id	Path	<b>Required</b> . The Keyfactor Command reference ID of the security role for which to retrieve global permissions.
		Use the <i>GET /Security/Roles</i> method (see <u>GET Security Roles on page 898</u> ) to retrieve a list of all the security roles to determine the role's ID.

Table 386: GET Security Roles {id} Global Permissions Response Data

Name	Description					
	An object containing information about the global permissions granted to the security role. Details include					
	Name	Description				
	Area	A string containing the name of the permission (e.g. "Certificates").				
	Permission	A string indicating the permission level granted in the area for this role (e.g. "Read").				

## 2.2.23.3 POST Security Roles ID Permissions Global

The POST /Security/Roles/{id}/Permissions/Global method is used to add global permissions to the security role that matches the ID. This method returns HTTP 200 OK on a success with global permission details for the specified security role.



**Important:** Only the permission settings included in the command will be affected. Any other permissions settings will not be affected and remain as is.



Note: The API Endpoint utility displays a list of valid global permissions on the endpoint.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: SecuritySettings: *Modify* 

Table 387: POST Security Roles {id}Global Permissions Input Parameters

Name	In	Description						
id	Path	Required. The Keyfactor Command reference ID of the security role for which to set global permissions.  Use the GET /Security/Roles method (see GET Security Roles on page 898) to retrieve a list of all the security roles to determine the role's ID.						
glob- alPermissions	Body	An object cont	taining information about the	global permissions gr	anted for this security role.			
		Name	Description					
		Area	Required. A string indicating "AdminPortal").	g the name of the per	missions to grant (e.g.			
		Permis- sion	<b>Required</b> . A string indicating the permission level to grant (e.g. "Read"). Possible values are:					
			Name	Value	Description			
			AdminPortal (a.k.a. Management Portal)	Read	Users can access the Management Portal. This permission must be enabled for all roles that will access the Management Portal.			
				AgentAutoRegistration  AgentAutoRegistration		AgentAutoRegistration	Read	Users can view the agent auto-registration settings; Users must also have Read permissions for Agent Management.
						Modify	Users can modify the agent auto-registration settings.	
				AgentManagement	Read	Users can access the Management Portal areas and API endpoints to:		

Name	In	Description				
		Name Description				
			Name	Value	Description	
					View orchestrators, including filtering the orchestrator management grid  View orchestrator jobs, including status, schedules, failures and warnings	
			AgentManagement	Modify	Users can access the Management Portal areas and API endpoints to:  • Manage orchestrators, including approving and disapproving them  • Unschedule and reschedule orchestrator jobs	

Name	In	Description			
		Name	Description		
			Name	Value	Description
			API	Read	Users can call the Classic (CMS) API endpoints.
			ApplicationSettings	Read	Users can view the application settings.
			ApplicationSettings	Modify	Users can modify the application settings.
			Auditing	Read	Users can access the Audit Log page in the Management Portal, and will be able to make API requests to obtain data from the audit log (query, etc.). The System Settings drop-down menu will display the Audit Log option to users with the Auditing Read permission.
			CertificateCollections	Modify	Users can add or edit certificate collections. See Certificate Permissions in the Keyfactor Command Reference Guide for more information.
			CertificateEnrollment	EnrollPFX	Users can use the PFX Enrollment page in the Management Portal and use the PFX enroll- ment related API endpoints.

Name	In	Description			
	Name	Name	Description		
			Name	Value	Description
			CertificateEnrollment	EnrollCSR	Users can use the CSR Enrollment page in the Management Portal and use the CSR enroll- ment related API endpoints.
			CertificateEnrollment	CsrGeneration	Users can use the CSR Generation page in the Management Portal and use the CSR gener- ation related API endpoints.
			CertificateEnrollment	PendingCsr	Users can use manage pending CSRs.
			Certi- ficateMetadataTypes	Read	Users can read custom metadata attribute definitions on the Certificate Metadata page in the Management Portal and with related API endpoints.
			Certi- ficateMetadataTypes	Modify	Users can add, edit, and delete custom metadata attribute definitions on the Certificate Metadata page in the Management Portal and with related API endpoints.
			Certi- ficateStoreManagement	Read	Users can view certi- ficate stores— including the stores and containers but not

Name	In	Description				
		Name	Description			
			Name	Value	Description	
					discovery records— and certificate store types. Users who also have Read permissions for <i>Certificates</i> can view inventory for a certificate store. See <i>Container Permis-</i> sions in the <i>Keyfactor</i> Command Reference Guide for more information.	
			Certi- ficateStoreManagement	Modify	Users can manage certificate stores—including the stores, containers, and discovery process—and certificate store types. Note that this permission does not control additions of certificates to certificate stores.	
			Certi- ficateStoreManagement	Schedule	Users can add certi- ficates to certificate stores, renew/reissue certificates, and remove certificates from certificate stores.	
			Certificates	Read	Users can view certificates in certificate search and certificate collections in the Management Portal	

Name	In	Description			
		Name	Description		
			Name	Value	Description
					and with related API endpoints, including certificate history, and can down- load certificates. Users who also have Read permissions for Certi- ficate Store Manage- ment or container permissions can add certificates to certi- ficate stores. See Certificate Permis- sions in the Keyfactor Command Reference Guide for more inform- ation.
			Certificates	Import	Users can import certificates through Add Certificate in the Management Portal and with related API endpoints. Users who also have Read permissions for Certificate Store Management or container permissions can add certificates to certificate stores from Add Certificate.
			Certificates	Recover	Users can download the certificates with their private key.

Name	In	Description			
		Name	Description		
			Name	Value	Description
			Certificates	Revoke	Users can revoke certificates through Certificate Search and Certificate Collections in the Management Portal and with related API endpoints.
			Certificates	Delete	Users can delete certificates and, if applicable, the private keys of the certificates from the Keyfactor Command database.
			Certificates	ImportPriv- ateKey	Users can save the private key for the certificate in the Keyfactor Command database.
			Certificates	EditMetadata	Users can modify certificate metadata for certificates accessed through Certificate Search and Certificate Collections in the Management Portal and with related API endpoints.
			Dashboard	Read	Users can view the panels on their personalized dashboard and add and remove them.
			Dashboard	RiskHeader	Users can view the risk header at the top of

Name	In	Description	ı			
		Name	Description	Description		
			Name	Value	Description	
					the dashboard.	
			EventHand- lerRegistration	Read	Users can view the event handler registration settings.	
			EventHand- lerRegistration	Modify	Users can modify the event handler registration settings.	
			MacAutoEn- rollManagement	Read	Users can view the Mac Auto-Enroll Management settings.	
			MacAutoEn- rollManagement	Modify	Users can modify the Mac Auto-Enroll Management settings.	
			Monitoring	Read	Users can view the expiration alerts in the Certificate Alerts in the Management Portal and with related API endpoints, including the alert schedule.	
			Monitoring	Modify	Users can modify the expiration alerts, including the alert text, recipients and event handlers. Users can also add new alerts, delete alerts and configure the expiration alert delivery schedule.	

Name	In	Description					
		Name	Description				
			Name	Value	Description		
			Monitoring	Test	Users can test the expiration alerts, including sending email to recipients. Users must also have Read permissions for <i>Monitoring</i> .		
			PkiManagement	Read	Users can view the Keyfactor Command PKI management settings within the following Manage- ment Portal areas and use related endpoints:  • Certificate Author- ities • Certificate Templates • Revoc- ation Monit- oring		
			PkiManagement	Modify	Users can modify the Keyfactor Command PKI management settings:  Import, add, edit, and delete certificate author- ities Import certificate		

Name	In	Description			
		Name	Description		
			Name	Value	Description
					templates  • Add, edit, delete, and test revocation monitoring endpoints  • Configure revocation monitoring schedule  • Configure revocation monitoring recipients
			Priv- ileged Ac- cess Management	Read	Users can view PAM providers.
			Priv- ilegedAc- cessManagement	Modify	Users can add, edit, and delete PAM providers.
			Reports	Read	Users can generate and view reports.
			Reports	Modify	Users can modify the delivery schedule for reports in Report Manager in the Management Portal and add, edit, and delete custom reports.

Name	In	Description			
		Name	Description		
			Name	Value	Description
					Note: Report scheduling is limited by collection permissions. Users in roles that have Reports: Read and Modify permissions will also need to have Read collection permissions on individual collections to have the ability to add, edit and delete schedules associated with collections. The user will not have access to add, edit and delete schedules for any collections for which they do not have collection Read permissions in addition to Reports

Name In	Description			
	Name	Description		
		Name	Value	Description
				permissions.
		SecuritySettings	Read	Users can view the settings for Security Roles and Security Identities. Users must also have the Read permission for System Settings.
		SecuritySettings	Modify	Users can modify the settings for Security Roles and Security Identities in the Management Portal and with related API endpoints.
		SSH	User	Users can generate their own SSH keys.
		SSH	ServerAdmin	Users can use all SSH functions, except creating server groups and assigning server group owners. Users have limited access to some functions based on server group ownership.  See SSH Permissions in the Keyfactor Command Reference Guide for more information.
		SSH	EnterpriseAdmin	Users can use all SSH

Name	In	Description			
		Name	Description		
			Name	Value	Description
					functions.  See SSH Permissions in the Keyfactor Command Reference Guide for more information.
			SslManagement	Read	Users can view the SSL Network Discovery and Monitoring area in the Management Portal and with related API endpoints, including defined networks and the network ranges configured for them, agent pools, and scan results. Users can use the query tool on the Results tab to find discovered endpoints and then view the discovered endpoints, including the details for the endpoints.
			SslManagement	Modify	Users can modify the SSL Network Discovery and Monitoring settings:  • Create, edit, and delete networks, including scan

Name	In	Description			
		Name	Description		
			Name	Value	Description
					schedules and noti- fication recipients  • Add, edit, and delete network ranges for networks  • Add, edit, and delete agent pools  • Add and remove discovered endpoints from monit- oring
			SystemSettings	Read	Users can view the System Settings for:  • Application Settings  • Event Handler Registration to view builtin or custom event handlers  • API Application:

Name I	In Descrip	tion		
	Name	Description		
		Name	Value	Description
				ations allowed to use the APIs for certificate lifecycle manage- ment  SMTP Config- uration for email delivery of reports and alerts  Installed compon- ents  Licensing  Alerts and Warnings about the health of the Keyfactor Command system
		SystemSettings	Modify	Users can modify the System Settings for:  • Application Settings to configure many options for

Name	In	Description			
		Name	Description		
			Name	Value	Description
					Keyfactor Command  Event Handler Regis- tration to add or remove built-in or custom event handlers  Update SMTP Config- uration for email delivery of reports and alerts  Installed compon- ents, including removing servers from use  Licensing, including the option to replace the existing license file
			WorkflowDefinitions	Read	Users can view the configured workflow

Name	In	Description			
		Name	Description		
			Name	Value	Description
					definitions.
			Workflow Definitions	Modify	Users can modify both the built-in and any custom workflow definitions, including the name and description and the configuration for the steps. Users can also add new workflow definitions, delete workflow definitions, publish workflow definitions, and import and export workflow definitions.
			WorkflowInstances	Manage	Users can manage initiated workflow instances, including stopping, restarting, and deleting them.
			WorkflowInstances	ReadAssignedTo-Me	Users can view the workflow instances that have been initiated and are awaiting input from them.  Tip: There is not a security permission at this level that controls whether users can provide

Name Ir	Description			
	Name	Description		
		Name	Value	Description
				input (a signal) to a workflow instance. This is controlled using the security roles configured on the specific workflow definition.  Any user who holds one of the roles configured in the workflow step that requires a signal may provide the necessary input. The user does not need to hold the ReadAssigned-ToMe WorkflowInstances permission in order to provide the input.
		WorkflowInstances	ReadAll	Users can view all the workflow instances that have been initiated.

Name	In	Description			
		Name	Description		
			Name	Value	Description
			WorkflowInstances	ReadMy	Users can view the workflow instances that have been initiated by them (e.g. because they enrolled for a certificate).
			WorkflowManagement (a.k.a. Alerts)	Read	Users can view the pending, issued, and denied workflow alerts.
			WorkflowManagement (a.k.a. Alerts)	Modify	Users can modify the pending, issued, and denied workflow alerts, including the alert text, recipients, and event handlers. Users can also add new alerts, delete alerts, and configure the pending alert delivery schedule.
			WorkflowManagement (a.k.a. Alerts)	Test	Users can test the pending alerts, including sending email to recipients. Users must also have Read permissions for Workflow.
			WorkflowManagement (a.k.a. Certificate Requests)	Participate	Users can participate in the pending, issued and denied workflow process by approving or denying certificate requests from the

Name	In	Description	1		
		Name	Description		
			Name	Value	Description
					Certificate Requests page or from the individual pages reached from links included in alerts in the Management Portal and with related API endpoints.

Table 388: POST Security Roles (id) Global Permissions Response Data

Name	Description				
	An object containin	An object containing information about the global permissions granted to the security role. Details include:			
	Name	Description			
	Area	A string containing the name of the permission (e.g. "Certificates").			
	Permission	A string indicating the permission level granted in the area for this role (e.g. "Read").			

## 2.2.23.4 PUT Security Roles ID Permissions Global

The PUT /Security/Roles/{id}/Permissions/Global method is used to update the global permissions granted to the specified security role by ID. Note that the areas *Certificates* and *CertificateStoreManagement* are reserved for collection and container permissions. This method returns HTTP 200 OK on a success with global permission details for the specified security role.



**Warning:** Any previously defined permissions of the given type (e.g. global) that are not submitted with their full existing data using this method will be cleared of their existing data. Existing data for other types will be retained. When using this method, you should first do a GET to retrieve all the permissions of the given type for the role you want to update, enter corrected data into the field(s) you want to update, and then submit all the fields using PUT, including the fields that contain values but which you are not changing. If you just wish to add permissions without modifying existing permissions, use the POST method.



**Note:** The API Endpoint utility displays a list of valid global permissions on the endpoint.



Table 389: PUT Security Roles {id}Global Permissions Input Parameters

Name	In	Description					
id	Path	Required. The Keyfactor Command reference ID of the security role for which to set global permissions.  Use the GET /Security/Roles method (see GET Security Roles on page 898) to retrieve a list of all the security roles to determine the role's ID.					
glob- alPermissions	Body		An object containing information about the global permissions granted for this security role. Details include:				
		Name	Description				
		Area	Required. A string indicating "AdminPortal").	g the name of the per	missions to grant (e.g.		
		Permis- sion	<b>Required</b> . A string indicating the permission level to grant (e.g. "Read"). Possible values are:				
			Name	Value	Description		
			AdminPortal (a.k.a. Management Portal)	Read	Users can access the Management Portal. This permission must be enabled for all roles that will access the Management Portal.		
			AgentAutoRegistration	Read	Users can view the agent auto-registration settings; Users must also have Read permissions for Agent Management.		
			AgentAutoRegistration	Modify	Users can modify the agent auto-registration settings.		
			Agent	AgentManagement	Read	Users can access the Management Portal areas and API endpoints to:	

Name	In	Description			
		Name	Description		
			Name	Value	Description
					<ul> <li>View orchestrators, including filtering the orchestrator management grid</li> <li>View orchestrator jobs, including status, schedules, failures and warnings</li> </ul>
			AgentManagement	Modify	Users can access the Management Portal areas and API endpoints to:  • Manage orchestrators, including approving and disapproving them  • Unschedule and reschedule orchestrator jobs

Name	In	Description					
		Name	Description				
			Name	Value	Description		
			API	Read	Users can call the Classic (CMS) API endpoints.		
			ApplicationSettings	Read	Users can view the application settings.		
			ApplicationSettings	Modify	Users can modify the application settings.		
			Auditing	Read	Users can access the Audit Log page in the Management Portal, and will be able to make API requests to obtain data from the audit log (query, etc.). The System Settings drop-down menu will display the Audit Log option to users with the Auditing Read permission.		
			CertificateCollections	Modify	Users can add or edit certificate collections. See Certificate Permissions in the Keyfactor Command Reference Guide for more information.		
			CertificateEnrollment	EnrollPFX	Users can use the PFX Enrollment page in the Management Portal and use the PFX enroll- ment related API endpoints.		

Name	In	Description			
	Name	Description			
			Name	Value	Description
			CertificateEnrollment	EnrollCSR	Users can use the CSR Enrollment page in the Management Portal and use the CSR enroll- ment related API endpoints.
			CertificateEnrollment	CsrGeneration	Users can use the CSR Generation page in the Management Portal and use the CSR gener- ation related API endpoints.
			CertificateEnrollment	PendingCsr	Users can use manage pending CSRs.
			Certi- ficateMetadataTypes	Read	Users can read custom metadata attribute definitions on the Certificate Metadata page in the Management Portal and with related API endpoints.
			Certi- ficateMetadataTypes	Modify	Users can add, edit, and delete custom metadata attribute definitions on the Certificate Metadata page in the Management Portal and with related API endpoints.
			Certi- ficateStoreManagement	Read	Users can view certi- ficate stores— including the stores and containers but not

Name	In	Description			
		Name	Description		
			Name	Value	Description
					discovery records— and certificate store types. Users who also have Read permissions for <i>Certificates</i> can view inventory for a certificate store. See <i>Container Permis-</i> sions in the <i>Keyfactor</i> Command Reference Guide for more information.
			Certi- ficateStoreManagement	Modify	Users can manage certificate stores— including the stores, containers, and discovery process— and certificate store types. Note that this permission does not control additions of certificates to certificate stores.
			Certi- ficateStoreManagement	Schedule	Users can add certificates to certificate stores, renew/reissue certificates, and remove certificates from certificate stores.
			Certificates	Read	Users can view certificates in certificate search and certificate collections in the Management Portal

Name	In	Description	ı				
		Name	e Description				
			Name	Value	Description		
					and with related API endpoints, including certificate history, and can down- load certificates. Users who also have Read permissions for Certi- ficate Store Manage- ment or container permissions can add certificates to certi- ficate stores. See Certificate Permis- sions in the Keyfactor Command Reference Guide for more inform- ation.		
			Certificates	Import	Users can import certificates through Add Certificate in the Management Portal and with related API endpoints. Users who also have Read permissions for Certificate Store Management or container permissions can add certificates to certificate stores from Add Certificate.		
			Certificates	Recover	Users can download the certificates with their private key.		

Name	In	Description					
		Name	Description				
			Name	Value	Description		
			Certificates	Revoke	Users can revoke certificates through Certificate Search and Certificate Collections in the Management Portal and with related API endpoints.		
			Certificates	Delete	Users can delete certificates and, if applicable, the private keys of the certificates from the Keyfactor Command database.		
			Certificates	ImportPriv- ateKey	Users can save the private key for the certificate in the Keyfactor Command database.		
			Certificates	EditMetadata	Users can modify certificate metadata for certificates accessed through Certificate Search and Certificate Collections in the Management Portal and with related API endpoints.		
			Dashboard	Read	Users can view the panels on their personalized dashboard and add and remove them.		
			Dashboard	RiskHeader	Users can view the risk header at the top of		

Name	In	Description			
		Name	Description		
			Name	Value	Description
					the dashboard.
			EventHand- lerRegistration	Read	Users can view the event handler registration settings.
			EventHand- lerRegistration	Modify	Users can modify the event handler registration settings.
			MacAutoEn- rollManagement	Read	Users can view the Mac Auto-Enroll Management settings.
			MacAutoEn- rollManagement	Modify	Users can modify the Mac Auto-Enroll Management settings.
			Monitoring	Read	Users can view the expiration alerts in the Certificate Alerts in the Management Portal and with related API endpoints, including the alert schedule.
			Monitoring	Modify	Users can modify the expiration alerts, including the alert text, recipients and event handlers. Users can also add new alerts, delete alerts and configure the expiration alert delivery schedule.

Name	In	Description	ı				
		Name	Description	Description			
			Name	Value	Description		
			Monitoring	Test	Users can test the expiration alerts, including sending email to recipients. Users must also have Read permissions for <i>Monitoring</i> .		
			PkiManagement	Read	Users can view the Keyfactor Command PKI management settings within the following Manage- ment Portal areas and use related endpoints:		
			PkiManagement	Modify	Users can modify the Keyfactor Command PKI management settings:  Import, add, edit, and delete certificate author- ities Import certificate		

Name	In	Description					
		Name	Description	Description			
			Name	Value	Description		
				templates  • Add, edit, delete, and test revocation monitoring endpoints  • Configure revocation monitoring schedule  • Configure revocation monitoring recipients			
			Priv- ileged Ac- cess Management	Read	Users can view PAM providers.		
			Priv- ilegedAc- cessManagement	Modify	Users can add, edit, and delete PAM providers.		
			Reports	Read	Users can generate and view reports.		
			Reports	Modify	Users can modify the delivery schedule for reports in Report Manager in the Management Portal and add, edit, and delete custom reports.		

Name	In	Description			
		Name	Description		
			Name	Value	Description
					Note: Report scheduling is limited by collection permissions. Users in roles that have Reports: Read and Modify permissions will also need to have Read collection permissions on individual collections to have the ability to add, edit and delete schedules associated with collections. The user will not have access to add, edit and delete schedules for any collections for which they do not have collection Read permissions in addition to Reports

Name In	Description			
	Name	Description		
		Name	Value	Description
				permissions.
		SecuritySettings	Read	Users can view the settings for Security Roles and Security Identities. Users must also have the Read permission for System Settings.
		SecuritySettings	Modify	Users can modify the settings for Security Roles and Security Identities in the Management Portal and with related API endpoints.
		SSH	User	Users can generate their own SSH keys.
		SSH	ServerAdmin	Users can use all SSH functions, except creating server groups and assigning server group owners. Users have limited access to some functions based on server group ownership.  See SSH Permissions in the Keyfactor Command Reference Guide for more information.
		SSH	EnterpriseAdmin	Users can use all SSH

Name	In	Description			
		Name	Description		
			Name	Value	Description
					functions.  See SSH Permissions in the Keyfactor Command Reference Guide for more information.
			SslManagement	Read	Users can view the SSL Network Discovery and Monitoring area in the Management Portal and with related API endpoints, including defined networks and the network ranges configured for them, agent pools, and scan results. Users can use the query tool on the Results tab to find discovered endpoints and then view the discovered endpoints, including the details for the endpoints.
			SslManagement	Modify	Users can modify the SSL Network Discovery and Monitoring settings:  • Create, edit, and delete networks, including scan

Name	In	Description			
		Name	Description		
			Name	Value	Description
					schedules and noti- fication recipients  • Add, edit, and delete network ranges for networks  • Add, edit, and delete agent pools  • Add and remove discovered endpoints from monit- oring
			SystemSettings	Read	Users can view the System Settings for:  • Application Settings  • Event Handler Registration to view builtin or custom event handlers  • API Application:

Name I	In Descrip	tion		
	Name	Description		
		Name	Value	Description
				ations allowed to use the APIs for certificate lifecycle manage- ment  SMTP Config- uration for email delivery of reports and alerts  Installed compon- ents  Licensing  Alerts and Warnings about the health of the Keyfactor Command system
		SystemSettings	Modify	Users can modify the System Settings for:  • Application Settings to configure many options for

Name	In	Description			
		Name	Description		
			Name	Value	Description
					Keyfactor Command  Event Handler Regis- tration to add or remove built-in or custom event handlers  Update SMTP Config- uration for email delivery of reports and alerts  Installed compon- ents, including removing servers from use  Licensing, including the option to replace the existing license file
			WorkflowDefinitions	Read	Users can view the configured workflow

Name	In	Description			
		Name	Description		
			Name	Value	Description
					definitions.
			Workflow Definitions	Modify	Users can modify both the built-in and any custom workflow definitions, including the name and description and the configuration for the steps. Users can also add new workflow definitions, delete workflow definitions, publish workflow definitions, and import and export workflow definitions.
			WorkflowInstances	Manage	Users can manage initiated workflow instances, including stopping, restarting, and deleting them.
			WorkflowInstances	ReadAssignedTo-Me	Users can view the workflow instances that have been initiated and are awaiting input from them.  Tip: There is not a security permission at this level that controls whether users can provide

Name Ir	Description			
	Name	Description		
		Name	Value	Description
				input (a signal) to a workflow instance. This is controlled using the security roles configured on the specific workflow definition.  Any user who holds one of the roles configured in the workflow step that requires a signal may provide the necessary input. The user does not need to hold the ReadAssigned-ToMe WorkflowInstances permission in order to provide the input.
		WorkflowInstances	ReadAll	Users can view all the workflow instances that have been initiated.

Name	In	Description			
		Name	Description		
			Name	Value	Description
			WorkflowInstances	ReadMy	Users can view the workflow instances that have been initiated by them (e.g. because they enrolled for a certificate).
			WorkflowManagement (a.k.a. Alerts)	Read	Users can view the pending, issued, and denied workflow alerts.
			WorkflowManagement (a.k.a. Alerts)	Modify	Users can modify the pending, issued, and denied workflow alerts, including the alert text, recipients, and event handlers. Users can also add new alerts, delete alerts, and configure the pending alert delivery schedule.
			WorkflowManagement (a.k.a. Alerts)	Test	Users can test the pending alerts, including sending email to recipients. Users must also have Read permissions for Workflow.
			WorkflowManagement (a.k.a. Certificate Requests)	Participate	Users can participate in the pending, issued and denied workflow process by approving or denying certificate requests from the

Name	In	Description			
		Name	Description		
			Name	Value	Description
					Certificate Requests page or from the individual pages reached from links included in alerts in the Management Portal and with related API endpoints.

Table 390: PUT Security Roles {id} Global Permissions Response Data

Name	Description			
	An object containin	An object containing information about the global permissions granted to the security role. Details include:		
	Name	Description		
	Area	A string containing the name of the permission (e.g. "Certificates").		
	Permission	A string indicating the permission level granted in the area for this role (e.g. "Read").		

## 2.2.23.5 GET Security Roles ID Permissions Containers

The GET /Security/Roles/{id}/Permissions/Containers method is used to return all certificate store container permissions associated with the security role that matches the ID. This method returns HTTP 200 OK on a success with certificate store container permission details for the specified security role.



Table 391: GET Security Roles {id} Permissions Containers Input Parameters

Name	In	Description
id	Path	Required. The Keyfactor Command reference ID of the security role for which to retrieve certificate store container permissions.  Use the GET /Security/Roles method (see GET Security Roles on page 898) to retrieve a list of all the security roles to determine the role's ID.

Table 392: GET Security Roles {id} Permissions Containers Response Data

Name	Description		
	An object containing information about the certificate store container permissions granted to the security role. Details include:		
	Name	Description	
	ContainerId	An integer containing the container ID.	
	Name	A string containing the name of the certificate store container.	
	Permission	A string indicating the permission granted on the entity for this role.	

#### 2.2.23.6 POST Security Roles ID Permissions Containers

The POST /Security/Roles/{id}/Permissions/Containers method is used to add new container permissions to the security role that matches the ID. This method returns HTTP 200 OK on a success with certificate store container permission details for the specified security role.



**Important:** Only the permission settings included in the command will be affected. Any other permissions settings will not be affected and remain as is.



Note: The API Endpoint utility displays a list of valid global permissions on the endpoint.



Table 393: POST Security Roles {id} Permissions Containers Input Parameters

Name	In	Description						
id	Path	Required. The Keyfactor Command reference ID of the security role for which to set certificate store container permissions.  Use the GET /Security/Roles method (see GET Security Roles on page 898) to retrieve a list of all the security roles to determine the role's ID.						
containerPermissions	Body		g information about the permissions granted to certificate this security role. Container details include:					
		Name	Description					
							ContainerId	Required. An integer containing the Keyfactor Command identifier for the certificate store container.
		Permission	<b>Required</b> . A string indicating the permission granted on the container for this role— <i>Read</i> , <i>Schedule</i> , or <i>Modify</i> .					
			Tip: Users with <i>Modify</i> permissions on a container inherit <i>Read</i> and <i>Schedule</i> ; users with <i>Schedule</i> permissions on a container inherit <i>Read</i> .					

Table 394: POST Security Roles {id} Permissions Containers Response Data

Name	Description			
	An object containing information about the certificate store container permissions granted to the security role. Details include:			
	Name	Description		
	ContainerId	An integer containing the container ID.		
	Name	A string containing the name of the certificate store container.		
	Permission	A string indicating the permission granted on the entity for this role.		

## 2.2.23.7 PUT Security Roles ID Permissions Containers

The PUT /Security/Roles/{id}/Permissions/Containers method is used to update container permissions to the security role that matches the ID. This method returns HTTP 200 OK on a success with certificate store container

permission details for the specified security role.



**Warning:** Any previously defined permissions of the given type (e.g. container) that are not submitted with their full existing data using this method will be cleared of their existing data. Existing data for other types will be retained. When using this method, you should first do a GET to retrieve all the permissions of the given type for the role you want to update, enter corrected data into the field(s) you want to update, and then submit all the fields using PUT, including the fields that contain values but which you are not changing. If you just wish to add permissions without modifying existing permissions, use the POST method.



**Note:** The API Endpoint utility displays a list of valid global permissions on the endpoint.



Table 395: PUT Security Roles {id} Permissions Containers Input Parameters

Name	In	Description							
id	Path	set certificate store Use the GET/Securit	actor Command reference ID of the security role for which to container permissions.  ty/Roles method (see GET Security Roles on page 898) to the security roles to determine the role's ID.						
containerPermissions	Body		g information about the permissions granted to certificate this security role. Container details include:						
		Name	Description						
		ContainerId	Required. An integer containing the Keyfactor Command identifier for the certificate store container.						
								Permission	<b>Required</b> . A string indicating the permission granted on the container for this role— <i>Read, Schedule</i> , or <i>Modify</i> .
				Tip: Users with <i>Modify</i> permissions on a container inherit <i>Read</i> and <i>Schedule</i> ; users with <i>Schedule</i> permissions on a container inherit <i>Read</i> .					

Table 396: PUT Security Roles {id} Permissions Containers Response Data

Name	Description		
	An object containing information about the certificate store container permissions granted to the security role. Details include:		
	Name	Description	
	ContainerId	An integer containing the container ID.	
	Name	A string containing the name of the certificate store container.	
	Permission	A string indicating the permission granted on the entity for this role.	

#### 2.2.23.8 GET Security Roles ID Permissions Collections

The GET /Security/Roles/{id}/Permissions/Collections method is used to return all certificate collection permissions associated with the security role that matches the ID. This method returns HTTP 200 OK on a success with certificate collection permission details for the specified security role.



Table 397: GET Security Roles {id} Permissions Collections Input Parameters

Name	In	Description
id	Path	<b>Required</b> . The Keyfactor Command reference ID of the security role for which to retrieve certificate collection permissions.
		Use the <i>GET /Security/Roles</i> method (see <u>GET Security Roles on page 898</u> ) to retrieve a list of all the security roles to determine the role's ID.

Table 398: GET Security Roles {id} Permissions Collections Response Data

Name	Description		
	An object containing information about the certificate collection permissions granted to the security role. Details include:		
	Name	Description	
	CollectionId	An integer containing the collection ID.	
	Name	A string containing the name of the certificate collection .	
	Permission	A string indicating the permission granted on the entity for this role.	

#### 2.2.23.9 POST Security Roles ID Permissions Collections

The POST/Security/Roles/{id}/Permissions/Collections method is used to add new collection permissions to the security role that matches the ID. This method returns HTTP 200 OK on a success with certificate collection permission details for the specified security role.



**Important:** Only the permission settings included in the command will be affected. Any other permissions settings will not be affected and remain as is.



**Note:** The API Endpoint utility displays a list of valid global permissions on the endpoint.



Table 399: POST Security Roles {id} Permissions Collections Input Parameters

Name	In	Description	
id	Path	set certificate collectuse the GET/Securit	ictor Command reference ID of the security role for which to tion permissions.  ty/Roles method (see GET Security Roles on page 898) to he security roles to determine the role's ID.
collectionPermissions	Body	,	g information about the permissions granted to certificate curity role. Collection details include:
		Name	Description
		CollectionId	Required. An integer containing the Keyfactor Command identifier for the certificate collection.
		Permission	<b>Required</b> . A string indicating the permission granted on the collection for this role— <i>Read</i> , <i>EditMetadata</i> , <i>Recover</i> , <i>Revoke</i> , or <i>Delete</i> .

Table 400: POST Security Roles {id} Permissions Collections Response Data

Name	Description		
	An object containing information about the certificate collection permissions granted to the security role. Details include:		
	Name	Description	
	CollectionId	An integer containing the collection ID.	
	Name	A string containing the name of the certificate collection .	
	Permission	A string indicating the permission granted on the entity for this role.	

## 2.2.23.10 PUT Security Roles ID Permissions Collections

The PUT /Security/Roles/{id}/Permissions/Collections method is used to update collection permissions to the security role that matches the ID. It replaces the deprecated endpoint: POST /CertificateCollections/{id}/Permissions. This method returns HTTP 200 OK on a success with certificate collection permission details for the specified security role.



Warning: Any previously defined permissions of the given type (e.g. collection) that are not submitted with their full existing data using this method will be cleared of their existing data. Existing data for other types will be retained. When using this method, you should first do a GET to retrieve all the permissions of the given type for the role you want to update, enter corrected data into the field(s) you want to update, and then submit all the fields using PUT, including the fields that contain values but which you are not changing. If you just wish to add permissions without modifying existing permissions, use the POST method.



Note: The API Endpoint utility displays a list of valid global permissions on the endpoint.



Table 401: PUT Security Roles {id} Permissions Collections Input Parameters

Name	In	Description	
id	Path	set certificate collectuse the GET/Security	ictor Command reference ID of the security role for which to tion permissions.  ty/Roles method (see GET Security Roles on page 898) to he security roles to determine the role's ID.
collectionPermissions	Body	,	g information about the permissions granted to certificate curity role. Collection details include:
		Name	Description
		CollectionId	Required. An integer containing the Keyfactor Command identifier for the certificate collection.
		Permission	<b>Required</b> . A string indicating the permission granted on the collection for this role— <i>Read</i> , <i>EditMetadata</i> , <i>Recover</i> , <i>Revoke</i> , or <i>Delete</i> .

Table 402: PUT Security Roles {id} Permissions Collections Response Data

Name	Description		
	An object containing information about the certificate collection permissions granted to the security role. Details include:		
	Name	Description	
	CollectionId	Required. An integer containing the collection ID.	
	Name	Required. A string containing the name of the certificate collection .	
	Permission	<b>Required</b> . A string indicating the permission granted on the entity for this role.	

# 2.2.24 Security Roles

The Security Roles component of the Keyfactor API includes methods necessary to list, add, update, and delete security roles. The permissions set with these methods are used to control access to all aspects of Keyfactor Command.

Table 403: Security Roles Endpoints

Endpoint	Method	Description	Link
/{id}	DELETE	Deletes the security role with the specified ID.	DELETE Security Roles ID below
/{id}	GET	Returns details for the security role with the specified ID, including permissions granted to the role and security identities assigned the role.	GET Security Roles ID on the next page
/{id}/Identities	GET	Returns the security identities assigned to the security role with the specified ID.	GET Security Roles ID Identities on page 897
/{id}/Identities	PUT	Updates the security identities assigned to the security role with the specified ID.	PUT Security Roles ID Identities on page 898
/	GET	Returns all security roles with filtering and output options.	GET Security Roles on page 898
/	POST	Adds a new security role.	POST Security Roles on page 901
/	PUT	Updates the security role with the specified ID.	PUT Security Roles on page 918
/{id}/Copy	POST	Adds a new security role by copying the existing security role with the specified ID.	POST Security Roles ID Copy on page 935

## 2.2.24.1 DELETE Security Roles ID

The DELETE /Security/Roles/{id} method is used to delete the security role with the specified ID. Use the *GET* /Security/Roles method (see <u>GET Security Roles on page 898</u>) to determine the ID of the security role you wish to delete. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see  $\underline{\text{Security Overview}}$ ) are required to use this feature: SecuritySettings: *Modify* 

Table 404: DELETE Security Roles {id} Input Parameters

Name	In	Description
id	Path	Required. The ID of the security role that should be deleted from Keyfactor Command.

# 2.2.24.2 GET Security Roles ID

The GET /Security/Roles/{id} method is used to return a security role by ID. This method returns HTTP 200 OK on a success with details for the specified security roles.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: SecuritySettings: *Read* 

Table 405: GET Security Roles {id} Input Parameters

Name	In	Description
id	Path	Required. The Keyfactor Command reference ID of the security role to retrieve.  Use the GET /Security/Roles method (see GET Security Roles on page 898) to retrieve a list of
		all the security roles to determine the role's ID.

Name	Description			
Id	An integer containing the Keyfactor Command identifier for the security role.			
Name	A string containing the short reference name for the security role.			
Descrip- tion	A string containing the description for the security role.			
Enabled	A Boolean that indicates whether the security role is enabled (true) or not (false). Security roles that have been disabled cannot be assigned to security identities. The default is <i>true</i> .  This is considered deprecated and may be removed in a future release.			
Immutable		es whether the security role has been marked as editable (true) or not (false). Internal ples are not editable. This setting is reserved for Keyfactor Command internal use.		
Valid	A Boolean that indicates whether the security role's audit XML is valid (true) or not (false). A security role may become invalid if Keyfactor Command determines that it appears to have been tampered with. This setting is not end-user configurable.			
Private	A Boolean that indicates whether the security role has been marked private (true) or not (false). The default is <i>false</i> .  This is considered deprecated and may be removed in a future release.			
Identities	An array containing information about the security identities assigned to the security role. Identity details include:			
	Name	Description		
	Id	An integer containing the Keyfactor Command identifier for the security identity.		
	AccountName	A string containing the account name for the security identity. For Active Directory users and groups, this will be in the form DOMAIN\\user or group name. For example:  KEYEXAMPLE\\PKI Administrators		
	IdentityType	A string indicating the type of identity—User or Group.		
	SID	A string containing the security identifier from the source identity store (e.g. Active Directory) for the security identity.		
Permis- sions	An object containing the permissions assigned to the role in a comma-separated list of Name:Value pairs. For example:			

Name	Description
	"Permissions": [     "AdminPortal:Read",     "Dashboard:Read" ],

## 2.2.24.3 GET Security Roles ID Identities

The GET /Security/Roles/{id}/Identities method is used to return the security identities assigned to a security role by security role ID. This method returns HTTP 200 OK on a success with details of the security identities assigned to the specified security role.



Table 407: GET Security Roles {id} Identities Input Parameters

Name	In	Description
id	Path	<b>Required</b> . The Keyfactor Command reference ID of the security role for which to retrieve security identities.
		Use the <i>GET /Security/Roles</i> method (see <u>GET Security Roles on the next page</u> ) to retrieve a list of all the security roles to determine the role's ID.

Table 408: GET Security Roles {id} Identities Response Data

Name	Description			
	An array containing information about the security identities assigned to the security role. Identity details include:			
	Name	Description		
	Id	An integer containing the Keyfactor Command identifier for the security identity.		
	Name	A string containing the account name for the security identity. For Active Directory users and groups, this will be in the form DOMAIN\\user or group name. For example: KEYEXAMPLE\\PKI Administrators		

## 2.2.24.4 PUT Security Roles ID Identities

The PUT /Security/Roles{id}/Identities method is used to update security identities assigned to a security role in Keyfactor Command. This method returns HTTP 200 OK on a success with the details of the security identities actively assigned to the security role.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: SecuritySettings: *Modify* 

Table 409: PUT Security Roles {id} Identities Input Parameters

Name	In	Description
id	Path	Required. The Keyfactor Command reference ID of the security role for which to update identities.  Use the GET/Security/Roles method (see GET Security Roles below) to retrieve a list of all the security roles to determine the role's ID.
identities	Body	An array in which you provide a <b>complete</b> list of the identities that are associated with an Security Role Id.  Use the GET/Security/Identities method (see GET Security Identities on page 820) to retrieve a list of all the security identities to determine the identity ID(s).

Table 410: PUT Security Roles {id} Identities Response Data

Name	Description			
	An array containing information about the security identities assigned to the security role. Identity details include:			
	Name	Description		
	Id	An integer containing the Keyfactor Command identifier for the security identity.		
	Name	A string containing the account name for the security identity. For Active Directory users and groups, this will be in the form DOMAIN\\user or group name. For example: KEYEXAMPLE\\PKI Administrators		

#### 2.2.24.5 GET Security Roles

The GET /Security/Roles method is used to return the list of security roles configured in Keyfactor Command. This method returns HTTP 200 OK on a success with the details of the security roles.



Table 411: GET Security Roles Input Parameters

Name	In	Description
validate	Query	A boolean that specifies whether the optional parameter of <i>validate</i> is <b>false</b> , which allows the AuditXML validation to be skipped when loading records, or <b>true</b> (or not specified) in which case validation will occur. The default is <b>true</b> .
queryString	Query	A string containing a query to limit the results (e.g. field1 -eq value1 AND field2 -gt value2). The default is to return all records. Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns for the same feature. For querying guidelines, refer to the Keyfactor Command Reference Guide: Using the Security Role Search Feature. The query fields supported for this endpoint are:  • Name
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>Name</i> .
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.

Table 412: GET Security Roles Response Data

Name	Description			
Id	An integer containing the Keyfactor Command identifier for the security role.			
Name	A string containing the	short reference name for the security role.		
Descrip- tion	A string containing the	description for the security role.		
Enabled	been disabled cannot l	es whether the security role is enabled (true) or not (false). Security roles that have be assigned to security identities. The default is <i>true</i> .  recated and may be removed in a future release.		
Immutable		es whether the security role has been marked as editable (true) or not (false). Internal ples are not editable. This setting is reserved for Keyfactor Command internal use.		
Valid	A Boolean that indicates whether the security role's audit XML is valid (true) or not (false). A security role may become invalid if Keyfactor Command determines that it appears to have been tampered with. This setting is not end-user configurable.			
Private	A Boolean that indicates whether the security role has been marked private (true) or not (false). The default is <i>false</i> .  This is considered deprecated and may be removed in a future release.			
Identities	An array containing information about the security identities assigned to the security role. Identity details include:			
	Name	Description		
	Id	An integer containing the Keyfactor Command identifier for the security identity.		
	AccountName  A string containing the account name for the security identity. For Active  Directory users and groups, this will be in the form DOMAIN\\user or group  name. For example:  KEYEXAMPLE\\PKI Administrators			
	IdentityType A string indicating the type of identity—User or Group.			
	SID	A string containing the security identifier from the source identity store (e.g. Active Directory) for the security identity.		
Permis- sions	An object containing the For example:	ne permissions assigned to the role in a comma-separated list of Name:Value pairs.		

Name	Description
	"Permissions": [     "AdminPortal:Read",     "Dashboard:Read" ],

## 2.2.24.6 POST Security Roles

The POST /Security/Roles method is used to create a new security role in Keyfactor Command. This method returns HTTP 200 OK on a success with the details of the security role.



Table 413: POST Security Roles Input Parameters

Name	In	Description			
Name	Body	Required. A string containing the short reference name for the security role.			
Description	Body	Required. A string containing the description for the security role.			
Enabled	Body	A Boolean that indicates whether the security role is enabled (true) or not (false). Security roles that have been disabled cannot be assigned to security identities. The default is <i>true</i> . This is considered deprecated and may be removed in a future release.			
Private	Body	A Boolean that indicates whether the security role has been marked private (true) or not (false). The default is <i>false</i> .  This is considered deprecated and may be removed in a future release.			
Permissions	Body	An object containing the permissio Name:Value pairs. Possible values		a comma-separated list of	
		Name	Value	Description	
	AdminPortal (a.k.a. Management Portal)  AgentAutoRegistration  AgentAutoRegistration  AgentManagement		Read	Users can access the Management Portal. This permission must be enabled for all roles that will access the Management Portal.	
			AgentAutoRegistration	Read	Users can view the agent auto-registration settings; Users must also have Read permissions for Agent Management.
		AgentAutoRegistration	Modify	Users can modify the agent auto-registration settings.	
		Read	Users can access the Management Portal areas and API endpoints to:  • View orchestrators, including filtering the orchestrator management grid		

Name	In	Description		
		Name	Value	Description
				<ul> <li>View orches- trator jobs, including status, schedules, fail- ures and warn- ings</li> </ul>
		AgentManagement	Modify	Users can access the Management Portal areas and API endpoints to:  • Manage orchestrators, including approving and disapproving them  • Unschedule and reschedule orchestrator jobs
		API	Read	Users can call the Classic (CMS) API endpoints.
		ApplicationSettings	Read	Users can view the application settings.
		ApplicationSettings	Modify	Users can modify the application settings.
		Auditing	Read	Users can access the Audit Log page in the Manage- ment Portal, and will be able to make API requests to obtain data from the audit log (query, etc.). The System Settings drop-down menu will display the Audit Log option to users with the Auditing Read permission.
		CertificateCollections	Modify	Users can add or edit certi-

Name	In	Description		
		Name	Value	Description
				ficate collections.  See Certificate Permissions in the Keyfactor Command Reference Guide for more information.
		CertificateEnrollment	EnrollPFX	Users can use the PFX Enrollment page in the Management Portal and use the PFX enrollment related API endpoints.
		CertificateEnrollment	EnrollCSR	Users can use the CSR Enrollment page in the Management Portal and use the CSR enrollment related API endpoints.
		CertificateEnrollment	CsrGeneration	Users can use the CSR Generation page in the Management Portal and use the CSR generation related API endpoints.
		CertificateEnrollment	PendingCsr	Users can use manage pending CSRs.
		CertificateMetadataTypes	Read	Users can read custom metadata attribute definitions on the Certificate Metadata page in the Management Portal and with related API endpoints.
		CertificateMetadataTypes	Modify	Users can add, edit, and delete custom metadata attribute definitions on the Certificate Metadata page in the Management Portal and with related API endpoints.
		CertificateStoreManagement	Read	Users can view certificate

Name	In	Description		
		Name	Value	Description
				stores—including the stores and containers but not discovery records—and certificate store types. Users who also have Read permissions for <i>Certificates</i> can view inventory for a certificate store.  See <i>Container Permissions</i> in the <i>Keyfactor Command Reference Guide</i> for more information.
		CertificateStoreManagement	Modify	Users can manage certificate stores—including the stores, containers, and discovery process—and certificate store types. Note that this permission does not control additions of certificates to certificate stores.
		CertificateStoreManagement	Schedule	Users can add certificates to certificate stores, renew/re-issue certificates, and remove certificates from certificate stores.
		Certificates	Read	Users can view certificates in certificate search and certificate collections in the Management Portal and with related API endpoints, including certificate history, and can download certificates. Users who also have Read permissions for Certificate Store Management or container permissions can add certificates to certificate stores.

Name	In	Description		
		Name	Value	Description
				See Certificate Permissions in the Keyfactor Command Reference Guide for more information.
		Certificates	Import	Users can import certificates through Add Certificate in the Management Portal and with related API endpoints. Users who also have Read permissions for <i>Certificate Store Management</i> or container permissions can add certificates to certificate stores from Add Certificate.
		Certificates	Recover	Users can download the certificates with their private key.
		Certificates	Revoke	Users can revoke certificates through Certificate Search and Certificate Collections in the Management Portal and with related API endpoints.
		Certificates	Delete	Users can delete certificates and, if applicable, the private keys of the certificates from the Keyfactor Command database.
		Certificates	ImportPrivateKey	Users can save the private key for the certificate in the Keyfactor Command database.
		Certificates	EditMetadata	Users can modify certificate metadata for certificates accessed through Certificate Search and Certificate Collec- tions in the Management

Name	In	Description		
		Name	Value	Description
				Portal and with related API endpoints.
		Dashboard	Read	Users can view the panels on their personalized dashboard and add and remove them.
		Dashboard	RiskHeader	Users can view the risk header at the top of the dashboard.
		EventHandlerRegistration	Read	Users can view the event handler registration settings.
		EventHandlerRegistration	Modify	Users can modify the event handler registration settings.
		MacAutoEnrollManagement	Read	Users can view the Mac Auto-Enroll Management settings.
		MacAutoEnrollManagement	Modify	Users can modify the Mac Auto-Enroll Management settings.
		Monitoring	Read	Users can view the expiration alerts in the Certificate Alerts in the Management Portal and with related API endpoints, including the alert schedule.
		Monitoring	Modify	Users can modify the expiration alerts, including the alert text, recipients and event handlers. Users can also add new alerts, delete alerts and configure the expiration alert delivery schedule.

Name	In	Description		
		Name	Value	Description
		Monitoring	Test	Users can test the expiration alerts, including sending email to recipients. Users must also have Read permissions for <i>Monitoring</i> .
	PkiManagement	Read	Users can view the Keyfactor Command PKI management settings within the following Management Portal areas and use related endpoints:	
		PkiManagement	Modify	Users can modify the Keyfactor Command PKI management settings:  Import, add, edit, and delete certificate authorities  Import certificate templates  Add, edit, delete, and test revocation monitoring endpoints  Configure revocation monitoring schedule  Configure revocation monitoring recipients
		PrivilegedAccessManagement	Read	Users can view PAM

Name	In	Description		
		Name	Value	Description
				providers.
		Privileged Access Management	Modify	Users can add, edit, and delete PAM providers.
		Reports	Read	Users can generate and view reports.
		Reports	Modify	Users can modify the delivery schedule for reports in Report Manager in the Management Portal and add, edit, and delete custom reports.  Note: Report scheduling is limited by collection permissions. Users in roles that have Reports: Read and Modify permissions will also need to have Read collection permissions on individual collections to have the ability to add, edit and delete schedules associated with collections. The user will not have access to add, edit and delete schedules for any collections for which they do not have collection Read permissions in addition to Reports permissions.

Name	In	Description		
		Name	Value	Description
		SecuritySettings	Read	Users can view the settings for Security Roles and Security Identities. Users must also have the Read permission for <i>System Settings</i> .
		SecuritySettings	Modify	Users can modify the settings for Security Roles and Security Identities in the Management Portal and with related API endpoints.
		SSH	User	Users can generate their own SSH keys.
		SSH	ServerAdmin	Users can use all SSH functions, except creating server groups and assigning server group owners. Users have limited access to some functions based on server group ownership.  See SSH Permissions in the Keyfactor Command Reference Guide for more information.
		SSH	EnterpriseAdmin	Users can use all SSH functions.  See SSH Permissions in the Keyfactor Command Reference Guide for more information.
		SslManagement	Read	Users can view the SSL Network Discovery and Monitoring area in the Management Portal and with related API endpoints, including defined networks

Name	In	Description		
		Name	Value	Description
				and the network ranges configured for them, agent pools, and scan results. Users can use the query tool on the Results tab to find discovered endpoints and then view the discovered endpoints, including the details for the endpoints.
		SslManagement	Modify	Users can modify the SSL Network Discovery and Monitoring settings:
		SystemSettings	Read	Users can view the System Settings for:  • Application Settings • Event Handler Registration to view built-in or custom event handlers

Name	In	Description	Description		
		Name	Value	Description	
				<ul> <li>API Applications allowed to use the APIs for certificate lifecycle management</li> <li>SMTP Configuration for email delivery of reports and alerts</li> <li>Installed components</li> <li>Licensing</li> <li>Alerts and Warnings about the health of the Keyfactor Command system</li> </ul>	
		SystemSettings	Modify	Users can modify the System Settings for:  • Application Settings to configure many options for Keyfactor Command • Event Handler Registration to add or remove built-in or custom event handlers • Update SMTP Configuration for email delivery of reports and alerts	

Name	In	Description		
		Name	Value	Description
				<ul> <li>Installed components, including removing servers from use</li> <li>Licensing, including the option to replace the existing license file</li> </ul>
		WorkflowDefinitions	Read	Users can view the configured workflow definitions.
		WorkflowDefinitions	Modify	Users can modify both the built-in and any custom workflow definitions, including the name and description and the configuration for the steps. Users can also add new workflow definitions, delete workflow definitions, publish workflow definitions, and import and export workflow definitions.
		WorkflowInstances	Manage	Users can manage initiated workflow instances, including stopping, restarting, and deleting them.
		WorkflowInstances	ReadAssignedToMe	Users can view the workflow instances that have been initiated and are awaiting input from them.  Tip: There is not a

Name	In	Description		
		Name	Value	Description
				security permission at this level that controls whether users can provide input (a signal) to a workflow instance. This is controlled using the security roles configured on the specific workflow definition. Any user who holds one of the roles configured in the workflow step that requires a signal may provide the necessary input. The user does not need to hold the ReadAssignedToMe WorkflowInstances permission in order to provide the input.
		WorkflowInstances	ReadAll	Users can view all the work- flow instances that have been initiated.
	WorkflowInstances	ReadMy	Users can view the workflow instances that have been initiated by them (e.g. because they enrolled for a certificate).	
		WorkflowManagement (a.k.a. Alerts)	Read	Users can view the pending, issued, and denied workflow alerts.

Name	In	Description			
		Name	Value	Description	
		WorkflowManagement (a.k.a. Alerts)	Modify	Users can modify the pending, issued, and denied workflow alerts, including the alert text, recipients, and event handlers. Users can also add new alerts, delete alerts, and configure the pending alert delivery schedule.	
		WorkflowManagement (a.k.a. Alerts)	Test	Users can test the pending alerts, including sending email to recipients. Users must also have Read permissions for <i>Workflow</i> .	
		WorkflowManagement (a.k.a. Certificate Requests)	Participate	Users can participate in the pending, issued and denied workflow process by approving or denying certificate requests from the Certificate Requests page or from the individual pages reached from links included in alerts in the Management Portal and with related API endpoints.	
		For example:			
	"Permissions": [     "AdminPortal:Read",     "Dashboard:Read" ],				
Identities	Body	An array containing one or more identifiers for each security identity to associate with the role. Supported identifiers include:			

Name	In	Description			
		Name	Description		
		AccountName	Required*. A string containing the account name for the security identity. For Active Directory user and groups, this will be in the form DOMAIN\\user or group name. For example:  KEYEXAMPLE\\PKI Administrators  * One of AccountName or SID is required in order to specify an identity, but not both.		
		SID	Required*. A string containing the security identifier from the source identity store (e.g. Active Directory) for the security identity.  * One of AccountName or SID is required in order to specify an identity, but not both.		
		For example:			
		}, {	EYEXAMPLE\\jsmith"  EYEXAMPLE\\mjones"		

Table 414: POST Security Roles Response Data

Name	Description			
Id	An integer containing the Keyfactor Command identifier for the security role.			
Name	A string containing the	short reference name for the security role.		
Descrip- tion	A string containing the	description for the security role.		
Enabled	been disabled cannot l	es whether the security role is enabled (true) or not (false). Security roles that have be assigned to security identities. The default is <i>true</i> . recated and may be removed in a future release.		
Immutable		es whether the security role has been marked as editable (true) or not (false). Internal ples are not editable. This setting is reserved for Keyfactor Command internal use.		
Valid	A Boolean that indicates whether the security role's audit XML is valid (true) or not (false). A security role may become invalid if Keyfactor Command determines that it appears to have been tampered with. This setting is not end-user configurable.			
Private	A Boolean that indicates whether the security role has been marked private (true) or not (false). The default is <i>false</i> .  This is considered deprecated and may be removed in a future release.			
Identities	An array containing information about the security identities assigned to the security role. Identity details include:			
	Name	Description		
	Id	An integer containing the Keyfactor Command identifier for the security identity.		
	AccountName  A string containing the account name for the security identity. For Active  Directory users and groups, this will be in the form DOMAIN\\user or group  name. For example:  KEYEXAMPLE\\PKI Administrators			
	IdentityType A string indicating the type of identity—User or Group.			
	SID	A string containing the security identifier from the source identity store (e.g. Active Directory) for the security identity.		
Permis- sions	An object containing the For example:	he permissions assigned to the role in a comma-separated list of Name:Value pairs.		

Name	Description
	"Permissions": [     "AdminPortal:Read",     "Dashboard:Read" ],

#### 2.2.24.7 PUT Security Roles

The PUT /Security/Roles method is used to update a security role in Keyfactor Command including the permissions set for the role and the security identities mapped to the role. This method returns HTTP 200 OK on a success with the details of the security role.



**Tip:** The following permissions (see Security Overview) are required to use this feature: SecuritySettings: Modify



Warning: Any previously populated fields that are not submitted with their full existing data using this method will be cleared of their existing data. When using this method, you should first do a GET to retrieve all the values for the record you want to update, enter corrected data into the field(s) you want to update, and then submit all the fields using PUT, including the fields that contain values but which you are not changing.

Table 415: PUT Security Roles Input Parameters

Name	In	Description					
ld	Body	the GET /Security/Roles method (se	<b>Required</b> . An integer containing the Keyfactor Command identifier for the security role. Use the <i>GET /Security/Roles</i> method (see <u>GET Security Roles on page 898</u> ) to retrieve a list of all the security roles to determine the role's ID.				
Name	Body	Required. A string containing the s	hort reference name for the	he security role.			
Description	Body	Required. A string containing the d	lescription for the security	role.			
Enabled	Body	A Boolean that indicates whether to roles that have been disabled cannot be a considered deprecated and	ot be assigned to security	identities. The default is <i>true</i> .			
Private	Body	A Boolean that indicates whether the security role has been marked private (true) or not (false). The default is <i>false</i> .  This is considered deprecated and may be removed in a future release.					
Permissions	Body	An object containing the permissions assigned to the role in a comma-separated list of Name:Value pairs. Possible values are:					
		Name	Value	Description			
					AdminPortal (a.k.a. Management Portal)	Read	Users can access the Management Portal. This permission must be enabled for all roles that will access the Management Portal.
				AgentAutoRegistration	Read	Users can view the agent auto-registration settings; Users must also have Read permissions for Agent Management.	
		AgentAutoRegistration	Modify	Users can modify the agent auto-registration settings.			
		AgentManagement	Read	Users can access the Management Portal areas and API endpoints to:  • View orchestrators, including			

Name	In	Description			
		Name	Value	Description	
				filtering the orchestrator management grid  • View orchestrator jobs, including status, schedules, failures and warnings	
		AgentManagement	Modify	Users can access the Management Portal areas and API endpoints to:  • Manage orchestrators, including approving and disapproving them  • Unschedule and reschedule orchestrator jobs	
		API	Read	Users can call the Classic (CMS) API endpoints.	
		ApplicationSettings	Read	Users can view the application settings.	
		ApplicationSettings	Modify	Users can modify the application settings.	
		Auditing	Read	Users can access the Audit Log page in the Manage- ment Portal, and will be able to make API requests to obtain data from the audit log (query, etc.). The System Settings drop-down menu	

Name	In	Description			
		Name	Value	Description	
				will display the Audit Log option to users with the <i>Auditing</i> Read permission.	
		CertificateCollections	Modify	Users can add or edit certificate collections.  See Certificate Permissions in the Keyfactor Command Reference Guide for more information.	
		CertificateEnrollment	EnrollPFX	Users can use the PFX Enrollment page in the Management Portal and use the PFX enrollment related API endpoints.	
		CertificateEnrollment	EnrollCSR	Users can use the CSR Enrollment page in the Management Portal and use the CSR enrollment related API endpoints.	
		CertificateEnrollment	CsrGeneration	Users can use the CSR Generation page in the Management Portal and use the CSR generation related API endpoints.	
		CertificateEnrollment	PendingCsr	Users can use manage pending CSRs.	
		CertificateMetadataTypes	Read	Users can read custom metadata attribute definitions on the Certificate Metadata page in the Management Portal and with related API endpoints.	
		CertificateMetadataTypes	Modify	Users can add, edit, and delete custom metadata attribute definitions on the	

Name	In	Description			
		Name	Value	Description	
				Certificate Metadata page in the Management Portal and with related API endpoints.	
		CertificateStoreManagement	Read	Users can view certificate stores—including the stores and containers but not discovery records—and certificate store types. Users who also have Read permissions for <i>Certificates</i> can view inventory for a certificate store.  See <i>Container Permissions</i> in the <i>Keyfactor Command Reference Guide</i> for more information.	
		CertificateStoreManagement	Modify	Users can manage certificate stores—including the stores, containers, and discovery process—and certificate store types. Note that this permission does not control additions of certificates to certificate stores.	
		CertificateStoreManagement	Schedule	Users can add certificates to certificate stores, renew/re-issue certificates, and remove certificates from certificate stores.	
	Certificates	Read	Users can view certificates in certificate search and certificate collections in the Management Portal and with related API endpoints, including certificate history, and can download certificates. Users who also have		

Name	In	Description			
		Name	Value	Description	
				Read permissions for <i>Certificate Store Management</i> or container permissions can add certificates to certificate stores.  See <i>Certificate Permissions</i> in the <i>Keyfactor Command Reference Guide</i> for more information.	
		Certificates	Import	Users can import certificates through Add Certificate in the Management Portal and with related API endpoints. Users who also have Read permissions for <i>Certificate Store Management</i> or container permissions can add certificates to certificate stores from Add Certificate.	
		Certificates	Recover	Users can download the certificates with their private key.	
		Certificates	Revoke	Users can revoke certificates through Certificate Search and Certificate Collections in the Management Portal and with related API endpoints.	
		Certificates	Delete	Users can delete certificates and, if applicable, the private keys of the certificates from the Keyfactor Command database.	
		Certificates	ImportPrivateKey	Users can save the private key for the certificate in the Keyfactor Command database.	

Name	In	Description				
		Name	Value	Description		
		Certificates	EditMetadata	Users can modify certificate metadata for certificates accessed through Certificate Search and Certificate Collections in the Management Portal and with related API endpoints.		
		Dashboard	Read	Users can view the panels on their personalized dash- board and add and remove them.		
		Dashboard	RiskHeader	Users can view the risk header at the top of the dashboard.		
		EventHandlerRegistration	Read	Users can view the event handler registration settings.		
		EventHandlerRegistration	Modify	Users can modify the event handler registration settings.		
			MacAutoEnrollManagement	Read	Users can view the Mac Auto-Enroll Management settings.	
		MacAutoEnrollManagement	Modify	Users can modify the Mac Auto-Enroll Management settings.		
		Monitoring	Read	Users can view the expiration alerts in the Certificate Alerts in the Management Portal and with related API endpoints, including the alert schedule.		
		Monitoring	Modify	Users can modify the expiration alerts, including the alert text, recipients and event handlers. Users can		

Name	In	Description		
		Name	Value	Description
				also add new alerts, delete alerts and configure the expiration alert delivery schedule.
		Monitoring	Test	Users can test the expiration alerts, including sending email to recipients. Users must also have Read permissions for <i>Monitoring</i> .
		PkiManagement	Read	Users can view the Keyfactor Command PKI management settings within the following Management Portal areas and use related endpoints:
		PkiManagement	Modify	Users can modify the Keyfactor Command PKI management settings:  Import, add, edit, and delete certificate authorities  Import certi- ficate templates  Add, edit, delete, and test revocation monitoring endpoints  Configure revocation monitoring schedule

	Value	Description
		Description
		Configure revocation monitoring recipients
AccessManagement	Read	Users can view PAM providers.
AccessManagement	Modify	Users can add, edit, and delete PAM providers.
	Read	Users can generate and view reports.
	Modify	Users can modify the delivery schedule for reports in Report Manager in the Management Portal and add, edit, and delete custom reports.  Note: Report scheduling is limited by collection permissions. Users in roles that have Reports: Read and Modify permissions will also need to have Read collection permissions on individual collections to have the ability to add, edit and delete schedules associated with collections. The user will not have access to add, edit and delete schedules for any collections for
	AccessManagement	AccessManagement Modify  Read

Name	In	Description			
		Name	Value	Description	
				have collection  Read permissions in addition to Reports permissions.	
		SecuritySettings	Read	Users can view the settings for Security Roles and Security Identities. Users must also have the Read permission for <i>System Settings</i> .	
		SecuritySettings	Modify	Users can modify the settings for Security Roles and Security Identities in the Management Portal and with related API endpoints.	
		SSH	User	Users can generate their own SSH keys.	
		SSH	ServerAdmin	Users can use all SSH functions, except creating server groups and assigning server group owners. Users have limited access to some functions based on server group ownership.  See SSH Permissions in the Keyfactor Command Reference Guide for more information.	
		SSH	EnterpriseAdmin	Users can use all SSH functions.  See SSH Permissions in the Keyfactor Command Reference Guide for more information.	

Name	In	Description			
		Name	Value	Description	
		SslManagement	Read	Users can view the SSL Network Discovery and Monitoring area in the Management Portal and with related API endpoints, including defined networks and the network ranges configured for them, agent pools, and scan results. Users can use the query tool on the Results tab to find discovered endpoints and then view the discovered endpoints, including the details for the endpoints.	
		SslManagement	Modify	Users can modify the SSL Network Discovery and Monitoring settings:	
		SystemSettings	Read	Users can view the System Settings for:  • Application Settings	

Name	In	Description		
		Name	Value	Description
				Event Handler     Registration to     view built-in or     custom event     handlers      API Applications     allowed to use     the APIs for certificate lifecycle     management      SMTP Configuration for email     delivery of     reports and     alerts      Installed     components      Licensing      Alerts and Warnings about the     health of the     Keyfactor     Command     system
		SystemSettings	Modify	Users can modify the System Settings for:  • Application Settings to configure many options for Keyfactor Command • Event Handler Registration to add or remove built-in or custom event handlers • Update SMTP

Name	In	Description			
		Name	Value	Description	
				Configuration for email delivery of reports and alerts Installed components, including removing servers from use Licensing, including the option to replace the existing license file	
		WorkflowDefinitions	Read	Users can view the configured workflow definitions.	
		WorkflowDefinitions	Modify	Users can modify both the built-in and any custom workflow definitions, including the name and description and the configuration for the steps. Users can also add new workflow definitions, delete workflow definitions, publish workflow definitions, and import and export workflow definitions.	
		WorkflowInstances	Manage	Users can manage initiated workflow instances, including stopping, restarting, and deleting them.	
		WorkflowInstances	ReadAssignedToMe	Users can view the workflow instances that have been	

Name	In	Description			
		Name	Value	Description	
				initiated and are awaiting input from them.	
				Tip: There is not a security permission at this level that controls whether users can provide input (a signal) to a workflow instance. This is controlled using the security roles configured on the specific workflow definition. Any user who holds one of the roles configured in the workflow step that requires a signal may provide the necessary input. The user does not need to hold the ReadAssignedToMe WorkflowInstances permission in order to provide the input.	
		WorkflowInstances	ReadAll	Users can view all the work- flow instances that have been initiated.	
		WorkflowInstances	ReadMy	Users can view the workflow instances that have been initiated by them (e.g. because they enrolled for a certificate).	
		WorkflowManagement	Read	Users can view the pending,	

Name	In	Description				
		Name	Value	Description		
		(a.k.a. Alerts)		issued, and denied workflow alerts.		
		WorkflowManagement (a.k.a. Alerts)	Modify	Users can modify the pending, issued, and denied workflow alerts, including the alert text, recipients, and event handlers. Users can also add new alerts, delete alerts, and configure the pending alert delivery schedule.		
		WorkflowManagement (a.k.a. Alerts)	Test	Users can test the pending alerts, including sending email to recipients. Users must also have Read permissions for <i>Workflow</i> .		
		WorkflowManagement (a.k.a. Certificate Requests)	Participate	Users can participate in the pending, issued and denied workflow process by approving or denying certificate requests from the Certificate Requests page or from the individual pages reached from links included in alerts in the Management Portal and with related API endpoints.		
		For example:				
		"Permissions": [     "AdminPortal:Read",     "Dashboard:Read" ],				
Identities	Body	An array containing one or more id role. Supported identifiers include		identity to associate with the		

Name	In	Description	
		Name	Description
		AccountName	Required*. A string containing the account name for the security identity. For Active Directory user and groups, this will be in the form DOMAIN\\user or group name. For example:  KEYEXAMPLE\\PKI Administrators  * One of AccountName or SID is required in order to specify an identity, but not both.
		SID	Required*. A string containing the security identifier from the source identity store (e.g. Active Directory) for the security identity.  * One of AccountName or SID is required in order to specify an identity, but not both.
		For example:	
		}, {	EYEXAMPLE\\jsmith"  EYEXAMPLE\\mjones"

Table 416: PUT Security Roles Response Data

Name	Description				
Id	An integer containing the Keyfactor Command identifier for the security role.				
Name	A string containing the	A string containing the short reference name for the security role.			
Descrip- tion	A string containing the	description for the security role.			
Enabled	been disabled cannot b	es whether the security role is enabled (true) or not (false). Security roles that have be assigned to security identities. The default is <i>true</i> . recated and may be removed in a future release.			
Immutable		es whether the security role has been marked as editable (true) or not (false). Internal ples are not editable. This setting is reserved for Keyfactor Command internal use.			
Valid	A Boolean that indicates whether the security role's audit XML is valid (true) or not (false). A security role may become invalid if Keyfactor Command determines that it appears to have been tampered with. This setting is not end-user configurable.				
Private	is false.	es whether the security role has been marked private (true) or not (false). The default recated and may be removed in a future release.			
Identities	An array containing information about the security identities assigned to the security role. Identity details include:				
	Name	Description			
	Id	An integer containing the Keyfactor Command identifier for the security identity.			
	AccountName	A string containing the account name for the security identity. For Active Directory users and groups, this will be in the form DOMAIN\\user or group name. For example:  KEYEXAMPLE\\PKI Administrators			
	IdentityType	A string indicating the type of identity—User or Group.			
	SID A string containing the security identifier from the source identity store (e.g. Active Directory) for the security identity.				
Permis- sions	An object containing the For example:	he permissions assigned to the role in a comma-separated list of Name:Value pairs.			

Name	Description
	"Permissions": [     "AdminPortal:Read",     "Dashboard:Read" ],

# 2.2.24.8 POST Security Roles ID Copy

The POST /Security/Roles{id}/Copy method is used to copy an existing security role in Keyfactor Command to create a new security role. This method returns HTTP 200 OK on a success with the details of the new security role.



**Tip:** The following permissions (see  $\underline{\text{Security Overview}}$ ) are required to use this feature: SecuritySettings: *Modify* 

Table 417: POST Security Roles {id} Copy Input Parameters

Name	In	Description				
id	Path	Required. The Keyfactor Command reference ID of the security role from which to copy role information.  Use the GET /Security/Roles method (see GET Security Roles on page 898) to retrieve a list of all the security roles to determine the role's ID.				
role	Body	An array containing information about the new security role to create. Role details include:				
		Name Description				
		Name	<b>Required</b> . A string containing the short reference name for the security role.			
		Description	Required. A string containing the description for the security role.			

Table 418: POST Security Roles {id} Copy Response Data

Name	Description				
Id	An integer containing the Keyfactor Command identifier for the security role.				
Name	A string containing the short reference name for the security role.				
Descrip- tion	A string containing the	description for the security role.			
Enabled	been disabled cannot l	es whether the security role is enabled (true) or not (false). Security roles that have be assigned to security identities. The default is <i>true</i> . recated and may be removed in a future release.			
Immutable		es whether the security role has been marked as editable (true) or not (false). Internal ples are not editable. This setting is reserved for Keyfactor Command internal use.			
Valid	A Boolean that indicates whether the security role's audit XML is valid (true) or not (false). A security role may become invalid if Keyfactor Command determines that it appears to have been tampered with. This setting is not end-user configurable.				
Private	is false.	es whether the security role has been marked private (true) or not (false). The default recated and may be removed in a future release.			
Identities	An array containing information about the security identities assigned to the security role. Identity details include:				
	Name	Description			
	Id	An integer containing the Keyfactor Command identifier for the security identity.			
	AccountName  A string containing the account name for the security identity. For Active Directory users and groups, this will be in the form DOMAIN\\user or grouname. For example:  KEYEXAMPLE\\PKI Administrators				
	IdentityType	A string indicating the type of identity—User or Group.			
	SID	A string containing the security identifier from the source identity store (e.g. Active Directory) for the security identity.			
Permis- sions	An object containing the For example:	he permissions assigned to the role in a comma-separated list of Name:Value pairs.			

```
Name

Description

"Permissions": [
    "AdminPortal:Read",
    "Dashboard:Read"
],
```

### 2.2.25 SSH

The SSH component of the Keyfactor Web APIs includes methods necessary to create, update, and delete SSH keys, logons, servers, server groups, and service accounts within Keyfactor Command.

Table 419: SSH Endpoints

Endpoint	Method	Description	Link
/Keys/Unmanaged/{id}	DELETE	Delete a discovered unmanaged SSH key for the specified ID.	DELETE SSH Keys Unmanaged ID on page 941
/Keys/Unmanaged/{id}	GET	Retrieve details for a discovered unmanaged SSH key for the specified ID.	GET SSH Keys Unmanaged ID on page 942
/Keys/MyKey	GET	Retrieve details for a user's SSH key generated through Keyfactor Command.	GET SSH Keys My Key on page 943
/Keys/MyKey	POST	Generate a new SSH key pair for a user through Keyfactor Command.	POST SSH Keys My Key on page 945
/Keys/MyKey	PUT	Update an SSH key for a user through Keyfactor Command.	PUT SSH Keys My Key on page 949
/Keys/Unmanaged	DELETE	Delete one or more discovered unmanaged SSH keys based on a selection query.	DELETE SSH Keys Unmanaged on page 951
/Keys/Unmanaged	GET	Retrieve details for one or more discovered unmanaged SSH keys based on a selection query.	GET SSH Keys Unmanaged on page 952
/Logons/{id}	DELETE	Deletes a Linux logon from Keyfactor Command.	DELETE SSH Logons ID on page 955
/Logons/{id}	GET	Returns information about a Linux logons.	GET SSH Logons

Endpoint	Method	Description	Link
			ID on page 955
/Logons/	GET	Returns information about one or more Linux logons.	GET SSH Logons on page 957
/Logons/	POST	Creates a new Linux logon in Keyfactor Command and, for servers in <i>inventory and</i> <i>publish policy</i> mode, publishes it out to a Linux server.	POST SSH Logons on page 959
/Logons/Access	POST	Maps users and service accounts with a Linux logon to associate the SSH keys of the users with the Linux logon.	POST SSH Logons Access on page 961
/Servers/{id}	DELETE	Deletes the SSH server with the specified ID.	DELETE SSH Servers ID on page 963
/Servers/{id}	GET	Returns the SSH server with the specified ID.	GET SSH Servers ID on page 964
/Servers/Access/{id}	GET	Retrieves Linux logons along with users and service accounts granted access to those logons for the specified SSH server.	GET SSH Servers Access ID on page 968
/Servers/	GET	Returns a list of a SSH servers configured in Keyfactor Command.	GET SSH Servers on page 969
/Servers/	POST	Creates a new SSH server.	POST SSH Servers on page 974
/Servers/	PUT	Updates an existing SSH server.	PUT SSH Servers on page 979
/Servers/Access	DELETE	Deletes Linux logon to user and service account mappings for an SSH server.	DELETE SSH Servers Access on page 984
/Servers/Access	POST	Creates Linux logon to user and service account mappings for an SSH server.	POST SSH Servers Access on page 986
/ServerGroups/{id}	DELETE	Deletes the SSH server group with the specified ID.	DELETE SSH Server Groups ID on page 989

Endpoint	Method	Description	Link
/ServerGroups/{id}	GET	Returns the SSH server group with the specified ID.	GET SSH Server Groups ID on page 990
/ServerGroups/{name}	GET	Returns the SSH server group with the specified name.	GET SSH Server Groups Name on page 993
/ServerGroups/Access/{id}	GET	Retrieves Linux logons along with users and service accounts granted access to those logons for the specified SSH server group.	GET SSH Server Groups Access ID on page 998
/ServerGroups/	GET	Returns a list of a SSH server groups configured in Keyfactor Command.	GET SSH Server Groups on page 999
/ServerGroups/	POST	Creates a new SSH server group.	POST SSH Server Groups on page 1003
/ServerGroups/	PUT	Updates an existing SSH server group.	PUT SSH Server Groups on page 1010
/ServerGroups/Access	DELETE	Deletes Linux logon to user and service account mappings for an SSH server group.	DELETE SSH Server Groups Access on page 1018
/ServerGroups/Access	POST	Creates Linux logon to user and service account mappings for an SSH server group.	POST SSH Server Groups Access on page 1019
/ServiceAccounts/{id}	DELETE	Deletes the SSH service account with the specified ID.	DELETE SSH Service Accounts ID on page 1022
/ServiceAccounts/{id}	GET	Returns the SSH service account with the specified ID.	GET SSH Service Accounts ID on page 1024
/ServiceAccounts/Key/{id}	GET	Returns the public key and optional private key of an SSH service account with the specified ID.	GET SSH Service Accounts Key ID on page 1030
/ServiceAccounts/	DELETE	Deletes one or more SSH service accounts with	DELETE SSH

Endpoint	Method	Description	Link
		the specified IDs.	Service Accounts on page 1033
/ServiceAccounts/	GET	Returns a list of SSH service accounts based on the specified filters.	GET SSH Service Accounts on page 1036
/ServiceAccounts/	POST	Creates a new SSH service account.	POST SSH Service Accounts on page 1043
/ServiceAccounts/	PUT	Updates an existing SSH service account.	PUT SSH Service Accounts on page 1052
/ServiceAccounts/Rotate/{id}	POST	Generates a new key pair for an existing service account.	POST SSH Service Accounts Rotate ID on page 1059
/Users/{id}	DELETE	Deletes the SSH user with the specified ID.	DELETE SSH Users ID on page 1063
/Users/{id}	GET	Returns the SSH user with the specified ID.	GET SSH Users ID on page 1063
/Users/	GET	Returns a list of SSH users based on the specified filters.	GET SSH Users on page 1068
/Users/	POST	Creates a new SSH user.	POST SSH Users on page 1076
/Users/	PUT	Updates an existing SSH user.	PUT SSH Users on page 1077
/Users/Access	POST	Creates a mapping from the SSH user to one or more Linux logons.	POST SSH Users Access on page 1078

# 2.2.25.1 SSH Keys

The SSH Keys component of the Keyfactor Web APIs includes methods necessary to allow a user with the SSH User Keyfactor Command role permission (see the <u>SSH Permissions</u> section of the Keyfactor Command Reference Guide) to generate an SSH key pair for himself or herself, retrieve that key, update it, or delete it. Methods are also included to list and delete unmanaged keys—keys discovered on servers configured in inventory only mode.

Table 420: SSH Keys Endpoints

Endpoint	Method	Description	Link
/Unmanaged/{id}	DELETE	Delete a discovered unmanaged SSH key for the specified ID.	DELETE SSH Keys Unmanaged ID below
/Unmanaged/{id}	GET	Retrieve details for a discovered unmanaged SSH key for the specified ID.	GET SSH Keys Unmanaged ID on the next page
/МуКеу	GET	Retrieve details for a user's SSH key generated through Keyfactor Command.	GET SSH Keys My Key on page 943
/МуКеу	POST	Generate a new SSH key pair for a user through Keyfactor Command.	POST SSH Keys My Key on page 945
/МуКеу	PUT	Update an SSH key for a user through Keyfactor Command.	PUT SSH Keys My Key on page 949
Unmanaged	DELETE	Delete one or more discovered unmanaged SSH keys based on a selection query.	DELETE SSH Keys Unmanaged on page 951
Unmanaged	GET	Retrieve details for one or more discovered unmanaged SSH keys based on a selection query.	GET SSH Keys Unmanaged on page 952

### **DELETE SSH Keys Unmanaged ID**

The DELETE /SSH/Keys/Unmanaged/{id} method is used to delete an unmanaged SSH key by ID. Keys discovered on SSH servers during inventory and discovery are considered unmanaged. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see Security Overview) are required to use this feature:

SSH: ServerAdmin OR SSH: EnterpriseAdmin

SSH actions are affected by ownership on the server group with which the key is associated and limited for users with only the *ServerAdmin* role. For more information, see *SSH Permissions* in the *Keyfactor Command Reference Guide*.



**Note:** Deleting an unmanaged key when the associated server is still in inventory only mode will not delete the key on the target server. The next time the server is scanned, the key will re-appear in Keyfactor Command. See the <a href="Unmanaged SSH Keys">Unmanaged SSH Keys</a> section of the <a href="Keyfactor Command Reference Guide">Keyfactor Command Reference Guide</a> for more information.

Table 421: DELETE SSH Keys Unmanaged {id} Input Parameters

Name	In	Description
id	Path	<b>Required</b> . The Keyfactor Command reference ID for the unmanaged SSH key to be deleted. Use the <i>GET /SSH/Keys/Unmanaged</i> method (see <u>GET SSH Keys Unmanaged on page 952</u> ) to retrieve a list of all the unmanaged keys to determine the unmanaged key's ID.

### **GET SSH Keys Unmanaged ID**

The GET /SSH/Keys/Unmanaged/{id} method is used to retrieve an unmanaged SSH key by ID. Keys discovered on SSH servers during inventory and discovery are considered unmanaged. This method returns HTTP 200 OK on a success with details for the requested SSH key.



**Tip:** The following permissions (see Security Overview) are required to use this feature:

SSH: ServerAdmin OR SSH: EnterpriseAdmin

SSH actions are affected by ownership on the server group with which the key is associated and limited for users with only the *ServerAdmin* role. For more information, see *SSH Permissions* in the *Keyfactor Command Reference Guide*.

Table 422: GET SSH Keys Unmanaged {id} Input Parameters

Name	In	Description
id	Path	<b>Required</b> . The Keyfactor Command reference ID for the unmanaged SSH key to be retrieved. Use the <i>GET/SSH/Keys/Unmanaged</i> method (see <u>GET SSH Keys Unmanaged on page 952</u> ) to retrieve a list of all the unmanaged keys to determine the unmanaged key's ID.

Table 423: GET SSH Keys Unmanaged {id} Response Data

Name	Description
ID	An integer indicating the Keyfactor Command reference ID for the SSH key.
Fingerprint	A string indicating the fingerprint of the public key. Each SSH public key has a single cryptographic fingerprint that can be used to uniquely identify the key.
PublicKey	A string indicating the public key of the key pair.
КеуТуре	A string indicating the cryptographic algorithm used to generate the SSH key. Possible values are:  RSA  ECDSA  Ed25519
KeyLength	An integer indicating the key length for the SSH key. The key length supported depends on the key type selected. Keyfactor Command supports 256 bits for Ed25519 and ECDSA and 2048 or 4096 bits for RSA.
DiscoveredDate	The date, in UTC, on which the SSH key was discovered.
Comments	An array containing one or more strings with the user-defined descriptive comments, if any, on the key. Although entry of an email address in the comment field of an SSH key is traditional, this is not a required format. The comment may can contain any characters supported for string fields, including spaces and most punctuation marks. A key may appear with more than one comment if the originating authorized_keys file contained more than one comment.
LogonCount	An integer indicating the number of Linux logons associated with the SSH key.

# **GET SSH Keys My Key**

The GET /SSH/Keys/MyKey method is used to retrieve the current user's SSH key generated in Keyfactor Command (see <u>POST SSH Keys My Key on page 945</u>). This method returns HTTP 200 OK on a success with the key's details.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature:

SSH: *User* OR

SSH: ServerAdmin OR SSH: EnterpriseAdmin

Table 424: GET SSH Keys My Key Input Parameters

Name	In	Description
includePrivateKey	Query	A Boolean that sets whether to include the private key of the SSH key pair in the response (true) or not (false). If set to <i>true</i> , the <i>x-keyfactor-key-passphrase</i> header must be supplied. The default is <i>false</i> .
x-keyfactor-key-pass- phrase		<b>Required</b> *. A string that sets a password used to secure the private key of the SSH key pair for download. This field is <b>required</b> if <i>IncludePrivateKey</i> is set to <i>true</i> .
		Tip: This password does not need to match the password entered to secure the private key when the SSH key pair was initially generated. The private key is encrypted at download time and a different password may be used for each download.

Table 425: GET SSH Keys My Key Response Data

Name	Description
ID	The Keyfactor Command reference ID for the user's SSH key pair.
Fingerprint	A string indicating the fingerprint of the public key. Each SSH public key has a single cryptographic fingerprint that can be used to uniquely identify the key.
PublicKey	A string indicating the public key of the key pair.
PrivateKey	A string indicating the private key of the key pair.
КеуТуре	A string indicating the cryptographic algorithm used to generate the SSH key pair. Possible values are:  RSA  ECDSA  Ed25519
KeyLength	An integer indicating the key length for the SSH key. The key length supported depends on the key type selected. Keyfactor Command supports 256 bits for Ed25519 and ECDSA and 2048 or 4096 bits for RSA.
CreationDate	The date, in UTC, on which the SSH key pair was created.
StaleDate	The date, in UTC, on which the SSH key pair will be considered to have reached the end of its lifetime. By default, the lifetime of an SSH key pair is 365 days.  The SSH lifetime is defined by the <i>Key Lifetime (days)</i> application setting. See in the <i>Keyfactor Command Reference Guide</i> for more information.
Email	A string containing the email address of the user who requested the key. This email address is used to alert the user when the key pair is approaching the end of its lifetime.
Comments	An array containing one or more strings with the user-defined descriptive comments, if any, on the key. Although entry of an email address in the comment field of an SSH key is traditional, this is not a required format. The comment may can contain any characters supported for string fields, including spaces and most punctuation marks. Keys created through the Keyfactor Command My SSH Key portal or with the POST /SSH/Keys/MyKey method will contain only one string in the array.
LogonCount	An integer indicating the number of Linux logons associated with the SSH key pair.

### POST SSH Keys My Key

The POST /SSH/Keys/MyKey method is used to generate a new SSH key pair for the current user in Keyfactor Command. The user needs to download the private key as an encrypted file and store it locally and an administrator needs to use Keyfactor Command to associate the user's Keyfactor user account with his or her Linux logon account(s) on the target server(s) that the user wishes to access via SSH (see POST SSH Logons Access on page 961, POST SSH Server Groups Access on page 1019, and POST SSH Servers Access on page 986). This method returns HTTP 200 OK on a success with the key's details.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature:

SSH: *User* OR

SSH: ServerAdmin OR SSH: EnterpriseAdmin

Table 426: POST SSH Keys My Key Input Parameters

Name	In	Description		
КеуТуре	Body	<b>Required</b> . A string indicating the cryptographic algorithm to use to generate the SSH key. Possible values are:		
		Numeric Value	Text Value	
		1	ECDSA	
		2	Ed25519	
		3	RSA	
		The KeyType may be specified using either the	numeric value or text value.	
PrivateKeyFormat	Body	<b>Required</b> . A string indicating the format to use Possible values are:	for the downloadable private key.	
		Numeric Value	Text Value	
		1	OpenSSH	
		2	PKCS8	
		The <i>PrivateKeyFormat</i> may be specified using a value.	either the numeric value or text	
KeyLength	Body	Required*. An integer indicating the key length supported depends on the key type selected. It for Ed25519 and ECDSA and 2048 or 4096 bits KeyType is set to ECDSA or Ed25519 and required.	Keyfactor Command supports 256 bits for RSA. This field is optional if the	
Email	Body	<b>Required</b> . A string containing the email address This email address is used to alert the user when end of its lifetime.		
Password	Body	<b>Required</b> . A string that sets a password used to SSH key pair for download.	o secure the private key of the	
		Tip: This password is used to secure the copy of the SSH key pair. You may late private key (see GET SSH Keys My Key different password, if desired.	r download the SSH key pair with	
Comment	Body	An array containing one or more strings with to comments, if any, on the key. Although entry of		

Name	In	Description
		field of an SSH key is traditional, this is not a required format. The comment may can contain any characters supported for string fields, including spaces and most punctuation marks.
	Note: Although this field is actually an array, entry of only a single comment string is supported. The field is defined as an array to support multiple comments on existing SSH keys found on servers during inventory and discovery.	

Table 427: POST SSH Keys My Key Response Data

Name	Description
ID	The Keyfactor Command reference ID for the user's SSH key pair.
Fingerprint	A string indicating the fingerprint of the public key. Each SSH public key has a single cryptographic fingerprint that can be used to uniquely identify the key.
PublicKey	A string indicating the public key of the key pair.
PrivateKey	A string indicating the private key of the key pair.
КеуТуре	A string indicating the cryptographic algorithm used to generate the SSH key pair. Possible values are:  RSA  ECDSA  Ed25519
KeyLength	An integer indicating the key length for the SSH key. The key length supported depends on the key type selected. Keyfactor Command supports 256 bits for Ed25519 and ECDSA and 2048 or 4096 bits for RSA.
CreationDate	The date, in UTC, on which the SSH key pair was created.
StaleDate	The date, in UTC, on which the SSH key pair will be considered to have reached the end of its lifetime. By default, the lifetime of an SSH key pair is 365 days.  The SSH lifetime is defined by the <i>Key Lifetime (days)</i> application setting. See in the <i>Keyfactor Command Reference Guide</i> for more information.
Email	A string containing the email address of the user who requested the key. This email address is used to alert the user when the key pair is approaching the end of its lifetime.
Comments	An array containing one or more strings with the user-defined descriptive comments, if any, on the key. Although entry of an email address in the comment field of an SSH key is traditional, this is not a required format. The comment may can contain any characters supported for string fields, including spaces and most punctuation marks. Keys created through the Keyfactor Command My SSH Key portal or with the POST /SSH/Keys/MyKey method will contain only one string in the array.
LogonCount	An integer indicating the number of Linux logons associated with the SSH key pair.

# PUT SSH Keys My Key

The PUT /SSH/Keys/MyKey method is used to update the existing SSH key pair for the current user in Keyfactor Command. Most features of a key pair are fixed and cannot be changed. Only the email address and comment associated with the key may be changed with this option. This method returns HTTP 200 OK on a success with the key's details.



**Tip:** The following permissions (see Security Overview) are required to use this feature:

SSH: User OR

SSH: ServerAdmin OR SSH: EnterpriseAdmin



Warning: Any previously populated fields that are not submitted with their full existing data using this method will be cleared of their existing data. When using this method, you should first do a GET to retrieve all the values for the record you want to update, enter corrected data into the field(s) you want to update, and then submit all the fields using PUT, including the fields that contain values but which you are not changing.

Table 428: PUT SSH Keys My Key Input Parameters

Name	In	Description
ID	Body	Required. The Keyfactor Command reference ID for the SSH key.
Email	Body	<b>Required</b> . A string containing the email address of the user who requested the key. This email address is used to alert the user when the key pair is approaching the end of its lifetime.
Comment	Body	An array containing one or more strings with the user-defined descriptive comments, if any, on the key. Although entry of an email address in the comment field of an SSH key is traditional, this is not a required format. The comment may can contain any characters supported for string fields, including spaces and most punctuation marks.
		Note: Although this field is actually an array, entry of only a single comment string is supported. The field is defined as an array to support multiple comments on existing SSH keys found on servers during inventory and discovery.

Table 429: PUT SSH Keys My Key Response Data

Name	Description	
ID	The Keyfactor Command reference ID for the user's SSH key pair.	
Fingerprint	A string indicating the fingerprint of the public key. Each SSH public key has a single cryptographic fingerprint that can be used to uniquely identify the key.	
PublicKey	A string indicating the public key of the key pair.	
КеуТуре	A string indicating the cryptographic algorithm used to generate the SSH key pair. Possible values are:  RSA  ECDSA  Ed25519	
KeyLength	An integer indicating the key length for the SSH key. The key length supported depends on the key type selected. Keyfactor Command supports 256 bits for Ed25519 and ECDSA and 2048 or 4096 bits for RSA.	
CreationDate	The date, in UTC, on which the SSH key pair was created.	
StaleDate	The date, in UTC, on which the SSH key pair will be considered to have reached the end of its lifetime. By default, the lifetime of an SSH key pair is 365 days.  The SSH lifetime is defined by the <i>Key Lifetime (days)</i> application setting. See <i>Application Settings: SSH Tab</i> in the <i>Keyfactor Command Reference Guide</i> for more information.	
Email	A string containing the email address of the user who requested the key. This email address is used to alert the user when the key pair is approaching the end of its lifetime.	
Comments	An array containing one or more strings with the user-defined descriptive comments, if any, on the key. Although entry of an email address in the comment field of an SSH key is traditional, this is not a required format. The comment may can contain any characters supported for string fields, including spaces and most punctuation marks. Keys created through the Keyfactor Command My SSH Key portal or with the POST /SSH/Keys/MyKey method will contain only one string in the array.	
LogonCount	An integer indicating the number of Linux logons associated with the SSH key pair.	

# **DELETE SSH Keys Unmanaged**

The DELETE /SSH/Keys/Unmanaged method is used to delete one or more unmanaged SSH keys. Keys discovered on SSH servers during inventory and discovery are considered unmanaged. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature:

SSH: ServerAdmin OR



SSH: EnterpriseAdmin

SSH actions are affected by ownership on the server group with which the key is associated and limited for users with only the *ServerAdmin* role. For more information, see *SSH Permissions* in the *Keyfactor Command Reference Guide*.



**Note:** Deleting an unmanaged key when the associated server is still in inventory only mode will not delete the key on the target server. The next time the server is scanned, the key will re-appear in Keyfactor Command. See the <u>Unmanaged SSH Keys</u> section of the *Keyfactor Command Reference Guide* for more information.

Table 430: DELETE SSH Keys Unmanaged Input Parameters

Name	In	Description
ids	ids Body	<b>Required</b> . An array of the Keyfactor Command reference IDs for the unmanaged SSH keys to be deleted provided in the request body in the following format (without parameter name): [4,27,89]
	Use the GET /SSH/Keys/Unmanaged method (see GET SSH Keys Unmanaged below) to retrieve a list of all the unmanaged keys to determine the unmanaged key IDs.	

## **GET SSH Keys Unmanaged**

The GET /SSH/Keys/Unmanaged method is used to retrieve one or more unmanaged SSH keys. Keys discovered on SSH servers during inventory and discovery are considered unmanaged. Results can be limited to selected keys using filtering, and URL parameters can be used to specify paging and the level of information detail. This method returns HTTP 200 OK on a success with details for the requested SSH keys.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature:

SSH: ServerAdmin OR SSH: EnterpriseAdmin

Table 431: GET SSH Keys Unmanaged Input Parameters

Name	In	Description
queryString	Query	A string containing a query to limit the results (e.g. field1 -eq value1 AND field2 -gt value2). The default is to return all records. Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns for the same feature. For querying guidelines, refer to the Keyfactor Command Reference Guide: Using the Unmanaged Keys Search. The query fields supported for this endpoint are:  • DiscoveredDate  • KeyComments  • KeyLength  • KeyType  • ServerId
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal.
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.

Table 432: GET SSH Keys Unmanaged Response Data

Name	Description
ID	An integer indicating the Keyfactor Command reference ID for the SSH key.
Fingerprint	A string indicating the fingerprint of the public key. Each SSH public key has a single cryptographic fingerprint that can be used to uniquely identify the key.
PublicKey	A string indicating the public key of the key pair.
КеуТуре	A string indicating the cryptographic algorithm used to generate the SSH key. Possible values are:  RSA  ECDSA  Ed25519
KeyLength	An integer indicating the key length for the SSH key. The key length supported depends on the key type selected. Keyfactor Command supports 256 bits for Ed25519 and ECDSA and 2048 or 4096 bits for RSA.
DiscoveredDate	The date, in UTC, on which the SSH key was discovered.
Comments	An array containing one or more strings with the user-defined descriptive comments, if any, on the key. Although entry of an email address in the comment field of an SSH key is traditional, this is not a required format. The comment may can contain any characters supported for string fields, including spaces and most punctuation marks. A key may appear with more than one comment if the originating authorized_keys file contained more than one comment.
LogonCount	An integer indicating the number of Linux logons associated with the SSH key.

# 2.2.25.2 SSH Logons

The SSH Logons component of the Keyfactor Web APIs includes methods necessary to view and manage the Linux user accounts associated with authorized\_keys files containing valid SSH public keys. The logons include both those discovered on SSH servers during the initial discovery phase using the orchestrator and those created in Keyfactor Command and published to the SSH servers using the orchestrator.

Table 433: SSH Logon Endpoints

Endpoint	Method	Description	Link
/{id}	DELETE	Deletes a Linux logon from Keyfactor Command.	DELETE SSH Logons ID on the next page
/{id}	GET	Returns information about a Linux logons.	GET SSH Logons ID on the next page

Endpoint	Method	Description	Link
/	GET	Returns information about one or more Linux logons.	GET SSH Logons on page 957
/	POST	Creates a new Linux logon in Keyfactor Command and, for servers in <i>inventory and publish policy</i> mode, publishes it out to a Linux server.	POST SSH Logons on page 959
/Access	POST	Maps users and service accounts with a Linux logon to associate the SSH keys of the users with the Linux logon.	POST SSH Logons Access on page 961

## **DELETE SSH Logons ID**

The DELETE /SSH/Logons/{id} method is used to delete a Linux logon in Keyfactor Command. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see Security Overview) are required to use this feature:

SSH: ServerAdmin OR SSH: EnterpriseAdmin

SSH actions are affected by ownership on the server group to which the server on which the logon exists belongs and limited for users with only the *ServerAdmin* role. For more information, see *SSH Permissions* in the *Keyfactor Command Reference Guide*.



**Note:** Deleting a logon in Keyfactor Command does not delete it on the Linux server. It must be manually removed from the Linux server at the same time. If this is not done, when the next inventory of the Linux server is performed, the logon will be recreated in Keyfactor Command. This method is intended primarily to be used to clean up logons in Keyfactor Command from SSH servers that have been retired.

Table 434: DELETE SSH Logons {id} Input Parameters

Name	In	Description
id	Path	<b>Required</b> . The Keyfactor Command reference ID for the SSH logon to be deleted.  Use the <i>GET /SSH/Logons</i> method (see <u>GET SSH Logons on page 957</u> ) to retrieve a list of all the SSH logons to determine the logon's ID.

# **GET SSH Logons ID**

The GET /SSH/Logons/{id} method is used to retrieve a Linux logon by ID. This method returns HTTP 200 OK on a success with details for the requested SSH logon.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature:

SSH: ServerAdmin OR SSH: EnterpriseAdmin

Table 435: GET SSH Logons {id} Input Parameters

Name	In	Description
id	Path	Required. The Keyfactor Command reference ID for the SSH logon to retrieve.  Use the GET /SSH/Logons method (see GET SSH Logons on the next page) to retrieve a list of all the SSH logons to determine the logon's ID.

Table 436: GET SSH Keys Unmanaged {id} Response Data

Name	Description		
ID	An integer indicating the Keyfactor Command reference ID for the SSH logon.		
Username	A string indicating	the user's	s logon name on the Linux server.
Server	Details about the s	server on	which the SSH logon resides. Server information includes:
	Name		Description
	Id		An integer indicating the Keyfactor Command reference ID of the server on which the SSH logon resides.
	Hostname		A string indicating the hostname of the SSH server on which the SSH logon resides. See <i>SSH Servers</i> in the <i>Keyfactor Command Reference Guide</i> for more information.
	UnderManagement		A Boolean indicating whether the server on which the SSH logon resides is in <i>inventory only</i> mode (false) or <i>inventory and publish policy</i> mode (true).
	GroupName		A string indicating the server group to which the server referenced by Hostname belongs. See SSH Server Groups in the Keyfactor Command Reference Guide for more information.
KeyCount	An integer indicating the number of SSH keys associated with the Linux logons.		
Access	An array of key/value pairs providing information about the users mapped to the logon. Access information includes:		
	Name	Descri	ption
	Id	An integer indicating the Keyfactor Command reference ID of a <i>user</i> or <i>service</i> account that has been associated with the logon. See <i>SSH</i> in the <i>Keyfactor</i> Command Reference Guide for more information.	
	Username	A string indicating the username of a <i>user</i> (in DOMAIN\\username format) or <i>service account</i> (in username@hostname format) that has been associated with the logon.	

# **GET SSH Logons**

The GET /SSH/Logons method is used to retrieve one or more Linux logons. Results can be limited to selected logons using filtering, and URL parameters can be used to specify paging and the level of information detail. This method returns HTTP 200 OK on a success with details for the requested SSH logons.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature:

SSH: ServerAdmin OR SSH: EnterpriseAdmin

Table 437: GET SSH Logons Input Parameters

Name	In	Description
queryString	Query	A string containing a query to limit the results (e.g. field1 -eq value1 AND field2 -gt value2). The default is to return all records. Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns for the same feature. For querying guidelines, refer to the Keyfactor Command Reference Guide: Using the Logons Search. The query fields supported for this endpoint are:  • Id (Login ID)  • LastLogon  • Hostname (Logon Server Name)  • LogonUserUsername  • ServerId  • UnmanagedKeyId  • Username
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>Username</i> .
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.

Table 438: GET SSH Logons Response Data

Name	Description
ID	An integer indicating the Keyfactor Command reference ID for the SSH logon.
Username	A string indicating the user's logon name on the Linux server.
ServerId	An integer indicating the Keyfactor Command reference ID of the server on which the SSH logon resides.
ServerName	A string indicating the hostname of the SSH server on which the SSH logon resides. See <i>SSH Servers</i> in the <i>Keyfactor Command Reference Guide</i> for more information.
GroupName	A string indicating the server group to which the server referenced by <i>ServerName</i> belongs. See <i>SSH Server Groups</i> in the <i>Keyfactor Command Reference Guide</i> for more information.
ServerUnderManagement	A Boolean indicating whether the server on which the SSH logon resides is in <i>inventory</i> only mode (false) or <i>inventory</i> and publish policy mode (true).
KeyCount	An integer indicating the number of SSH keys associated with the Linux logons.

# **POST SSH Logons**

The POST /SSH/Logons method is used to create a new Linux logon in Keyfactor Command and, for servers in *inventory and publish policy* mode, publish it out to a Linux server. The logon can optionally be associated with one or more SSH keys by mapping the logon to one or more *users* or *service accounts* during creation. This method returns HTTP 200 OK on a success with details for the new SSH logon.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature:

SSH: ServerAdmin OR SSH: EnterpriseAdmin

Table 439: POST SSH Logons Input Parameters

Name	In	Description
Username	Body	<b>Required</b> . A string indicating the user's logon name on the Linux server.
ServerId	Body	Required. An integer indicating the Keyfactor Command reference ID of the server on which the SSH logon should be created.  Use the GET/SSH/Servers method (see GET SSH Servers on page 969) to retrieve a list of all the SSH servers to determine the server's ID.
Userlds	Body	An array of integers indicating the Keyfactor Command reference IDs for the users and/or service accounts with which the logon should be associated, provided in the following format:  [4,7,19]  See the <u>SSH</u> section of the <i>Keyfactor Command Reference Guide</i> for more information about users and service accounts.  Use the <i>GET /SSH/Users</i> method (see <u>GET SSH Users on page 1068</u> ) to retrieve a list of all the users (including service accounts) created in Keyfactor Command to determine a user's ID.

Table 440: POST SSH Logons Response Data

Name	Description			
ID	An integer indicating the Keyfactor Command reference ID for the SSH logon.			
Username	A string indicating the user's logon name on the Linux server.			
Server	Details about the server on which the SSH logon resides. Server information includes:			
	Name		Description	
	Id		An integer indicating the Keyfactor Command reference ID of the server on which the SSH logon resides.	
	Hostname		A string indicating the hostname of the SSH server on which the SSH logon resides. See <i>SSH Servers</i> in the <i>Keyfactor Command Reference Guide</i> for more information.	
	UnderManagement		A Boolean indicating whether the server on which the SSH logon resides is in <i>inventory only</i> mode (false) or <i>inventory and publish policy</i> mode (true).	
	GroupName		A string indicating the server group to which the server referenced by Hostname belongs. See SSH Server Groups in the Keyfactor Command Reference Guide for more information.	
KeyCount	An integer indicating the number of SSH keys associated with the Linux logons.			
Access	An array of key/va ation includes:	lue pairs pr	oviding information about the users mapped to the logon. Access inform-	
	Name Descrip		tion	
	Id	An integer indicating the Keyfactor Command reference ID of a <i>user</i> or <i>service account</i> that has been associated with the logon. See <i>SSH</i> in the <i>Keyfactor Command Reference Guide</i> for more information.		
	Username	A string indicating the username of a <i>user</i> (in DOMAIN\\username format) or <i>service account</i> (in username@hostname format) that has been associated with the logon.		

# **POST SSH Logons Access**

The POST /SSH/Logons/Access method is used to associate one or more SSH keys with a Linux logon by mapping the logon to one or more *users* or *service accounts*. This method returns HTTP 200 OK on a success with a list of the users associated with the logon.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature:

SSH: ServerAdmin OR SSH: EnterpriseAdmin

Table 441: POST SSH Logons Access Input Parameters

Name	In	Description
LogonId	Body	Required. An integer indicating the Keyfactor Command reference ID for the SSH logon.  Use the GET /SSH/Logons method (see GET SSH Logons on page 957) to retrieve a list of all the SSH logons to determine the logon's ID.
Userlds	Body	An array of integers indicating the Keyfactor Command reference IDs for the users and/or service accounts with which the logon should be associated, provided in the following format:  [4,7,19]  Use the GET /SSH/Users method (see GET SSH Users on page 1068) to retrieve a list of all the users (including service accounts) created in Keyfactor Command to determine a user's ID.  See the SSH section of the Keyfactor Command Reference Guide for more information about users and service accounts.

Table 442: POST SSH Logons Access Response Data

Name	Description			
LogonId	An integer indicating the Keyfactor Command reference ID for the SSH logon.			
LogonName	A string indicating	A string indicating the user's logon name on the Linux server.		
Users	An array of key/value pairs providing information about the users mapped to the logon. User information includes:			
	Name	Description		
	Id	An integer indicating the Keyfactor Command reference ID of a <i>user</i> or <i>service</i> account that has been associated with the logon. See the <u>SSH</u> section of the <i>Keyfactor Command Reference Guide</i> for more information.		
	Username	A string indicating the username of a <i>user</i> (in DOMAIN\\username format) or <i>service account</i> (in username@hostname format) that has been associated with the logon.		

#### 2.2.25.3 SSH Servers

The SSH Servers component of the Keyfactor Web APIs includes methods necessary to create, update, and delete SSH servers within Keyfactor Command.

Table 443: SSH Servers Endpoints

Endpoint	Method	Description	Link
/{id}	DELETE	Deletes the SSH server with the specified ID.	DELETE SSH Servers  ID below
/{id}	GET	Returns the SSH server with the specified ID.	GET SSH Servers ID on the next page
/Access/{id}	GET	Retrieves Linux logons along with users and service accounts granted access to those logons for the specified SSH server.	GET SSH Servers Access ID on page 968
/	GET	Returns a list of a SSH servers configured in Keyfactor Command.	GET SSH Servers on page 969
/	POST	Creates a new SSH server.	POST SSH Servers on page 974
/	PUT	Updates an existing SSH server.	PUT SSH Servers on page 979
/Access	DELETE	Deletes Linux logon to user and service account mappings for an SSH server.	DELETE SSH Servers Access on page 984
/Access	POST	Creates Linux logon to user and service account mappings for an SSH server.	POST SSH Servers Access on page 986

#### **DELETE SSH Servers ID**

The DELETE /SSH/Servers/{id} method is used to delete an SSH server in Keyfactor Command. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature:

SSH: ServerAdmin OR SSH: EnterpriseAdmin

Table 444: DELETE SSH Servers {id} Input Parameters

Name	In	Description
id	Path	Required. The Keyfactor Command reference ID for the SSH server to be deleted.  Use the GET /SSH/Servers method (see GET SSH Servers on page 969) to retrieve a list of all the SSH servers to determine the server's ID.

### **GET SSH Servers ID**

The GET /SSH/Servers/{id} method is used to retrieve an SSH server with the specified ID from Keyfactor Command. This method returns HTTP 200 OK on a success with details for the specified SSH server.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature:

SSH: ServerAdmin OR SSH: EnterpriseAdmin

Table 445: GET SSH Servers {id} Input Parameters

Name	In	Description
id	Path	<b>Required</b> . The Keyfactor Command reference ID for the SSH server to be retrieved.  Use the <i>GET /SSH/Servers</i> method (see <u>GET SSH Servers on page 969</u> ) to retrieve a list of all the SSH servers to determine the server's ID.

Table 446: GET SSH Servers {id} Response Data

Name	Description			
ID	An integer indicating the Keyfactor Command reference ID for the SSH server. This ID is automatically set by Keyfactor Command.			
AgentId	A string indicating the Keyfactor Command reference GUID for the SSH orchestrator controlling the SSH server.			
Hostname	A string indica	ting the hostname of the SSH server.		
ServerGroupId	A string indicating the Keyfactor Command reference GUID for the SSH server group to which the server belongs.			
SyncSchedule	An array providing the inventory schedule for the SSH server group to which the SSH server belongs. Inventory schedules cannot be set on an individual SSH server basis. The schedule can be off (unset) or one of the supported values. Supported schedule values are:			
	Name	Description		
	Off	Turn off a previously configured schedule.		
	Interval	A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database.		
		Name Description		
		Minutes An integer indicating the number of minutes between each interval.		
		For example, every hour:		
		"Interval": {     "Minutes": 60 }		
	Daily	A dictionary that indicates a job scheduled to run every day at the same time with the parameter:		

Name	Description	ion		
	Name	Description		
		Name	Description	
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
		For example, da	aily at 11:30 pm:	
		"Daily": {     "Time": }	"2022-02-25T23:30:00Z"	
	Weekly	A dictionary that indicates a job scheduled to run on a specific day or days every week at the same time with the parameters:		
		Name	Description	
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
		Days	An array of values representing the days of the week on which to run the job. These can either be entered as integers (0 for Sunday, 1 for Monday, etc.) or as days of the week (e.g. "Sunday").	
		<pre>For example, every Monday, Wednesday and Friday at 5:30 pm:  "Weekly": {     "Days": [         "Monday",         "Wednesday",         "Friday"     ],     "Time": "2022-02-27T17:30:00Z" }</pre>		
	Monthly		it indicates a job scheduled to run on a specific day or days every me time with the parameters:	

Name	Description		
	Name	Description	
		Name	Description
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
		Day	The number of the day, in the month, to run the job.
		"Monthly":	
		"Day": 1 "Time": }	"2022-02-27T17:30:00Z"
	Note: Although the Swagger Example Value may show examples of various other schedules, only the schedules shown here—that are available in the Management Portal for the functionality—are valid for this endpoint.  For example:		
"SyncSchedule": {     "Weekly": {         "Days": [		0T14:00:00Z"	
Under- Management	A Boolean indicating whether the SSH server is in <i>inventory only</i> mode (False) or <i>inventory and publish policy</i> mode (True).		
	Tip: If the server group associated with the SSH server is in <i>inventory and publish policy</i> mode, you will not be able to configure the server in <i>inventory only</i> mode.		
Owner	An array that indicates the Active Directory user who owns the server group to which the server belongs. The owner can only be set by a Keyfactor Command user with the SSH Enterprise Admin role. See SSH Server Groups in the Keyfactor Command Reference Guide for more information. Owner parameters are:		

Name	Description		
	Name	Description	
	Id	An integer indicating the Keyfactor Command reference ID of the <i>user</i> who holds the owner role on the SSH server group to which the SSH server belongs.	
	Username	A string indicating the username of the <i>user</i> (in DOMAIN\\username format) who holds the owner role on the SSH server group to which the SSH server belongs.	
GroupName	A string indicating the SSH server group to which the SSH server belongs. See <i>SSH Server Groups</i> in the <i>Keyfactor Command Reference Guide</i> for more information.		
Orchestrator	A string indicating the name the SSH orchestrator provided to Keyfactor Command when it registered. This value is configurable when the orchestrator is installed.  For more information about the orchestrator, see <i>Bash Orchestrator</i> in the <i>Keyfactor Orchestrators Installation and Configuration Guide</i> .		
Port	An integer indicating the port that is configured for SSH on the SSH server. The default is 22.		

### **GET SSH Servers Access ID**

The GET /SSH/Servers/Access/{id} method is used to retrieve Linux logons for an SSH server, along with any users or service accounts mapped to those logons, from Keyfactor Command for the specified server ID. This method returns HTTP 200 OK on a success with details of the logons and associated users, if applicable, for the specified SSH server.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature:

SSH: ServerAdmin OR SSH: EnterpriseAdmin

Table 447: GET SSH Servers Access {id} Input Parameters

Name	In	Description
id	Path	Required. The Keyfactor Command reference ID for the SSH server for which to retrieve logon and user mappings.  Use the GET /SSH/Servers method (see GET SSH Servers on the next page) to retrieve a list of all the SSH servers to determine the server's ID.

Table 448: GET SSH Servers Access {id} Response Data

Name	Description			
ServerId	An integer indicating the Keyfactor Command reference ID for the SSH server.			
LogonUsers	An array containing information for the Linux logons from the Linux server that have been stored in Keyfactor Command. Possible information includes:			
	Name	Description		
	LogonId	An integer indicati	ng the Keyfactor Command reference ID of the Linux logon.	
	LogonName	A string indicating	the name of the Linux logon.	
	Users	An array of user objects containing information about the users and/or service accounts defined in Keyfactor Command that have been mapped to the Linux logon. User information includes:		
		Name	Description	
		Id	An integer indicating the Keyfactor Command reference ID of a user or service account that has been associated with the logon. See SSH in the Keyfactor Command Reference Guide for more information.	
		Username	A string indicating the username of a <i>user</i> (in DOMAIN\\username format) or <i>service account</i> (in username@hostname format) that has been associated with the logon.	

#### **GET SSH Servers**

The GET /SSH/Servers method is used to retrieve one or more SSH servers defined in Keyfactor Command. Results can be limited to selected servers using filtering, and URL parameters can be used to specify paging and the level of information detail. This method returns HTTP 200 OK on a success with details for the requested SSH servers.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature:

SSH: ServerAdmin OR SSH: EnterpriseAdmin

Table 449: GET SSH Servers Input Parameters

Name	In	Description
queryString	Query	A string containing a query to limit the results (e.g. field1 -eq value1 AND field2 -gt value2). The default is to return all records. Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns for the same feature. For querying guidelines, refer to the Keyfactor Command Reference Guide: Using the SSH Server Search. The query fields supported for this endpoint are:  • Agent (Agent ID)  • Hostname  • Orchestrator (ClientMachine)  • ServerGroup (Server Group Id)  • ServerGroupOwner (Username)  • EnforcePublishPolicy (UnderManagement) (true, false)
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>Host-name</i> .
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.

Table 450: GET SSH Servers Response Data

Name	Description		
ID	An integer indicating the Keyfactor Command reference ID for the SSH server. This ID is automatically set by Keyfactor Command.		
AgentId	A string indicating the Keyfactor Command reference GUID for the SSH orchestrator controlling the SSH server.		
Hostname	A string indica	ting the hostname of the SSH server.	
ServerGroupId	A string indica server belongs	ting the Keyfactor Command reference GUID for the SSH server group to which the	
SyncSchedule	belongs. Inven	ding the inventory schedule for the SSH server group to which the SSH server story schedules cannot be set on an individual SSH server basis. The schedule can be one of the supported values. Supported schedule values are:	
	Name Description		
	Off	Turn off a previously configured schedule.	
	Interval	A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database.	
		Name Description	
		Minutes An integer indicating the number of minutes between each interval.	
		For example, every hour:	
		"Interval": {     "Minutes": 60 }	
	Daily	A dictionary that indicates a job scheduled to run every day at the same time with the parameter:	

Name	Description		
	Name	Description	
		Name	Description
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
		For example, da	aily at 11:30 pm:
		"Daily": {     "Time": }	"2022-02-25T23:30:00Z"
	Weekly		nt indicates a job scheduled to run on a specific day or days every ne time with the parameters:
		Name	Description
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
		Days	An array of values representing the days of the week on which to run the job. These can either be entered as integers (0 for Sunday, 1 for Monday, etc.) or as days of the week (e.g. "Sunday").
		"Weekly": {     "Days":     "Mono     "Wedr     "Fric	[ day", nesday",
	Monthly		it indicates a job scheduled to run on a specific day or days every me time with the parameters:

Name	Description			
	Name	Description		
		Name	Description	
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
		Day	The number of the day, in the month, to run the job.	
		<pre>For example, on the first of every month at 5:30 pm: "Monthly": {     "Day": 1     "Time": "2022-02-27T17:30:00Z" }</pre>		
	Note: Although the Swagger Example Value may show examples of various other so ules, only the schedules shown here—that are available in the Management Portal functionality—are valid for this endpoint.			
	For example:			
	" " ,[	•	0T14:00:00Z"	
Under- Management		A Boolean indicating whether the SSH server is in <i>inventory only</i> mode (False) or <i>inventory and</i> publish policy mode (True).		
			associated with the SSH server is in <i>inventory and publish policy</i> ole to configure the server in <i>inventory only</i> mode.	
Owner	An array that indicates the Active Directory user who owns the server group to which the server belongs. The owner can only be set by a Keyfactor Command user with the SSH Enterprise Admin role. See SSH Server Groups in the Keyfactor Command Reference Guide for more information. Owner parameters are:			

Name	Description		
	Name	Description	
	Id	An integer indicating the Keyfactor Command reference ID of the <i>user</i> who holds the owner role on the SSH server group to which the SSH server belongs.	
	Username	A string indicating the username of the <i>user</i> (in DOMAIN\\username format) who holds the owner role on the SSH server group to which the SSH server belongs.	
GroupName	A string indicating the SSH server group to which the SSH server belongs. See SSH Server Groups in the Keyfactor Command Reference Guide for more information.		
Orchestrator	A string indicating the name the SSH orchestrator provided to Keyfactor Command when it registered. This value is configurable when the orchestrator is installed.  For more information about the orchestrator, see <i>Bash Orchestrator</i> in the <i>Keyfactor Orchestrators Installation and Configuration Guide</i> .		
Port	An integer indicating the port that is configured for SSH on the SSH server. The default is 22.		

### **POST SSH Servers**

The POST /SSH/Servers method is used to create a new SSH server in Keyfactor Command. This method returns HTTP 200 OK on a success with details for the new SSH server.

Before adding a new SSH server, be sure that you have added at least one server group (see <u>POST SSH Server</u> <u>Groups on page 1003</u>) and that your Keyfactor Bash Orchestrator has been registered and approved in Keyfactor Command (see GET Agents on page 12).



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature:

SSH: ServerAdmin OR SSH: EnterpriseAdmin

Table 451: POST SSH Servers Input Parameters

Name	In	Description	
AgentId	Body	<b>Required</b> . A string indicating the Keyfactor Command reference GUID for the SSH orchestrator controlling the SSH server.	
Hostname	Body	Required. A string indicating the hostname of the SSH server.	
ServerGroupId	Body	<b>Required</b> . A string indicating the Keyfactor Command reference GUID for the SSH server group to which the server belongs.	
UnderManagement	Body	A Boolean indicating whether the SSH server is in <i>inventory only</i> mode (False) or <i>inventory and publish policy</i> mode (True).	
		Tip: If the server group associated with the SSH server is in inventory and publish policy mode, you will not be able to configure the server in inventory only mode.	
Port	Body	An integer indicating the port that is configured for SSH on the SSH server. The default is 22.	

Table 452: POST SSH Servers Response Data

Name	Description		
ID	An integer indicating the Keyfactor Command reference ID for the SSH server. This ID is automatically set by Keyfactor Command.		
AgentId	A string indicating the Keyfactor Command reference GUID for the SSH orchestrator controlling the SSH server.		
Hostname	A string indica	ting the hostname of the SSH server.	
ServerGroupId	A string indica server belongs	ting the Keyfactor Command reference GUID for the SSH server group to which the	
SyncSchedule	belongs. Inven	ding the inventory schedule for the SSH server group to which the SSH server atory schedules cannot be set on an individual SSH server basis. The schedule can be one of the supported values. Supported schedule values are:	
	Name Description		
	Off	Turn off a previously configured schedule.	
	Interval	A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database.	
		Name Description	
		Minutes An integer indicating the number of minutes between each interval.	
		For example, every hour:	
		"Interval": {     "Minutes": 60 }	
	Daily	A dictionary that indicates a job scheduled to run every day at the same time with the parameter:	

Name	Description		
	Name	Description	
		Name	Description
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
		For example, da	aily at 11:30 pm:
		"Daily": {     "Time": }	"2022-02-25T23:30:00Z"
	Weekly		nt indicates a job scheduled to run on a specific day or days every ne time with the parameters:
		Name	Description
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
		Days	An array of values representing the days of the week on which to run the job. These can either be entered as integers (0 for Sunday, 1 for Monday, etc.) or as days of the week (e.g. "Sunday").
		"Weekly": {     "Days":     "Mono     "Wedr     "Fric	[ day", nesday",
	Monthly		it indicates a job scheduled to run on a specific day or days every me time with the parameters:

Name	Description			
	Name	Description		
		Name	Description	
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
		Day	The number of the day, in the month, to run the job.	
		"Monthly":		
		"Day": 1 "Time": "2022-02-27T17:30:00Z" }		
	ules, o	_	agger Example Value may show examples of various other sched- shown here—that are available in the Management Portal for this for this endpoint.	
	For example:			
	],		0T14:00:00Z"	
Under- Management	A Boolean indicating whether the SSH server is in <i>inventory only</i> mode (False) or <i>inventory and publish policy</i> mode (True).			
			associated with the SSH server is in <i>inventory and publish policy</i> ole to configure the server in <i>inventory only</i> mode.	
Owner	An array that indicates the Active Directory user who owns the server group to which the server belongs. The owner can only be set by a Keyfactor Command user with the SSH Enterprise Admin role. See SSH Server Groups in the Keyfactor Command Reference Guide for more information. Owner parameters are:			

Name	Description		
	Name	Description	
	Id	An integer indicating the Keyfactor Command reference ID of the <i>user</i> who holds the owner role on the SSH server group to which the SSH server belongs.	
	Username	A string indicating the username of the <i>user</i> (in DOMAIN\\username format) who holds the owner role on the SSH server group to which the SSH server belongs.	
GroupName	A string indicating the SSH server group to which the SSH server belongs. See SSH Server Groups in the Keyfactor Command Reference Guide for more information.		
Orchestrator	A string indicating the name the SSH orchestrator provided to Keyfactor Command when it registered. This value is configurable when the orchestrator is installed.  For more information about the orchestrator, see <i>Bash Orchestrator</i> in the <i>Keyfactor Orchestrators Installation and Configuration Guide</i> .		
Port	An integer indicating the port that is configured for SSH on the SSH server. The default is 22.		

### **PUT SSH Servers**

The PUT /SSH/Servers method is used to update an existing SSH server in Keyfactor Command. This method returns HTTP 200 OK on a success with details for the SSH server.



**Tip:** The following permissions (see Security Overview) are required to use this feature:

SSH: ServerAdmin OR SSH: EnterpriseAdmin

SSH actions are affected by ownership on the server group to which the server belongs and limited for users with only the *ServerAdmin* role. For more information, see *SSH Permissions* in the *Keyfactor Command Reference Guide*.



Warning: Any previously populated fields that are not submitted with their full existing data using this method will be cleared of their existing data. When using this method, you should first do a GET to retrieve all the values for the record you want to update, enter corrected data into the field(s) you want to update, and then submit all the fields using PUT, including the fields that contain values but which you are not changing.

Table 453: PUT SSH Servers Input Parameters

Name	In	Description	
ID	Body	<b>Required</b> . The Keyfactor Command reference ID for the SSH server. This ID is automatically set by Keyfactor Command.	
UnderManagement	Body	A Boolean indicating whether the SSH server is in <i>inventory only</i> mode (False) or <i>inventory and publish policy</i> mode (True).	
		Tip: If the server group associated with the SSH server is in <i>inventory and publish policy</i> mode, you will not be able to configure the server in <i>inventory only</i> mode.	
Port	Body	The port that is configured for SSH on the SSH server. The default is 22.	

Table 454: PUT SSH Servers Response Data

Name	Description			
ID	An integer indicating the Keyfactor Command reference ID for the SSH server. This ID is automatically set by Keyfactor Command.			
AgentId	A string indicating the Keyfactor Command reference GUID for the SSH orchestrator controlling the SSH server.			
Hostname	A string indica	ting the hostname of the SSH server.		
ServerGroupId	A string indica server belongs	ting the Keyfactor Command reference GUID for the SSH server group to which the		
SyncSchedule	belongs. Inven	ding the inventory schedule for the SSH server group to which the SSH server story schedules cannot be set on an individual SSH server basis. The schedule can be one of the supported values. Supported schedule values are:		
	Name	Description		
	Off	Turn off a previously configured schedule.		
	Interval	A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database.		
		Name Description		
		Minutes An integer indicating the number of minutes between each interval.		
		For example, every hour:		
		"Interval": {     "Minutes": 60 }		
	Daily	A dictionary that indicates a job scheduled to run every day at the same time with the parameter:		

Name	Description	scription	
	Name	Description	
		Name	Description
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
		For example, da	illy at 11:30 pm:
		"Daily": {     "Time": }	"2022-02-25T23:30:00Z"
	Weekly	A dictionary that indicates a job scheduled to run on a specific day or days every week at the same time with the parameters:	
		Name	Description
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
		Days	An array of values representing the days of the week on which to run the job. These can either be entered as integers (0 for Sunday, 1 for Monday, etc.) or as days of the week (e.g. "Sunday").
		<pre>For example, every Monday, Wednesday and Friday at 5:30 pm:  "Weekly": {     "Days": [         "Monday",         "Wednesday",         "Friday"     ],     "Time": "2022-02-27T17:30:00Z" }</pre>	
	Monthly	A dictionary that indicates a job scheduled to run on a specific day or days every month at the same time with the parameters:	

Name	Description			
	Name	Description		
		Name	Description	
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
		Day	The number of the day, in the month, to run the job.	
		For example, on the first of every month at 5:30 pm:  "Monthly": {		
	"Day": 1 "Time": "2022-02-27T17:30:00Z" }			
	Note: Although the Swagger Example Value may show examples of various other schedules, only the schedules shown here—that are available in the Management Portal for this functionality—are valid for this endpoint.			
	For example:	For example:		
"Wee		edule": { ly": { ays": [ "Monday", "Wednesday", "Friday" ime": "2022-11-20T14:00:00Z"		
Under- Management	A Boolean indicating whether the SSH server is in <i>inventory only</i> mode (False) or <i>inventory and publish policy</i> mode (True).			
	Tip: If the server group associated with the SSH server is in <i>inventory and publish policy</i> mode, you will not be able to configure the server in <i>inventory only</i> mode.			
Owner	An array that indicates the Active Directory user who owns the server group to which the server belongs. The owner can only be set by a Keyfactor Command user with the SSH Enterprise Admin role. See SSH Server Groups in the Keyfactor Command Reference Guide for more information. Owner parameters are:			

Name	Description		
	Name	Description	
	Id	An integer indicating the Keyfactor Command reference ID of the <i>user</i> who holds the owner role on the SSH server group to which the SSH server belongs.	
	Username	A string indicating the username of the <i>user</i> (in DOMAIN\\username format) who holds the owner role on the SSH server group to which the SSH server belongs.	
GroupName	A string indicating the SSH server group to which the SSH server belongs. See SSH Server Groups in the Keyfactor Command Reference Guide for more information.		
Orchestrator	A string indicating the name the SSH orchestrator provided to Keyfactor Command when it registered. This value is configurable when the orchestrator is installed.  For more information about the orchestrator, see <i>Bash Orchestrator</i> in the <i>Keyfactor Orchestrators Installation and Configuration Guide</i> .		
Port	An integer indicating the port that is configured for SSH on the SSH server. The default is 22.		

#### **DELETE SSH Servers Access**

The DELETE /SSH/Servers/Access method is used to remove a mapping of Keyfactor Command users or service accounts to one or more Linux logons on one or more SSH servers. This method returns HTTP 200 OK on a success with details of the logons and remaining associated users, if applicable, for the specified SSH server(s).



Tip: The following permissions (see Security Overview) are required to use this feature:

SSH: ServerAdmin OR SSH: EnterpriseAdmin

SSH actions are affected by ownership on the server group to which the server belongs and limited for users with only the *ServerAdmin* role. For more information, see *SSH Permissions* in the *Keyfactor Command Reference Guide*.



**Tip:** Before deleting a logon to user mapping, be sure that you have switched the server from which you will removing your mapping (or its server group) to *inventory and publish policy* mode so that the key for the user will be removed from the server. If the server is in *inventory only* mode and you remove a mapping for it in Keyfactor Command, the mapping will be removed in Keyfactor Command only and the key for the user will not be removed from the server.

Table 455: DELETE SSH Servers Access Input Parameters

Name	In	Description		
ServerId	Body	Required. The Keyfactor Command reference ID for the SSH server.		
LogonUsers	Body	<b>Required</b> . An array containing information for the Linux logon(s) to update. The following information should be included:		
		Name	Description	
		LogonName	A string indicating the name of the Linux logon.	
	Users	An array of strings indicating the user names of one or more users (in DOMAIN\\username format) or service accounts (in username@hostname format) to be removed from association with the logon.		
		<pre>"LogonUsers": [</pre>		

Table 456: DELETE SSH Servers Access Response Data

Name	Description			
ServerId	An integer indicating the Keyfactor Command reference ID for the SSH server.			
LogonUsers	An array containing information for the Linux logons from the Linux server that have been stored in Keyfactor Command. Possible information includes:			
	Name	Description		
	LogonId	An integer indicating the Keyfactor Command reference ID of the Linux logon.		
	LogonName A string indicating the name of the Linux logon.			
	Users	An array of user objects containing information about the users and/or service accounts defined in Keyfactor Command that have been mapped to the Linux logon. User information includes:		
		Name	Description	
		Id	An integer indicating the Keyfactor Command reference ID of a user or service account that has been associated with the logon. See SSH in the Keyfactor Command Reference Guide for more information.	
		Username	A string indicating the username of a <i>user</i> (in DOMAIN\\username format) or <i>service account</i> (in username@hostname format) that has been associated with the logon.	

#### **POST SSH Servers Access**

The POST /SSH/Servers/Access method is used to create a mapping of one or more Linux logons to Keyfactor Command users or service accounts for one or more SSH servers. This method returns HTTP 200 OK on a success with details of the logons and associated users, if applicable, for the specified SSH server(s).



**Tip:** The following permissions (see Security Overview) are required to use this feature:

SSH: ServerAdmin OR SSH: EnterpriseAdmin



**Tip:** Before creating a logon to user mapping, be sure that you have switched the server to which you will add your mapping (or its server group) to *inventory and publish policy* mode so that the key for the user will be published to the server. If the server is in *inventory only* mode and you add a mapping for it in Keyfactor Command, the mapping will appear in Keyfactor Command only and the key for the user will not be published out to the server.

Table 457: POST SSH Servers Access Input Parameters

Name	In	Description		
ServerId	Body	Required. The Keyfactor Command reference ID for the SSH server.		
LogonUsers	Body	<b>Required</b> . An array containing information for the Linux logon(s) to update. The following information should be included:		
		Name	Description	
		LogonName	A string indicating the name of the Linux logon.	
		Users	An array of strings indicating the user names of one or more users (in DOMAIN\\username format) or service accounts (in username@hostname format) to be associated with the logon.	
		For example:		
		"Users":	ne": "johns",	

Table 458: POST SSH Servers Access Response Data

Name	Description			
ServerId	An integer indicating the Keyfactor Command reference ID for the SSH server.			
LogonUsers	An array containing information for the Linux logons from the Linux server that have been stored in Keyfactor Command. Possible information includes:			
	Name	Name Description		
	LogonId	An integer indicati	ng the Keyfactor Command reference ID of the Linux logon.	
	LogonName	A string indicating	the name of the Linux logon.	
	Users		ojects containing information about the users and/or service in Keyfactor Command that have been mapped to the Linux mation includes:	
		Name	Description	
		Id	An integer indicating the Keyfactor Command reference ID of a user or service account that has been associated with the logon. See SSH in the Keyfactor Command Reference Guide for more information.	
		Username	A string indicating the username of a <i>user</i> (in DOMAIN\\username format) or <i>service account</i> (in username@hostname format) that has been associated with the logon.	

# 2.2.25.4 SSH Server Groups

The SSH Server Groups component of the Keyfactor Web APIs includes methods necessary to create, update and delete SSH server groups within Keyfactor Command.

Table 459: SSH Server Groups Endpoints

Endpoint	Method	Description	Link
/{id}	DELETE	Deletes the SSH server group with the specified ID.	DELETE SSH Server Groups ID on the next page
/{id}	GET	Returns the SSH server group with the specified ID.	GET SSH Server Groups ID on page 990

Endpoint	Method	Description	Link
/{name}	GET	Returns the SSH server group with the specified name.	GET SSH Server Groups Name on page 993
/Access/{id}	GET	Retrieves Linux logons along with users and service accounts granted access to those logons for the specified SSH server group.	GET SSH Server Groups Access ID on page 998
/	GET	Returns a list of a SSH server groups configured in Keyfactor Command.	GET SSH Server Groups on page 999
/	POST	Creates a new SSH server group.	POST SSH Server Groups on page 1003
/	PUT	Updates an existing SSH server group.	PUT SSH Server Groups on page 1010
/Access	DELETE	Deletes Linux logon to user and service account mappings for an SSH server group.	DELETE SSH Server Groups Access on page 1018
/Access	POST	Creates Linux logon to user and service account mappings for an SSH server group.	POST SSH Server Groups Access on page 1019

## **DELETE SSH Server Groups ID**

The DELETE /SSH/ServerGroups/{id} method is used to delete an SSH server group in Keyfactor Command. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: SSH: *EnterpriseAdmin* 

Table 460: DELETE SSH Server Groups {id} Input Parameters

Name	In	Description
id	Path	Required. A string indicating the Keyfactor Command reference GUID for the SSH server group to be deleted.  Use the GET /SSH/ServerGroups method (see GET SSH Server Groups on page 999) to retrieve a list of all the SSH server groups to determine the server group's GUID.

### **GET SSH Server Groups ID**

The GET /SSH/ServerGroups/{id} method is used to retrieve an SSH server group with the specified GUID from Keyfactor Command. This method returns HTTP 200 OK on a success with details for the specified SSH server group.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature:

SSH: ServerAdmin OR SSH: EnterpriseAdmin

Table 461: GET SSH Server Groups {id} Input Parameters

Name	In	Description
id	Path	<b>Required</b> . A string indicating the Keyfactor Command reference GUID for the SSH server group to be retrieved.  Use the <i>GET /SSH/ServerGroups</i> method (see <u>GET SSH Server Groups on page 999</u> ) to retrieve a list of all the SSH server groups to determine the server group's GUID.

Table 462: GET SSH Server Groups {id} Response Data

Name	Description			
ID	A string indicating the Keyfactor Command reference GUID for the SSH server group. This GUID is automatically set by Keyfactor Command.			
Owner	An object indicating the Active Directory user who owns the server group. See <i>SSH Server Groups</i> in the <i>Keyfactor Command Reference Guide</i> for more information. Owner parameters are:			
	Name	Description		
	Id	An integer indicating the Keyfactor Command reference ID of the <i>user</i> who holds the owner role on the SSH server group.		
	Username	A string indicating the username of the <i>user</i> (in DOMAIN\\username format) who holds the owner role on the SSH server group.		
GroupName	A string indicating the name of the SSH server group.			
SyncSchedule		ling the inventory schedule for the SSH server group. The schedule can be off (unset) apported values. Supported schedule values are:		
	Name	Description		
	Off	Turn off a previously configured schedule.		
	Interval	A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database.		
		Name Description		
		Minutes An integer indicating the number of minutes between each interval.		
		For example, every hour:		
		"Interval": {     "Minutes": 60 }		

Name	Description				
	Name	Description			
	Daily		A dictionary that indicates a job scheduled to run every day at the same time with the parameter:		
		Name	Description		
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).		
		For example, o	daily at 11:30 pm:		
		"Daily": "Time" }	{ : "2022-02-25T23:30:00Z"		
	Weekly		nat indicates a job scheduled to run on a specific day or days every ame time with the parameters:  Description		
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).		
		Days	An array of values representing the days of the week on which to run the job. These can either be entered as integers (0 for Sunday, 1 for Monday, etc.) or as days of the week (e.g. "Sunday").		
		"Weekly": "Days": "Mor "Wee			
	Monthly	A dictionary th	nat indicates a job scheduled to run on a specific day or days every		

Name	Description			
	Name	Description		
		month at the same time with the parameters:		
		Name	Description	
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
		Day	The number of the day, in the month, to run the job.	
	ules, c	"Monthly":     "Day":     "Time": }  Although the Swonly the schedule:		
	],		20T14:00:00Z"	
Under- Management	A Boolean indicating whether the SSH server group is in <i>inventory only</i> mode (False) or <i>inventory and publish policy</i> mode (True).			
ServerCount	An integer indicating the number of SSH servers that belong to the server group.			

## **GET SSH Server Groups Name**

The GET /SSH/ServerGroups/{name} method is used to retrieve an SSH server group with the specified name from Keyfactor Command. This method returns HTTP 200 OK on a success with details for the specified SSH server

#### group.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature:

SSH: ServerAdmin OR SSH: EnterpriseAdmin

Table 463: GET SSH Server Groups {name} Input Parameters

Name	In	Description
name	Path	Required. A string indicating the full name of the SSH server group to be retrieved.

Table 464: GET SSH Server Groups {name} Response Data

Name	In	Description		
ID	Body	A string indicating the Keyfactor Command reference GUID for the SSH server group. This GUID is automatically set by Keyfactor Command.		
Owner	Body	An object indicating the Active Directory user who owns the server group. See <i>SSH Server Groups</i> in the <i>Keyfactor Command Reference Guide</i> for more information. Owner parameters are:		
		Name	Description	
		Id	An integer indicating the Keyfactor Command reference ID of the <i>user</i> who holds the owner role on the SSH server group.	
		Username	A string indicating the username of the <i>user</i> (in DOMAIN\\username format) who holds the owner role on the SSH server group.	
GroupName	Body	A string indicating the name of the SSH server group.		
SyncSchedule	Body	An array providing the inventory schedule for the SSH server group. The schedule can be off (unset) or one of the supported values. Supported schedule values are:		
		Name	Description	
		Off	Turn off a previously configured schedule.	
		Interval	A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database.	
			Name Description	
			Minutes An integer indicating the number of minutes between each interval.	
			For example, every hour:	
			"Interval": {     "Minutes": 60 }	

Name	In	Description	า	
		Name	Description	
		Daily	A dictionary that	at indicates a job scheduled to run every day at the same parameter:
			Name	Description
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
			For example, da	aily at 11:30 pm:
			"Daily": {     "Time": }	"2022-02-25T23:30:00Z"
		Weekly		at indicates a job scheduled to run on a specific day or days the same time with the parameters:
			Name	Description
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
			Days	An array of values representing the days of the week on which to run the job. These can either be entered as integers (0 for Sunday, 1 for Monday, etc.) or as days of the week (e.g. "Sunday").
			For example, e	very Monday, Wednesday and Friday at 5:30 pm:
			"Wed: "Fri	[ day", nesday", day"
			"Time":	"2022-02-27T17:30:00Z"

Name	In	Description			
		Name	Description		
		Monthly		at indicates a job scheduled to run on a specific day or days the same time with the parameters:	
			Name	Description	
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
			Day	The number of the day, in the month, to run the job.	
		sched	For example, on the first of every month at 5:30 pm:  "Monthly": {     "Day": 1     "Time": "2022-02-27T17:30:00Z" }  Although the Swagger Example Value may show examples of various other dules, only the schedules shown here—that are available in the Management I for this functionality—are valid for this endpoint.		
		<pre>For example:  "SyncSchedule": {     "Weekly": {         "Days": [</pre>			
Under- Management	Body		dicating whether t	the SSH server group is in <i>inventory only</i> mode (False) or ode (True).	
ServerCount	Body	An integer in	dicating the numb	per of SSH servers that belong to the server group.	

### **GET SSH Server Groups Access ID**

The GET /SSH/ServerGroups/Access/{id} method is used to retrieve Linux logons for an SSH server group, along with any users or service accounts mapped to those logons, from Keyfactor Command for the specified server group GUID. This method returns HTTP 200 OK on a success with details of the logons and associated users, if applicable, for the specified SSH server group.



**Tip:** The following permissions (see Security Overview) are required to use this feature:

SSH: ServerAdmin OR SSH: EnterpriseAdmin

Table 465: GET SSH Server Groups Access {id} Input Parameters

Name	In	Description
id	Path	Required. The Keyfactor Command reference GUID for the SSH server group for which to retrieve logon and user mappings.  Use the GET /SSH/ServerGroups method (see GET SSH Server Groups on the next page) to retrieve a list of all the SSH server groups to determine the server group's ID.

Table 466: GET SSH Server Groups Access {id} Response Data

Name	Description				
ServerGroupId	The Keyfactor Command reference GUID for the SSH server group.				
LogonUsers	An array containing information for the Linux logons from the Linux server that have been stored in Keyfactor Command. Possible information includes:				
	Name Description				
	LogonName	A string indicating	the name of the Linux logon.		
		NIZ	ns only appear in the results if they exist with the same all servers in the server group.		
	Users	An array of user objects containing information about the users and/or service accounts defined in Keyfactor Command that are mapped to the Linux logon. User information includes:			
		Name	Description		
		Id	An integer indicating the Keyfactor Command reference ID of a user or service account that is associated with the logon. See SSH in the Keyfactor Command Reference Guide for more information.		
		Username	A string indicating the username of a <i>user</i> (in DOMAIN\username format) or <i>service account</i> (in username@hostname format) that is associated with the logon.		
		N/	only appear in the results if they have been mapped to ogon on all servers in the server group.		

### **GET SSH Server Groups**

The GET /SSH/ServerGroups method is used to retrieve one or more SSH server groups defined in Keyfactor Command. Results can be limited to selected server groups using filtering, and URL parameters can be used to specify paging and the level of information detail. This method returns HTTP 200 OK on a success with details for the requested SSH server groups.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature:

SSH: ServerAdmin OR



#### SSH: EnterpriseAdmin

Table 467: GET SSH Server Groups Input Parameters

Name	In	Description
queryString	Query	A string containing a query to limit the results (e.g. field1 -eq value1 AND field2 -gt value2). The default is to return all records. Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns for the same feature. For querying guidelines, refer to the Keyfactor Command Reference Guide: Using the Server Group Search. The query fields supported for this endpoint are:  • GroupId  • GroupName  • Owner (Owner ID)  • OwnerName (Username)  • EnforcePublishPolicy (Under Management) (true, false)
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>GroupName</i> .
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.

Table 468: GET SSH Server Groups Response Data

Name	Description				
ID	A string indicating the Keyfactor Command reference GUID for the SSH server group. This GUID is automatically set by Keyfactor Command.				
Owner	-	An object indicating the Active Directory user who owns the server group. See SSH Server Groups in the Keyfactor Command Reference Guide for more information. Owner parameters are:			
	Name	Description			
	Id	An integer indicating the Keyfactor Command reference ID of the <i>user</i> who holds the owner role on the SSH server group.			
	Username	A string indicating the username of the <i>user</i> (in DOMAIN\\username format) who holds the owner role on the SSH server group.			
GroupName	A string indica	ting the name of the SSH server group.			
SyncSchedule	An array providing the inventory schedule for the SSH server group. The schedule can be off (unset) or one of the supported values. Supported schedule values are:				
	Name	Description			
	Off	Turn off a previously configured schedule.			
	Interval	A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database.			
		Name Description			
		Minutes An integer indicating the number of minutes between each interval.			
		For example, every hour:			
		"Interval": {     "Minutes": 60 }			

Name	Description					
	Name	Description				
	Daily		A dictionary that indicates a job scheduled to run every day at the same time with the parameter:			
		Name	Description			
		should be given using the ISO 8601 UTC tim	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).			
		For example, o	Description  The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).  Idaily at 11:30 pm:  "2022-02-25T23:30:00Z"  The date and time to next run on a specific day or days every me time with the parameters:  Description  The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).  An array of values representing the days of the week on which to run the job. These can either be entered as integers (0 for Sunday, 1 for Monday, etc.) or as days of the week (e.g. "Sunday").  Every Monday, Wednesday and Friday at 5:30 pm:  { [ [ [ [ [ [ [ [ [ [ [ [ [ [ [ [ [ [			
		"Daily": "Time" }	{ : "2022-02-25T23:30:00Z"			
	week at the same time with the parameters:					
		Name  Description  Time  The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).				
		Days	which to run the job. These can either be entered as integers (0 for Sunday, 1 for Monday, etc.) or as days of the week			
		"Weekly": "Days": "Mor "Wee				
	Monthly	A dictionary th	nat indicates a job scheduled to run on a specific day or days every			

Name	Description				
	Name	Description			
		month at the same time with the parameters:			
		Name	Description		
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).		
		Day	The number of the day, in the month, to run the job.		
	ules, o	"Monthly":     "Day":     "Time": }  Although the Swa			
	" " ,		0T14:00:00Z"		
Under- Management	A Boolean indicating whether the SSH server group is in <i>inventory only</i> mode (False) or <i>inventory and publish policy</i> mode (True).				
ServerCount	An integer indi	icating the numbe	er of SSH servers that belong to the server group.		

### **POST SSH Server Groups**

The POST /SSH/ServerGroups method is used to create an SSH server groups defined in Keyfactor Command. This method returns HTTP 200 OK on a success with details for the new SSH server group.



 $\textbf{Tip: } The following permissions (see \underline{Security\ Overview}) are required to use this feature: \\ SSH: \underline{EnterpriseAdmin}$ 

Table 469: POST SSH Server Groups Input Parameters

Name	In	Description	1	
OwnerName	Body	Required. A string indicating the Active Directory user who owns the server group (in DOMAIN\\username format). The owner can only be set by a Keyfactor Command user with the SSH Enterprise Admin role. See SSH Server Groups in the Keyfactor Command Reference Guide for more information.  Tip: Notice that the field name and structure returned on a GET is not the same as that used on a POST and PUT for the server group owner.		
GroupName	Body	Required. A	string indicating the name of the SSH server group.	
SyncSchedule	Body		viding the inventory schedule for the SSH server group. The schedule can be rone of the supported values. Supported schedule values are:	
		Name	Description	
		Off	Turn off a previously configured schedule.	
		Interval	A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database.  Name  Description  Minutes  An integer indicating the number of minutes between each interval.  For example, every hour:  "Interval": {     "Minutes": 60   }	
		Daily	A dictionary that indicates a job scheduled to run every day at the same time with the parameter:  Name  Description  Time  The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time	

Name	In	Description	Description	
		Name	Description	
			Name	Description
				format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
			For example, o	daily at 11:30 pm:
			"Daily": "Time"; }	{ : "2022-02-25T23:30:00Z"
		Weekly		nat indicates a job scheduled to run on a specific day or days the same time with the parameters:
			Name	Description
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
			Days	An array of values representing the days of the week on which to run the job. These can either be entered as integers (0 for Sunday, 1 for Monday, etc.) or as days of the week (e.g. "Sunday").
			"Weekly": "Days": "Mor "Wee	
		Monthly		nat indicates a job scheduled to run on a specific day or days at the same time with the parameters:

Name	In	Description				
		Name	Description			
			Name	Description		
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).		
			Day	The number of the day, in the month, to run the job.		
			"Monthly": "Day": 1	<pre>For example, on the first of every month at 5:30 pm: "Monthly": {     "Day": 1     "Time": "2022-02-27T17:30:00Z" }</pre>		
		sched	Although the Swagger <i>Example Value</i> may show examples of various other ules, only the schedules shown here—that are available in the Management for this functionality—are valid for this endpoint.			
		For example:				
		],		20T14:00:00Z"		
		The default is	unset.			
Under- Management	Body			the SSH server group is in <i>inventory only</i> mode (False) or ode (True). The default is False.		

Table 470: POST SSH Server Groups Response Data

Name	Description			
ID	A string indicating the Keyfactor Command reference GUID for the SSH server group. This GUID is automatically set by Keyfactor Command.			
Owner		ating the Active Directory user who owns the server group. See SSH Server Groups in command Reference Guide for more information. Owner parameters are:		
	Name	Description		
	Id	An integer indicating the Keyfactor Command reference ID of the <i>user</i> who holds the owner role on the SSH server group.		
	Username	A string indicating the username of the <i>user</i> (in DOMAIN\\username format) who holds the owner role on the SSH server group.		
GroupName	A string indicating the name of the SSH server group.			
SyncSchedule		ling the inventory schedule for the SSH server group. The schedule can be off (unset) apported values. Supported schedule values are:		
	Name	Description		
	Off	Turn off a previously configured schedule.		
	Interval	A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database.		
		Name Description		
		Minutes An integer indicating the number of minutes between each interval.		
		For example, every hour:		
		"Interval": {     "Minutes": 60 }		

Name	Description				
	Name	Description			
	Daily		A dictionary that indicates a job scheduled to run every day at the same time with the parameter:		
		Name	Description		
		Time The date and time to next run the job. The date and should be given using the ISO 8601 UTC time formation MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:0			
		For example,	daily at 11:30 pm:		
		"Daily": "Time" }	{ : "2022-02-25T23:30:00Z"		
	Weekly		hat indicates a job scheduled to run on a specific day or days every ame time with the parameters:  Description		
		Time The date and time to next run the job. The date should be given using the ISO 8601 UTC time for	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).		
		Days	An array of values representing the days of the week on which to run the job. These can either be entered as integers (0 for Sunday, 1 for Monday, etc.) or as days of the week (e.g. "Sunday").		
		"Weekly": "Days" "Mon "Wee			
	Monthly	A dictionary tl	hat indicates a job scheduled to run on a specific day or days every		

Name	Description					
	Name	Description				
		month at the s	month at the same time with the parameters:			
		Name	Description			
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).			
		Day	The number of the day, in the month, to run the job.			
	ules, c	"Monthly":     "Day":     "Time": }  Although the Sw				
	],		20T14:00:00Z"			
Under- Management		icating whether the colicy mode (True).	he SSH server group is in <i>inventory only</i> mode (False) or <i>inventory</i>			
ServerCount	An integer ind	icating the numb	er of SSH servers that belong to the server group.			

# **PUT SSH Server Groups**

The PUT /SSH/ServerGroups method is used to update an existing SSH server groups defined in Keyfactor Command. This method returns HTTP 200 OK on a success with details for the updated SSH server group.



**Tip:** The following permissions (see Security Overview) are required to use this feature:

SSH: ServerAdmin OR SSH: EnterpriseAdmin

SSH actions are affected by ownership on the server group and limited for users with only the *ServerAdmin* role. For more information, see *SSH Permissions* in the *Keyfactor Command Reference Guide*.



Warning: Any previously populated fields that are not submitted with their full existing data using this method will be cleared of their existing data. When using this method, you should first do a GET to retrieve all the values for the record you want to update, enter corrected data into the field(s) you want to update, and then submit all the fields using PUT, including the fields that contain values but which you are not changing.

Table 471: PUT SSH Server Groups Input Parameters

Name	In	Description	1		
ID	Body	A string indicating the Keyfactor Command reference GUID for the SSH server group. This GUID is automatically set by Keyfactor Command.			
OwnerName	Body	Required. A string indicating the Active Directory user who owns the server group (in DOMAIN\\username format). The owner can only be set by a Keyfactor Command user with the SSH Enterprise Admin role. See SSH Server Groups in the Keyfactor Command Reference Guide for more information.  Tip: Notice that the field name and structure returned on a GET is not the same as that used on a POST and PUT for the server group owner.			
GroupName	Body	Required. A string indicating the name of the SSH server group.			
SyncSchedule	Body	An array providing the inventory schedule for the SSH server group. The schedule can off (unset) or one of the supported values. Supported schedule values are:			
		Name	Description		
		Off	Turn off a previously configured schedule.		
		Interval	A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database.		
			Name Description		
			Minutes An integer indicating the number of minutes between each interval.		
		Daily	For example, every hour:		
			"Interval": {     "Minutes": 60 }		
			A dictionary that indicates a job scheduled to run every day at the same time with the parameter:		

Name	In	Description			
			Description		
			Name	Description	
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
			For example, da	illy at 11:30 pm:	
			"Daily": {	"2022-02-25T23:30:00Z"	
		Weekly	A dictionary that indicates a job scheduled to run on a specific day or days every week at the same time with the parameters:		
			Name	Description	
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
			Days	An array of values representing the days of the week on which to run the job. These can either be entered as integers (0 for Sunday, 1 for Monday, etc.) or as days of the week (e.g. "Sunday").	
			"Weekly": {     "Days":     "Mond     "Wedn     "Frid	day", nesday",	
		Monthly		t indicates a job scheduled to run on a specific day or days the same time with the parameters:	

Name	In	Description			
		Name	Description		
			Name	Description	
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
			Day	The number of the day, in the month, to run the job.	
			"Monthly": "Day": 1		
		sched	dules, only the sch	ragger Example Value may show examples of various other edules shown here—that are available in the Management ality—are valid for this endpoint.	
		For example:			
		],		20T14:00:00Z"	
		The default is	unset.		
Under- Management	Body		_	he SSH server group is in <i>inventory only</i> mode (False) or ode (True). The default is False.	

Table 472: PUT SSH Server Groups Response Data

Name	In	Description	Description			
ID	Body	A string indicating the Keyfactor Command reference GUID for the SSH server group. This GUID is automatically set by Keyfactor Command.				
Owner	Body	An object indicating the Active Directory user who owns the server group. See SSH Groups in the Keyfactor Command Reference Guide for more information. Owner meters are:				
		Name	Description			
		Id	An integer indicating the Keyfactor Command reference ID of the <i>user</i> who holds the owner role on the SSH server group.			
		Username	A string indicating the username of the <i>user</i> (in DOMAIN\\username format) who holds the owner role on the SSH server group.			
GroupName	Body	A string indicating the name of the SSH server group.				
SyncSchedule	Body	An array providing the inventory schedule for the SSH server group. The schedule can be off (unset) or one of the supported values. Supported schedule values are:				
		Name	Description			
		Off	Turn off a previously configured schedule.			
		Interval	A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database.			
			Name Description			
			Minutes An integer indicating the number of minutes between each interval.			
			For example, every hour:			
			"Interval": {     "Minutes": 60 }			

Name	In	Description			
		Name	Description		
		Daily	A dictionary that	at indicates a job scheduled to run every day at the same parameter:	
			Name	Description	
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
			For example, da	aily at 11:30 pm:	
			"Daily": {     "Time": }	"2022-02-25T23:30:00Z"	
		Weekly	A dictionary that indicates a job scheduled to run on a specific day or days every week at the same time with the parameters:		
			Name	Description	
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
			Days	An array of values representing the days of the week on which to run the job. These can either be entered as integers (0 for Sunday, 1 for Monday, etc.) or as days of the week (e.g. "Sunday").	
			For example, e	very Monday, Wednesday and Friday at 5:30 pm:	
			"Wed: "Fri	[ day", nesday", day"	
			"Time":	"2022-02-27T17:30:00Z"	

Name	In	Description	Description			
		Name	Name Description			
		Monthly		at indicates a job scheduled to run on a specific day or days the same time with the parameters:		
			Name	Description		
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).		
			Day	The number of the day, in the month, to run the job.		
		₩ sched	"Monthly":     "Day":     "Time": }  : Although the Sodules, only the school for this function			
		],	edule": {	20T14:00:00Z"		
Under- Management	Body		dicating whether dipublish policy m	the SSH server group is in <i>inventory only</i> mode (False) or ode (True).		
ServerCount	Body	An integer in	dicating the numb	per of SSH servers that belong to the server group.		

#### **DELETE SSH Server Groups Access**

The DELETE /SSH/ServerGroups/Access method is used to remove a mapping of one or more Linux logons to Keyfactor Command users or service accounts for one or more SSH server groups. This method returns HTTP 200 OK on a success with details of the logons and associated users, if applicable, for the specified SSH server group(s).



**Tip:** The following permissions (see Security Overview) are required to use this feature:

SSH: ServerAdmin OR SSH: EnterpriseAdmin

SSH actions are affected by ownership on the server group and limited for users with only the *ServerAdmin* role. For more information, see *SSH Permissions* in the *Keyfactor Command Reference Guide*.



**Tip:** Before deleting a logon to user mapping, be sure that you have switched the server group from which you will removing your mapping to *inventory and publish policy* mode so that the key for the user will be removed from the servers in the server group. If the server group is in *inventory only* mode and you remove a mapping for it in Keyfactor Command, the mapping will be removed in Keyfactor Command only and the key for the user will not be removed from the servers.

Table 473: DELETE SSH Server Groups Access Input Parameters

Name	In	Description				
ServerGroupId	Body	Required. The Keyfa	Required. The Keyfactor Command reference ID for the SSH server group.			
LogonUsers	Body	An array containing ation should be inclu	information for the Linux logon(s) to update. The following informuded:			
		Name	Description			
		LogonName	A string indicating the name of the Linux logon.			
		Users	An array of strings indicating the user names of one or more users (in DOMAIN\\username format) or service accounts (in username@hostname format) to be removed from association with the logon.			
		For example:				
		<pre>"LogonUsers": [      {          "LogonName": "johns",          "Users": [                 "KEYEXAMPLE\\jsmith"          ]     } ]</pre>				

Table 474: DELETE SSH Server Groups Access {id} Response Data

Name	Description				
ServerGroupId	The Keyfactor Comr	nand reference GUID	for the SSH server group.		
LogonUsers	An array containing information for the Linux logons from the Linux server that have been Keyfactor Command. Possible information includes:				
	Name	Description			
	LogonName	A string indicating	the name of the Linux logon.		
		Tip: Logons only appear in the results if they exist with the same spelling on all servers in the server group.			
	Users	An array of user objects containing information about the users and/or service accounts defined in Keyfactor Command that are mapped to the Linux logon. User information includes:			
		Name	Description		
		Id	An integer indicating the Keyfactor Command reference ID of a user or service account that is associated with the logon. See SSH in the Keyfactor Command Reference Guide for more information.		
		Username	A string indicating the username of a <i>user</i> (in DOMAIN\username format) or <i>service account</i> (in username@hostname format) that is associated with the logon.		
			s only appear in the results if they have been mapped to logon on all servers in the server group.		

## **POST SSH Server Groups Access**

The POST /SSH/ServerGroups/Access method is used to create a mapping of one or more Linux logons to Keyfactor Command users or service accounts for one or more SSH server groups. This method returns HTTP 200 OK on a success with details of the logons and associated users, if applicable, for the specified SSH server group(s).



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature:

SSH: ServerAdmin OR SSH: EnterpriseAdmin



SSH actions are affected by ownership on the server group and limited for users with only the *ServerAdmin* role. For more information, see *SSH Permissions* in the *Keyfactor Command Reference Guide*.



**Tip:** Before creating a logon to user mapping, be sure that you have switched the server group to which you will add your mapping to *inventory and publish policy* mode so that the key for the user will be published to the servers in the group. If the server group is in *inventory only* mode and you add a mapping for it in Keyfactor Command, the mapping will appear in Keyfactor Command only and the key for the user will not be published out to the servers.

Table 475: POST SSH Server Groups Access Input Parameters

Name	In	Description			
ServerGroupId	Body	Required. The Keyfactor Command reference ID for the SSH server group.			
LogonUsers	Body	<b>Required</b> . An array containing information for the Linux logon(s) to update. The following information should be included:			
		Name	Description		
		LogonName	A string indicating the name of the Linux logon.		
		Users	An array of strings indicating the user names of one or more users (in DOMAIN\\username format) or service accounts (in username@hostname format) to be associated with the logon.		
		For example:			
		"LogonUsers": [ {          "LogonName": "johns",          "Users": [			

Table 476: POST SSH Server Groups Access {id} Response Data

Name	Description				
ServerGroupId	The Keyfactor Comr	nand reference GUID	for the SSH server group.		
LogonUsers	An array containing information for the Linux logons from the Linux server that have been Keyfactor Command. Possible information includes:				
	Name	Description			
	LogonName	A string indicating	the name of the Linux logon.		
		Tip: Logons only appear in the results if they exist with the same spelling on all servers in the server group.			
	Users	An array of user objects containing information about the users and/or service accounts defined in Keyfactor Command that are mapped to the Linux logon. User information includes:			
		Name	Description		
		Id	An integer indicating the Keyfactor Command reference ID of a user or service account that is associated with the logon. See SSH in the Keyfactor Command Reference Guide for more information.		
		Username	A string indicating the username of a <i>user</i> (in DOMAIN\username format) or <i>service account</i> (in username@hostname format) that is associated with the logon.		
			s only appear in the results if they have been mapped to logon on all servers in the server group.		

### 2.2.25.5 SSH Service Accounts

The SSH Service Accounts component of the Keyfactor Web APIs includes methods necessary to retrieve, create, update, rotate and delete service accounts and associated keys in Keyfactor Command.

Table 477: SSH Service Accounts Endpoints

Endpoint	Method	Description	Link
/{id}	DELETE	Deletes the SSH service account with the specified ID.	DELETE SSH Service Accounts ID below
/{id}	GET	Returns the SSH service account with the specified ID.	GET SSH Service Accounts ID on page 1024
/Key/{id}	GET	Returns the public key and optional private key of an SSH service account with the specified ID.	GET SSH Service Accounts Key ID on page 1030
/	DELETE	Deletes one or more SSH service accounts with the specified IDs.	DELETE SSH Service Accounts on page 1033
/	GET	Returns a list of SSH service accounts based on the specified filters.	GET SSH Service Accounts on page 1036
/	POST	Creates a new SSH service account.	POST SSH Service Accounts on page 1043
/	PUT	Updates an existing SSH service account.	PUT SSH Service Accounts on page 1052
/Rotate/{id}	POST	Generates a new key pair for an existing service account.	POST SSH Service Accounts Rotate ID on page 1059

#### **DELETE SSH Service Accounts ID**

The DELETE /SSH/ServiceAccounts/{id} method is used to delete an SSH service account in Keyfactor Command, including its SSH key pair. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature:

SSH: ServerAdmin OR SSH: EnterpriseAdmin

Name	In	Description
Name id	In Path	Required. An integer indicating the Keyfactor Command reference ID for the SSH service account to be deleted.  Use the GET /SSH/ServiceAccounts method (see GET SSH Service Accounts on page 1036) to retrieve a list of all the SSH service accounts to determine the service account's ID.  Tip: Be sure to use the ID of the service account itself and not the ID of the service account user or service account's key within the service account. For example, notice the following record returned from a GET /SSH/ServiceAccounts:  {     "Id": 2,     "ClientHostname": "appsrvr80.keyexample.com",     "ServerGroup": {         "Id": "603d3d4c-89dd-4ab8-92e1-8e83db3d5546",         "GroupName": "Server Group Two",         "UnderManagement": false     },     "User": {
		<pre>"User": {     "Id": 7,     "Key": {         "Id": 36,         "Fingerprint":     "kwuo2k3Ej7wFVMLhI3g+rxt2qXwGp7qcvzdBjVTDHNg=",         "PublicKey": "ssh-rsa     AAAAB3NzaC1yc2EAAAADAQABAAABAQCAln+t [truncated for display]",         "KeyType": "RSA",         "KeyLength": 2048,         "CreationDate": "2020-11-17T17:53:55.68",         "Email": "pkiadmins@keyexample.com",         "Comments": [         "Access App Two"</pre>
		TLogonCount": 3

### **GET SSH Service Accounts ID**

The GET /SSH/ServiceAccounts/{id} method is used to retrieve an SSH service account from Keyfactor Command. This method returns HTTP 200 OK on a success with details for the requested SSH service account and its public key. To return the SSH private key, use the GET /SSH/ServiceAccounts/Key/{id} method (see GET SSH Service Accounts Key ID on page 1030).



**Tip:** The following permissions (see Security Overview) are required to use this feature:

SSH: ServerAdmin OR SSH: EnterpriseAdmin

Table 479: GET SSH Service Accounts {id} Input Parameters

Name	In	Description
id	Path	Required. An integer indicating the Keyfactor Command reference ID for the SSH service account to be retrieved.  Use the GET /SSH/ServiceAccounts method (see GET SSH Service Accounts on page 1036) to retrieve a list of all the SSH service accounts to determine the service account's ID.

Table 480: GET SSH Service Accounts {id} Response Data

Name	Description					
ID	The Keyfactor Comr	e Keyfactor Command reference ID for the SSH service account. This ID is automatically set by Keyfactor mmand.				
ClientHost- name	A string indicating the client hostname reference for the service account key. This field is used for reference only and does not need to match an actual client hostname. It is used when building the full user name of the service account key for mapping to Linux logons for publishing to Linux servers (e.g. username@client_hostname). The naming convention is to enter the hostname of the server on which the application that will use the private key resides (e.g. appsrvr12), but you can put anything you like in this field (e.g. cheesetoast).					
ServerGroup	An array that indicates the SSH server group for the service account. The server group is used to control who has access in Keyfactor Command to the service account key. It does not limit where the key can be published. See SSH Permissions in the Keyfactor Command Reference Guide for more information. Server group information includes:					
	Name	Description				
	Id	A string indicating the Keyfactor Command reference GUID of the SSH server group.				
	Owner	An object indicating the Active Directory user who owns the server group. See <i>SSH</i> Server Groups in the Keyfactor Command Reference Guide for more information.				
		Name Description				
		Id An integer indicating the Keyfactor Command reference ID of the <i>user</i> who holds the owner role on the SSH server group.				
	GroupName	A string indicating the name of the SSH server group.				
	SyncSchedule	An array providing the inventory schedule for the SSH server group. The schedule can be off (unset) or one of the supported values. Supported schedule values are:				
		Name Description				
		Off Turn off a previously configured schedule.				

Name	Description		
	Name	Description	n
		Name	Description
		Interval	A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database.
			Name Description
			Minutes An integer indicating the number of minutes between each interval.
			For example, every hour:
			"Interval": {     "Minutes": 60 }
		Daily	A dictionary that indicates a job scheduled to run every day at the same time with the parameter:
			Name Description
			Time The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
			For example, daily at 11:30 pm:
			"Daily": {     "Time": "2022-02-25T23:30:00Z" }
		Weekly	A dictionary that indicates a job scheduled to run on a specific day or days every week at the same time with the parameters:

Name	Description			
	Name	Description	n	
		Name	Description	
			Name	Description
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
			Days	An array of values representing the days of the week on which to run the job. These can either be entered as integers (0 for Sunday, 1 for Monday, etc.) or as days of the week (e.g. "Sunday").
			For example, ev	ery Monday, Wednesday and Friday at 5:30 pm:
			"Frid	[ day", desday",
		Monthl-		t indicates a job scheduled to run on a specific day onth at the same time with the parameters:
			Name	Description
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:m-m:ss.000Z (e.g. 2021-05-19T16:23:01Z).
			Day	The number of the day, in the month, to run the job.
			For example, on	the first of every month at 5:30 pm:

Name	Description				
	Name	Description	Description		
		Name	Description		
			"Monthly": {     "Day": 1     "Time": "2022-02-27T17:30:00Z" }		
		Note: Although the Swagger Example Value may show examples of various other schedules, only the schedules shown here—that are available in the Management Portal for this functionality—are valid for this endpoint.			
	Under- Management		dicating whether the SSH server group is in <i>inventory only</i> mode entory and publish policy mode (True).		
User	An array containing information about the service account user. Service account user details include:				
	Name	Description			
	Id	An integer indicating the Keyfactor Command reference ID of the SSH service account user.			
	Key	An array containi details include:	ing information about the key for the service account user. Key		
		Name	Description		
		Id	An integer indicating the Keyfactor Command reference ID of the SSH service account's key.		
		Fingerprint	A string indicating the fingerprint of the public key. Each SSH public key has a single cryptographic fingerprint that can be used to uniquely identify the key.		
		PublicKey	A string indicating the public key of the key pair for the SSH service account.		
		КеуТуре	A string indicating the cryptographic algorithm used to		

Name	Description			
	Name	Description		
		Name	Description	
			generate the SSH key. Possible values are:  RSA ECDSA Ed25519	
		KeyLength	An integer indicating the key length for the SSH key. The key length supported depends on the key type selected.  Keyfactor Command supports 256 bits for Ed25519 and ECDSA and 2048 or 4096 bits for RSA.	
		CreationDate	The date, in UTC, on which the SSH key pair was created.	
		StaleDate	The date, in UTC, after which the SSH key pair is considered to be out of date based on the key lifetime defined by the Key Lifetime (days) application setting. See Application Settings: SSH Tab in the Keyfactor Command Reference Guide for more information.	
			Email	A string containing the email address of the administrator or group of administrators responsible for managing the key. This email address is used to alert the administrator or group of administrators when the key pair is approaching the end of its lifetime.
		Comments	An array containing one or more strings with the user-defined descriptive comments, if any, on the key. Although entry of an email address in the comment field of an SSH key is traditional, this is not a required format. The comment may can contain any characters supported for string fields, including spaces and most punctuation marks. Keys created through the Keyfactor Command Management Portal or with the POST /SSH/ServiceAccounts method will contain only one string in the array.	
		LogonCount	An integer indicating the number of Linux logons associated with the SSH key pair.	
Username			the service account. The username is made up of the user name service account is created (e.g. myapp@appsrvr75).	

Name	Description
LogonIds	An array of integers indicating the Keyfactor Command reference IDs of Linux logons that are associated with the service account in order to publish the service account's public key to the servers on which the logons are located.

# **GET SSH Service Accounts Key ID**

The GET /SSH/ServiceAccounts/Key/{id} method is used to retrieve the key information for an SSH service account from Keyfactor Command. This method returns HTTP 200 OK on a success with details for the requested SSH service account key, including optional private key.



**Tip:** The following permissions (see Security Overview) are required to use this feature:

SSH: ServerAdmin OR SSH: EnterpriseAdmin

Table 481: GET SSH Service Accounts Key {id} Input Parameters

Name	In	Description
id	Path	Required. The Keyfactor Command reference ID for the SSH service account key for which to retrieve key information.  Use the GET /SSH/ServiceAccounts method (see GET SSH Service Accounts on page 1036) to retrieve a list of all the SSH service accounts to determine the service account's key ID.  Tip: Be sure to use the ID of the service account's key and not the ID of
		the service account itself or the service account user. For example, notice the following record returned from a GET /SSH/ServiceAccounts:  {
		<pre>"Id": 2,  "ClientHostname": "appsrvr80.keyexample.com",  "ServerGroup": {</pre>
		"Id": "603d3d4c-89dd-4ab8-92e1-8e83db3d5546", "GroupName": "Server Group Two", "UnderManagement": false
		}, "User": {
		"Id": 7, "Key": { "Id": 36,
		"Fingerprint": "kwuo2k3Ej7wFVMLhI3g+rxt2qXwGp7qcvzdBjVTDHNg=", "PublicKey": "ssh-rsa
		AAAAB3NzaC1yc2EAAAADAQABAAABAQCAln+t [truncated for display]",
		"KeyType": "RSA", "KeyLength": 2048, "CreationDate": "2020-11-17T17:53:55.68",
		"Email": "pkiadmins@keyexample.com", "Comments": [
		"Access App Two" ], "LogonCount": 3
		}, "Username": "svc_
		<pre>access2@appsrvr80.keyexample.com" } }</pre>
		It contains three IDs:
		<ul><li>ID 2: The service account's ID.</li><li>ID 7: The service account user's ID.</li></ul>

Name	In	Description	
		• ID 36: The ID of the service account user's key. Use this one to request the key.	
IncludePrivateKey	Query	A Boolean that sets whether to include the private key of the SSH key pair in the response (True) or not (False). The default is <i>False</i> . If set to True, the X-Keyfactor-Key-Passphrase header must be supplied.	

Table 482: GET SSH Service Accounts Key {id} Response Data

Name	Description
ID	The Keyfactor Command reference ID for the SSH service account. This ID is automatically set by Keyfactor Command.
Fingerprint	A string indicating the fingerprint of the public key. Each SSH public key has a single cryptographic fingerprint that can be used to uniquely identify the key.
PublicKey	A string indicating the public key of the key pair for the SSH service account.
PrivateKey	A string indicating the private key of the key pair for the SSH service account.
КеуТуре	A string indicating the cryptographic algorithm used to generate the SSH key. Possible values are:  • RSA  • ECDSA  • Ed25519
KeyLength	An integer indicating the key length for the SSH key. The key length supported depends on the key type selected. Keyfactor Command supports 256 bits for Ed25519 and ECDSA and 2048 or 4096 bits for RSA.
CreationDate	The date, in UTC, on which the SSH key pair was created.
StaleDate	The date, in UTC, after which the SSH key pair is considered to be out of date based on the key life-time defined by the <i>Key Lifetime (days)</i> application setting. See the <u>Application Settings: SSH Tab</u> section of the <i>Keyfactor Command Reference Guide</i> for more information.
Email	A string containing the email address of the administrator or group of administrators responsible for managing the key. This email address is used to alert the administrator or group of administrators when the key pair is approaching the end of its lifetime.
Comments	An array containing one or more strings with the user-defined descriptive comments, if any, on the key. Although entry of an email address in the comment field of an SSH key is traditional, this is not a required format. The comment may can contain any characters supported for string fields, including spaces and most punctuation marks. Keys created through the Keyfactor Command Management Portal or with the POST /SSH/ServiceAccounts method will contain only one string in the array.
LogonCount	An integer indicating the number of Linux logons associated with the SSH key pair.

## **DELETE SSH Service Accounts**

The DELETE /SSH/ServiceAccounts method is used to delete one or more SSH service accounts in Keyfactor Command, including their SSH key pairs. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature:

SSH: ServerAdmin OR SSH: EnterpriseAdmin

### **GET SSH Service Accounts**

The GET /SSH/ServiceAccounts method is used to retrieve one or more SSH service accounts defined in Keyfactor Command. Results can be limited to selected service accounts using filtering, and URL parameters can be used to specify paging and the level of information detail. This method returns HTTP 200 OK on a success with details for the requested SSH service accounts and their public keys. To return the SSH private key, use the GET /SSH/ServiceAccounts/Key/{id} method (see GET SSH Service Accounts Key ID on page 1030).



Tip: The following permissions (see Security Overview) are required to use this feature:

SSH: ServerAdmin OR SSH: EnterpriseAdmin

Table 484: GET SSH Service Accounts Input Parameters

Name	In	Description
queryString	Query	A string containing a query to limit the results (e.g. field1 -eq value1 AND field2 -gt value2). The default is to return all records. Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns for the same feature. For querying guidelines, refer to the Keyfactor Command Reference Guide: Using the Service Account Key Search. The query fields supported for this endpoint are:  • CreationDate  • Id  • Comments (Key comments)  • KeyLength  • KeyType  • ServerGroup (Server Group ID)  • ServerGroupName  • Username
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>Username</i> .
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.

Table 485: GET SSH Service Accounts Response Data

Name	Description				
ID	The Keyfactor Comr	and reference ID for the SSH service account. This ID is automatically set by Keyfactor			
ClientHost- name	ence only and does name of the service name@client_hostr application that will	string indicating the client hostname reference for the service account key. This field is used for reference only and does not need to match an actual client hostname. It is used when building the full user ame of the service account key for mapping to Linux logons for publishing to Linux servers (e.g. userame@client_hostname). The naming convention is to enter the hostname of the server on which the oplication that will use the private key resides (e.g. appsrvr12), but you can put anything you like in this celd (e.g. cheesetoast).			
ServerGroup	who has access in K	tes the SSH server group for the service account. The server group is used to control eyfactor Command to the service account key. It does not limit where the key can be Permissions in the Keyfactor Command Reference Guide for more information. Server ncludes:			
	Name	Description			
	Id	A string indicating the Keyfactor Command reference GUID of the SSH server group.			
	Owner	An object indicating the Active Directory user who owns the server group. See SSH Server Groups in the Keyfactor Command Reference Guide for more information.			
		Name Description			
		Id An integer indicating the Keyfactor Command reference ID of the <i>user</i> who holds the owner role on the SSH server group.			
	GroupName	A string indicating the name of the SSH server group.			
	SyncSchedule	An array providing the inventory schedule for the SSH server group. The schedule can be off (unset) or one of the supported values. Supported schedule values are:			
		Name Description			
		Off Turn off a previously configured schedule.			

Name	Description		
	Name	Description	
		Name	Description
		Interval	A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database.
			Name Description
			Minutes An integer indicating the number of minutes between each interval.
		For example, every hour:	
			"Interval": {     "Minutes": 60 }
		Daily	A dictionary that indicates a job scheduled to run every day at the same time with the parameter:
			Name Description
			Time  The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
			For example, daily at 11:30 pm:
			"Daily": {     "Time": "2022-02-25T23:30:00Z" }
		Weekly	A dictionary that indicates a job scheduled to run on a specific day or days every week at the same time with the parameters:

Name	Description				
	Name	Description	n		
		Name	Description		
			Name	Description	
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
			Days	An array of values representing the days of the week on which to run the job. These can either be entered as integers (0 for Sunday, 1 for Monday, etc.) or as days of the week (e.g. "Sunday").	
			For example, ev	ery Monday, Wednesday and Friday at 5:30 pm:	
			"Fric	[ day", nesday",	
		Monthl-		t indicates a job scheduled to run on a specific day onth at the same time with the parameters:	
			Name	Description	
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:m-m:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
			Day	The number of the day, in the month, to run the job.	
			For example, or	the first of every month at 5:30 pm:	

Name	Description				
	Name	Description			
		Name	Description		
			"Monthly": {     "Day": 1     "Time": "2022-02-27T17:30:00Z" }		
		variou able ii	Note: Although the Swagger Example Value may show examples of various other schedules, only the schedules shown here—that are available in the Management Portal for this functionality—are valid for this endpoint.		
	Under- Management		A Boolean indicating whether the SSH server group is in <i>inventory only</i> mode (False) or <i>inventory and publish policy</i> mode (True).		
User	An array contain	ing information abo	out the service account user. Service account user details include:		
	Name	Description	Description		
	Id	An integer indicat user.	An integer indicating the Keyfactor Command reference ID of the SSH service account user.		
	Key	An array containing details include:	ng information about the key for the service account user. Key		
		Name	Description		
		Id	An integer indicating the Keyfactor Command reference ID of the SSH service account's key.		
		Fingerprint	A string indicating the fingerprint of the public key. Each SSH public key has a single cryptographic fingerprint that can be used to uniquely identify the key.		
		PublicKey	A string indicating the public key of the key pair for the SSH service account.		
		КеуТуре	A string indicating the cryptographic algorithm used to		

Name	Description			
	Name	Description		
		Name	Description	
			generate the SSH key. Possible values are:  RSA ECDSA Ed25519	
		KeyLength	An integer indicating the key length for the SSH key. The key length supported depends on the key type selected.  Keyfactor Command supports 256 bits for Ed25519 and ECDSA and 2048 or 4096 bits for RSA.	
		CreationDate	The date, in UTC, on which the SSH key pair was created.	
		StaleDate	The date, in UTC, after which the SSH key pair is considered to be out of date based on the key lifetime defined by the Key Lifetime (days) application setting. See Application Settings: SSH Tab in the Keyfactor Command Reference Guide for more information.	
		Email	A string containing the email address of the administrator or group of administrators responsible for managing the key. This email address is used to alert the administrator or group of administrators when the key pair is approaching the end of its lifetime.	
		Comments	An array containing one or more strings with the user-defined descriptive comments, if any, on the key. Although entry of an email address in the comment field of an SSH key is traditional, this is not a required format. The comment may can contain any characters supported for string fields, including spaces and most punctuation marks. Keys created through the Keyfactor Command Management Portal or with the POST /SSH/ServiceAccounts method will contain only one string in the array.	
		LogonCount	An integer indicating the number of Linux logons associated with the SSH key pair.	
Username			the service account. The username is made up of the user name service account is created (e.g. myapp@appsrvr75).	

#### **POST SSH Service Accounts**

The POST /SSH/ServiceAccounts method is used to create a new SSH service account in Keyfactor Command. This method returns HTTP 200 OK on a success with details for the new SSH service account.

Before adding a new SSH service account, be sure that you have added at least one server group (see <u>POST SSH Server Groups on page 1003</u>) and that your Keyfactor Bash Orchestrator has been registered and approved in Keyfactor Command (see GET Agents on page 12).



**Tip:** The following permissions (see Security Overview) are required to use this feature:

SSH: ServerAdmin OR SSH: EnterpriseAdmin

Table 486: POST SSH Service Accounts Input Parameters

Name	In	Description					
KeyGenerationRequest	Body		<b>Required</b> . An array that set the information to include in the SSH key pair request. Key generation request details include:				
		Name	Description				
		КеуТуре	<b>Required</b> . A string indicate algorithm used to generable values are:				
			Numeric Value	Text Value			
			1	ECDSA			
			2	Ed25519			
			3	RSA			
			The KeyType may be spenumeric value or text va				
		PrivateKeyFormat	Required. A string indicating the format to for the downloadable private key. Possible values are:				
			Numeric Value	Text Value			
			1	OpenSSH			
			2	PKCS8			
			The <i>PrivateKeyFormat</i> neither the numeric value				
		KeyLength	Required*. An integer in for the SSH key. The key depends on the key type Command supports 256 ECDSA and 2048 or 4096 is optional if the <i>KeyTyp</i> Ed25519 and required it RSA.	e length supported e selected. Keyfactor bits for Ed25519 and 6 bits for RSA. This field e is set to ECDSA or			

Name	In	Description	Description		
		Name	Description		
		Email	Required. A string containing the email address of the administrator or group of administrators responsible for managing the key. This email address is used to alert the administrator or group of administrators when the key pair is approaching the end of its lifetime.		
		Password	<b>Required</b> . A string that sets a password used to secure the private key of the SSH key pair for download.		
		Comment	A string containing the user-defined descriptive comment, if any, on the key. Although entry of an email address in the comment field of an SSH key is traditional, this is not a required format. The comment may can contain any characters supported for string fields, including spaces and most punctuation marks.		
User	Body	<b>Required</b> . An array containing information about the service account user. User details include:			
		Name	Description		
		Username	<b>Required</b> . A string indicating the short name of the SSH service account user (e.g. myapp). This, together with the <i>ClientHostname</i> , is used to build the full user name (e.g. myapp@appsrvr75).		
		LogonIds	An array of integers indicating the Keyfactor Command reference IDs of Linux logons that should be associated with the service account in order to publish the service account's public key to the servers on which the logons are located.		
Client Hostname	Body	Required. A string indicating the client hostname reference for the service account key. This field is used for reference only and does not need to match an actual client hostname. It is used when building the full user name of the service account key for mapping to Linux logons for publishing to Linux servers (e.g. username@client_hostname). The naming convention is to use the hostname of the server on which the application that will use the private key resides (e.g. appsrvr12), but you can put anything you like in this field (e.g. cheesetoast).			

Name	In	Description
ServerGroupId	Body	<b>Required</b> . A string indicating the Keyfactor Command reference GUID for the SSH server group for the service account. The server group is used to control who has access in Keyfactor Command to the service account key. It does not limit where the key can be published. See <i>SSH Permissions</i> in the <i>Keyfactor Command Reference Guide</i> for more information.

Table 487: POST SSH Service Accounts Response Data

Name	Description			
ID	The Keyfactor Comr	and reference ID for the SSH service account. This ID is automatically set by Keyfactor		
ClientHost- name	ence only and does name of the service name@client_hostr	the client hostname reference for the service account key. This field is used for reference to match an actual client hostname. It is used when building the full user account key for mapping to Linux logons for publishing to Linux servers (e.g. userame). The naming convention is to enter the hostname of the server on which the use the private key resides (e.g. appsrvr12), but you can put anything you like in this st).		
ServerGroup	who has access in K	tes the SSH server group for the service account. The server group is used to control eyfactor Command to the service account key. It does not limit where the key can be <i>Permissions</i> in the <i>Keyfactor Command Reference Guide</i> for more information. Server ncludes:		
	Name	Description		
	Id	A string indicating the Keyfactor Command reference GUID of the SSH server group.		
	Owner	An object indicating the Active Directory user who owns the server group. See <i>SSH</i> Server Groups in the Keyfactor Command Reference Guide for more information.		
		Name Description		
		Id An integer indicating the Keyfactor Command reference ID of the <i>user</i> who holds the owner role on the SSH server group.		
	GroupName	A string indicating the name of the SSH server group.		
	SyncSchedule	An array providing the inventory schedule for the SSH server group. The schedule can be off (unset) or one of the supported values. Supported schedule values are:		
		Name Description		
		Off Turn off a previously configured schedule.		

Name	Description		
	Name	Description	n
		Name	Description
		Interval	A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database.
			Name Description
			Minutes An integer indicating the number of minutes between each interval.
			For example, every hour:
			"Interval": {     "Minutes": 60 }
		Daily	A dictionary that indicates a job scheduled to run every day at the same time with the parameter:
			Name Description
			Time The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
			For example, daily at 11:30 pm:
			"Daily": {     "Time": "2022-02-25T23:30:00Z" }
		Weekly	A dictionary that indicates a job scheduled to run on a specific day or days every week at the same time with the parameters:

Name	Description				
	Name	Description	n		
		Name	Description		
			Name	Description	
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
		Days	An array of values representing the days of the week on which to run the job. These can either be entered as integers (0 for Sunday, 1 for Monday, etc.) or as days of the week (e.g. "Sunday").		
			For example, ev	ery Monday, Wednesday and Friday at 5:30 pm:	
		Monthl-	"Frid	[ day", mesday",	
				t indicates a job scheduled to run on a specific day onth at the same time with the parameters:	
			Name	Description	
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
			Day	The number of the day, in the month, to run the job.	
			For example, on	the first of every month at 5:30 pm:	

Name	Description			
	Name	Description	Description	
		Name	Description	
			"Monthly": {     "Day": 1     "Time": "2022-02-27T17:30:00Z" }	
		Note: Although the Swagger Example Value may show examples of various other schedules, only the schedules shown here—that are available in the Management Portal for this functionality—are valid for this endpoint.		
	Under- A Boolean indicating whether the SSH server group is in <i>inventory only</i> mode (True).			
User	An array contain	rray containing information about the service account user. Service account user details include:		
	Name	Description		
	Id	An integer indicating the Keyfactor Command reference ID of the SSH service account user.		
	Key	An array containi details include:	ng information about the key for the service account user. Key	
		Name	Description	
		Id	An integer indicating the Keyfactor Command reference ID of the SSH service account's key.	
		Fingerprint	A string indicating the fingerprint of the public key. Each SSH public key has a single cryptographic fingerprint that can be used to uniquely identify the key.	
		PublicKey	A string indicating the public key of the key pair for the SSH service account.	
		КеуТуре	A string indicating the cryptographic algorithm used to	

Name	Description			
	Name	Description		
		Name	Description	
			generate the SSH key. Possible values are:  RSA ECDSA Ed25519	
		KeyLength	An integer indicating the key length for the SSH key. The key length supported depends on the key type selected.  Keyfactor Command supports 256 bits for Ed25519 and ECDSA and 2048 or 4096 bits for RSA.	
		CreationDate	The date, in UTC, on which the SSH key pair was created.	
		StaleDate	The date, in UTC, after which the SSH key pair is considered to be out of date based on the key lifetime defined by the Key Lifetime (days) application setting. See Application Settings: SSH Tab in the Keyfactor Command Reference Guide for more information.	
		Email	A string containing the email address of the administrator or group of administrators responsible for managing the key. This email address is used to alert the administrator or group of administrators when the key pair is approaching the end of its lifetime.	
		Comments	An array containing one or more strings with the user-defined descriptive comments, if any, on the key. Although entry of an email address in the comment field of an SSH key is traditional, this is not a required format. The comment may can contain any characters supported for string fields, including spaces and most punctuation marks. Keys created through the Keyfactor Command Management Portal or with the POST /SSH/ServiceAccounts method will contain only one string in the array.	
		LogonCount	An integer indicating the number of Linux logons associated with the SSH key pair.	
Username	A string indicating the full username of the service account. The username is made up of the user name and <i>ClientHostname</i> entered when the service account is created (e.g. myapp@appsrvr75).			

Name	Description
Logonids	An array of integers indicating the Keyfactor Command reference IDs of Linux logons that are associated with the service account in order to publish the service account's public key to the servers on which the logons are located.

#### **PUT SSH Service Accounts**

The PUT /SSH/ServiceAccounts method is used to update an existing SSH service account in Keyfactor Command. This method returns HTTP 200 OK on a success with details for the SSH service account.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature:

SSH: ServerAdmin OR SSH: EnterpriseAdmin

SSH actions are affected by ownership on the server group with which the key is associated and limited for users with only the ServerAdmin role. For more information, see SSH Permissions in the Keyfactor Command Reference Guide.



Warning: Any previously populated fields that are not submitted with their full existing data using this method will be cleared of their existing data. When using this method, you should first do a GET to retrieve all the values for the record you want to update, enter corrected data into the field(s) you want to update, and then submit all the fields using PUT, including the fields that contain values but which you are not changing.

Table 488: PUT SSH Service Accounts Input Parameters

Name	In	Description		
KeyUpdateRequest	Body	<b>Required</b> . An array that sets the information to include in the SSH service account key update request. Key update request information includes:		
		Name	Description	
		Id	<b>Required</b> . The Keyfactor Command reference ID for the service account's key.	
		Email	<b>Required</b> . A string containing the email address of the administrator or group of administrators responsible for managing the key. This email address is used to alert the administrator or group of administrators when the key pair is approaching the end of its lifetime.	
		Comment	An string containing the user-defined descriptive comment, if any, on the key. Although entry of an email address in the comment field of an SSH key is traditional, this is not a required format. The comment may can contain any characters supported for string fields, including spaces and most punctuation marks.	
Id	Body	Required. The Keyfactor Command reference ID for the service account.  Use the GET /SSH/ServiceAccounts method (see GET SSH Service Accounts on page 1036) to retrieve a list of all the SSH service accounts to determine the service account's ID.		

Table 489: PUT SSH Service Accounts Response Data

Name	Description			
ID	The Keyfactor Command reference ID for the SSH service account. This ID is automatically set by Keyfactor Command.			
ClientHost- name	A string indicating the client hostname reference for the service account key. This field is used for reference only and does not need to match an actual client hostname. It is used when building the full user name of the service account key for mapping to Linux logons for publishing to Linux servers (e.g. username@client_hostname). The naming convention is to enter the hostname of the server on which the application that will use the private key resides (e.g. appsrvr12), but you can put anything you like in this field (e.g. cheesetoast).			
ServerGroup	An array that indicates the SSH server group for the service account. The server group is use who has access in Keyfactor Command to the service account key. It does not limit where the published. See SSH Permissions in the Keyfactor Command Reference Guide for more inform group information includes:			
	Name	Description		
	Id	A string indicating the Keyfactor Command reference GUID of the SSH server group.		
	Owner	•	icating the Active Directory user who owns the server group. See SSH in the Keyfactor Command Reference Guide for more information.	
		Name	Description	
		Id	An integer indicating the Keyfactor Command reference ID of the <i>user</i> who holds the owner role on the SSH server group.	
	GroupName	A string indicating the name of the SSH server group.		
	SyncSchedule	An array providing the inventory schedule for the SSH server group. The schedule can be off (unset) or one of the supported values. Supported schedule values are:		
		Name	Description	
		Off	Turn off a previously configured schedule.	

Name	Description		
	Name	Description	
		Name	Description
		Interval	A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database.
			Name Description
			Minutes An integer indicating the number of minutes between each interval.
			For example, every hour:
			"Interval": {     "Minutes": 60 }
		Daily	A dictionary that indicates a job scheduled to run every day at the same time with the parameter:
			Name Description
			Time The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
			For example, daily at 11:30 pm:
			"Daily": {     "Time": "2022-02-25T23:30:00Z" }
		Weekly	A dictionary that indicates a job scheduled to run on a specific day or days every week at the same time with the parameters:

Name	Description	Description			
	Name	Description			
		Name	Description		
			Name	Description	
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
			Days	An array of values representing the days of the week on which to run the job. These can either be entered as integers (0 for Sunday, 1 for Monday, etc.) or as days of the week (e.g. "Sunday").	
			For example, ev	ery Monday, Wednesday and Friday at 5:30 pm:	
			"Frid	[ day", desday",	
		Monthl-		t indicates a job scheduled to run on a specific day onth at the same time with the parameters:	
			Name	Description	
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:m-m:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
			Day	The number of the day, in the month, to run the job.	
			For example, on	the first of every month at 5:30 pm:	

Name	Description			
	Name	Description	Description	
		Name	Description	
			"Monthly": {     "Day": 1     "Time": "2022-02-27T17:30:00Z" }	
		Note: Although the Swagger Example Value may show examples of various other schedules, only the schedules shown here—that are available in the Management Portal for this functionality—are valid for this endpoint.		
	Under- A Boolean indicating whether the SSH server group is in <i>inventory only</i> mode (True).			
User	An array contain	rray containing information about the service account user. Service account user details include:		
	Name	Description		
	Id	An integer indicating the Keyfactor Command reference ID of the SSH service account user.		
	Key	An array containi details include:	ng information about the key for the service account user. Key	
		Name	Description	
		Id	An integer indicating the Keyfactor Command reference ID of the SSH service account's key.	
		Fingerprint	A string indicating the fingerprint of the public key. Each SSH public key has a single cryptographic fingerprint that can be used to uniquely identify the key.	
		PublicKey	A string indicating the public key of the key pair for the SSH service account.	
		КеуТуре	A string indicating the cryptographic algorithm used to	

Name	Description			
	Name	Description		
		Name	Description	
			generate the SSH key. Possible values are:  RSA ECDSA Ed25519	
		KeyLength	An integer indicating the key length for the SSH key. The key length supported depends on the key type selected.  Keyfactor Command supports 256 bits for Ed25519 and ECDSA and 2048 or 4096 bits for RSA.	
		CreationDate	The date, in UTC, on which the SSH key pair was created.	
		StaleDate	The date, in UTC, after which the SSH key pair is considered to be out of date based on the key lifetime defined by the Key Lifetime (days) application setting. See Application Settings: SSH Tab in the Keyfactor Command Reference Guide for more information.	
		Email	A string containing the email address of the administrator or group of administrators responsible for managing the key. This email address is used to alert the administrator or group of administrators when the key pair is approaching the end of its lifetime.	
		Comments	An array containing one or more strings with the user-defined descriptive comments, if any, on the key. Although entry of an email address in the comment field of an SSH key is traditional, this is not a required format. The comment may can contain any characters supported for string fields, including spaces and most punctuation marks. Keys created through the Keyfactor Command Management Portal or with the POST /SSH/ServiceAccounts method will contain only one string in the array.	
		LogonCount	An integer indicating the number of Linux logons associated with the SSH key pair.	
Username	A string indicating the full username of the service account. The username is made up of the user name and <i>ClientHostname</i> entered when the service account is created (e.g. myapp@appsrvr75).			

Name	Description
LogonIds	An array of integers indicating the Keyfactor Command reference IDs of Linux logons that are associated with the service account in order to publish the service account's public key to the servers on which the logons are located.

### **POST SSH Service Accounts Rotate ID**

The POST /SSH/ServiceAccounts/Rotate/{id} method is used to generate a new key pair in Keyfactor Command for an existing SSH service account. This method returns HTTP 200 OK on a success with details for the new key pair of the SSH service account, including the private key.



**Tip:** The following permissions (see Security Overview) are required to use this feature:

SSH: ServerAdmin OR SSH: EnterpriseAdmin

SSH actions are affected by ownership on the server group with which the key is associated and limited for users with only the *ServerAdmin* role. For more information, see *SSH Permissions* in the *Keyfactor Command Reference Guide*.

Name	In	Description
id	Path	Required. The Keyfactor Command reference ID for the SSH service account key for which to retrieve key information.  Use the GET /SSH/ServiceAccounts method (see GET SSH Service Accounts on page 1036) to retrieve a list of all the SSH service accounts to determine the service account's key ID.
		Tip: Be sure to use the ID of the service account itself and not the ID of the service account user or service account's key within the service account.  For example, notice the following record returned from a GET /SSH/ServiceAccounts:  {  "Id": 2,
		<pre>"ClientHostname": "appsrvr80.keyexample.com", "ServerGroup": {</pre>
		"Id": "603d3d4c-89dd-4ab8-92e1-8e83db3d5546", "GroupName": "Server Group Two", "UnderManagement": false
		}, "User": {
		"Id": 7, "Key": {
		"Id": 36, "Fingerprint":
		<pre>"kwuo2k3Ej7wFVMLhI3g+rxt2qXwGp7qcvzdBjVTDHNg=",</pre>
		AAAAB3NzaC1yc2EAAAADAQABAAABAQCAln+t [truncated for display]",
		"KeyType": "RSA", "KeyLength": 2048,
		"CreationDate": "2020-11-17T17:53:55.68", "Email": "pkiadmins@keyexample.com", "Comments": [
		"Access App Two"
		"LogonCount": 3
		}, "Username": "svc_
		<pre>access2@appsrvr80.keyexample.com" }</pre>
		} It contains three IDs:
		<ul> <li>ID 2: The service account's ID. Use this one to rotate the key.</li> <li>ID 7: The service account user's ID.</li> </ul>
		ID 7: The service account user's ID.

Name	In	Description	
		• ID 36: The ID of the s	ervice account user's key.
КеуТуре	Body	<b>Required</b> . A string indicating the crekey. Possible values are:	yptographic algorithm used to generate the SSH
		Value	Description
		1	ECDSA
		2	Ed25519
		3	RSA
PrivateKeyFormat	Body	<b>Required</b> . A string indicating the fo Possible values are:	rmat to use for the downloadable private key.
		Value	Description
		1	OpenSSH
		2	PKCS8
KeyLength	Body	supported depends on the key type for Ed25519 and ECDSA and 2048 c	e key length for the SSH key. The key length e selected. Keyfactor Command supports 256 bits or 4096 bits for RSA. This field is optional if the 9 and <b>required</b> if the <i>KeyType</i> is set to RSA.
Email	Body	administrators responsible for man	mail address of the administrator or group of laging the key. This email address is used to alert nistrators when the key pair is approaching the
Password	Body	<b>Required</b> . A string that sets a passw SSH key pair for download.	word used to secure the private key of the
Comment	Body	Although entry of an email address tional, this is not a required format	ed descriptive comment, if any, on the key. In the comment field of an SSH key is tradi- The comment may can contain any characters g spaces and most punctuation marks.

Table 491: GET SSH Service Accounts Rotate {id} Response Data

Name	Description
ID	An integer indicating the Keyfactor Command reference ID for the SSH service account key. This ID is automatically set by Keyfactor Command.
Fingerprint	A string indicating the fingerprint of the public key. Each SSH public key has a single cryptographic fingerprint that can be used to uniquely identify the key.
PublicKey	A string indicating the public key of the key pair for the SSH service account.
PrivateKey	A string indicating the private key of the key pair for the SSH service account.
КеуТуре	A string indicating the cryptographic algorithm used to generate the SSH key. Possible values are:  RSA  ECDSA  Ed25519
KeyLength	An integer indicating the key length for the SSH key. The key length supported depends on the key type selected. Keyfactor Command supports 256 bits for Ed25519 and ECDSA and 2048 or 4096 bits for RSA.
Comments	An array containing one or more strings with the user-defined descriptive comments, if any, on the key. Although entry of an email address in the comment field of an SSH key is traditional, this is not a required format. The comment may can contain any characters supported for string fields, including spaces and most punctuation marks. Keys created through the Keyfactor Command Management Portal or with the POST /SSH/ServiceAccounts method will contain only one string in the array.
LogonCount	An integer indicating the number of Linux logons associated with the SSH key pair.

### 2.2.25.6 SSH Users

The SSH Users component of the Keyfactor Web APIs includes methods necessary to retrieve, create, update, rotate, and delete users and associated keys in Keyfactor Command.

Table 492: SSH Users Endpoints

Endpoint	Method	Description	Link
/{id}	DELETE	Deletes the SSH user with the specified ID.	DELETE SSH Users ID below
/{id}	GET	Returns the SSH user with the specified ID.	GET SSH Users ID below
/	GET	Returns a list of SSH users based on the specified filters.	GET SSH Users on page 1068
/	POST	Creates a new SSH user.	POST SSH Users on page 1076
/	PUT	Updates an existing SSH user.	PUT SSH Users on page 1077
/Access	POST	Creates a mapping from the SSH user to one or more Linux logons.	POST SSH Users Access on page 1078

### **DELETE SSH Users ID**

The DELETE /SSH/Users/{id} method is used to delete an SSH user in Keyfactor Command. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: SSH: <u>ServerAdmin</u>

Table 493: DELETE SSH Users {id} Input Parameters

Name	In	Description
id	Path	Required. The Keyfactor Command reference ID for the SSH user (user or service account) to be deleted.  Use the GET /SSH/Users method (see GET SSH Users on page 1068) to retrieve a list of all the SSH users to determine the user's ID.

### **GET SSH Users ID**

The GET /SSH/Users/{id} method is used to retrieve an SSH user defined in Keyfactor Command. The method can return either a *user* or a *service account* See the <u>SSH</u> section of the *Keyfactor Command Reference Guide* for more information on the difference between *users* and *service accounts*. This method returns HTTP 200 OK on a success with details for the requested SSH user and its public key. To return an SSH private key, use the GET /SSH/Key-s/MyKey method (see <u>GET SSH Keys My Key on page 943</u>) for a user account or the GET /SSH/Ser-viceAccounts/Key/{id} method (see <u>GET SSH Service Accounts Key ID on page 1030</u>) for a service account.



**Tip:** The following permissions (see Security Overview) are required to use this feature:

SSH: ServerAdmin OR SSH: EnterpriseAdmin

SSH actions are affected by ownership on the server group with which user to logon mappings are associated and limited for users with only the *ServerAdmin* role. For more information, see *SSH Permissions* in the *Keyfactor Command Reference Guide*.

This method has two available versions. Keyfactor recommends using the newer method when possible. For more information about versioning, see Versioning on page 6.

### Version 2

Version 2 of the GET /SSH/Users/{id} method redesigns how logon information for the user is returned, providing a greater level of detail in the returned data.

Table 494: GET SSH Users {id} v2 Input Parameters

Name	In	Description
id	Path	Required. The Keyfactor Command reference ID for the SSH user (user or service account) to be retrieved.  Use the GET /SSH/Users method (see GET SSH Users on page 1068) to retrieve a list of all the SSH users to determine the user's ID.

Name	Description		
Id	An integer indicating the Keyfactor Command reference ID of the SSH user.		
Key	An array containing information about the key for the user. Key details include:		
	Name	Description	
	Id	An integer indicating the Keyfactor Command reference ID of the SSH user's key.	
	Fingerprint	A string indicating the fingerprint of the public key. Each SSH public key has a single cryptographic fingerprint that can be used to uniquely identify the key.	
	PublicKey	A string indicating the public key of the key pair for the SSH user.	
	КеуТуре	A string indicating the cryptographic algorithm used to generate the SSH key.  Possible values are:  RSA  ECDSA  Ed25519	
	KeyLength	An integer indicating the key length for the SSH key. The key length supported depends on the key type selected. Keyfactor Command supports 256 bits for Ed25519 and ECDSA and 2048 or 4096 bits for RSA.	
	CreationDate	The date, in UTC, on which the SSH key pair was created.	
	StaleDate	The date, in UTC, after which the SSH key pair is considered to be out of date based on the key lifetime defined by the Key Lifetime (days) application setting. See Application Settings: SSH Tab in the Keyfactor Command Reference Guide for more information.	
	Email	A string containing the email address of the user, for user accounts, or administrator or group of administrators responsible for managing the key, for service accounts. This email address is used to alert the user or administrator when the key pair is approaching the end of its lifetime.	
	Comments	An array containing one or more strings with the user-defined descriptive comments, if any, on the key. Although entry of an email address in the comment field of an SSH key is traditional, this is not a required format. The comment may can contain any characters supported for string fields, including spaces and most punctuation marks. Keys created through the Keyfactor Command Management Portal or with the POST /SSH/Keys/MyKey or POST	

Name	Description		
	Name	Description	
		/SSH/ServiceAccounts method will contain only one string in the array.	
	LogonCount	An integer indicating the number of Linux logons associated with the SSH key pair.	
Username	A string indicating the full username of the user or service account. For a user account, the username appears in DOMAIN\\username format (e.g. KEYEXAMPLE\\jsmith). For a service account, the username is made up of the user name and <i>ClientHostname</i> entered when the service account is created (e.g. myapp@appsrvr75).		
Access	An array containing information about the Linux logons mapped to the user. Linux logon mapping details include:		
	Name	Description	
	Id	An integer indicating the Keyfactor Command reference ID of the Linux logon.	
	KeyCount	An integer indicating the number of SSH keys associated with the Linux logon.	
	Access	An array containing information about the users mapped to the Linux logon.	
IsGroup	A Boolean indicating whether the user is an Active Directory group (true) or not (false).		

# Version 1

Version 1 of the GET /SSH/Users/{id} method includes the same capabilities as version 2, but offers more limited information on returned logons for the user.

Table 496: GET SSH Users {id} v1 Input Parameters

Name	In	Description
id	Path	Required. The Keyfactor Command reference ID for the SSH user (user or service account) to be retrieved.  Use the GET /SSH/Users method (see GET SSH Users on page 1068) to retrieve a list of all the SSH users to determine the user's ID.

Name	Description		
Id	An integer indicating the Keyfactor Command reference ID of the SSH user.		
Key	An array containing information about the key for the user. Key details include:		
	Name	Description	
	Id	An integer indicating the Keyfactor Command reference ID of the SSH user's key.	
	Fingerprint	A string indicating the fingerprint of the public key. Each SSH public key has a single cryptographic fingerprint that can be used to uniquely identify the key.	
	PublicKey	A string indicating the public key of the key pair for the SSH user.	
	КеуТуре	A string indicating the cryptographic algorithm used to generate the SSH key.  Possible values are:  RSA  ECDSA  Ed25519	
	KeyLength	An integer indicating the key length for the SSH key. The key length supported depends on the key type selected. Keyfactor Command supports 256 bits for Ed25519 and ECDSA and 2048 or 4096 bits for RSA.	
	CreationDate	The date, in UTC, on which the SSH key pair was created.	
	StaleDate	The date, in UTC, after which the SSH key pair is considered to be out of date based on the key lifetime defined by the Key Lifetime (days) application setting. See Application Settings: SSH Tab in the Keyfactor Command Reference Guide for more information.	
	Email	A string containing the email address of the user, for user accounts, or administrator or group of administrators responsible for managing the key, for service accounts. This email address is used to alert the user or administrator when the key pair is approaching the end of its lifetime.	
	Comments	An array containing one or more strings with the user-defined descriptive comments, if any, on the key. Although entry of an email address in the comment field of an SSH key is traditional, this is not a required format. The comment may can contain any characters supported for string fields, including spaces and most punctuation marks. Keys created through the Keyfactor Command Management Portal or with the POST /SSH/Keys/MyKey or POST	

Name	Description		
	Name	Description	
		/SSH/ServiceAccounts method will contain only one string in the array.	
	LogonCount	An integer indicating the number of Linux logons associated with the SSH key pair.	
Username	A string indicating the full username of the user or service account. For a user account, the username appears in DOMAIN\\username format (e.g. KEYEXAMPLE\\jsmith). For a service account, the username is made up of the user name and <i>ClientHostname</i> entered when the service account is created (e.g. myapp@appsrvr75).		
LogonIds	An array of Keyfactor Command reference IDs for the Linux logons mapped to the user to cause the user's SSH public key to be published out to the Linux servers on which those logons reside.		

#### **GET SSH Users**

The GET /SSH/Users method is used to retrieve one or more SSH users defined in Keyfactor Command. The method returns both *users* and *service accounts*. See the <u>SSH</u> section of the *Keyfactor Command Reference Guide* for more information on the difference between *users* and *service accounts*. Results can be limited to selected users using filtering, and URL parameters can be used to specify paging and the level of information detail. This method returns HTTP 200 OK on a success with details for the requested SSH users and their public keys. To return the SSH private key, use the GET /SSH/Keys/MyKey method (see <u>GET SSH Keys My Key on page 943</u>) for user accounts and the GET /SSH/ServiceAccounts/Key/{id} method (see <u>GET SSH Service Accounts Key ID on page 1030</u>) for service accounts.



Tip: The following permissions (see Security Overview) are required to use this feature:

SSH: ServerAdmin OR SSH: EnterpriseAdmin

SSH actions are affected by ownership on the server group with which user to logon mappings are associated and limited for users with only the *ServerAdmin* role. For more information, see *SSH Permissions* in the *Keyfactor Command Reference Guide*.

This method has two available versions. Keyfactor recommends using the newer method when possible. For more information about versioning, see <u>Versioning on page 6</u>.

#### Version 2

Version 2 of the GET /SSH/Users method redesigns how logon information for the user is returned, providing a greater level of detail in the returned data.

Name	In	Description
showOwnedAccess C	Query	A Boolean that specifies whether to return only users that have logons on servers that the requesting user owns (true) or not (false). The default is false.  This option applies only to requesting users with SSH User or SSH Server Admin permissions; users with SSH Enterprise Admin permissions will see all users regardless of the configuration of this setting.  Use the GET /SSH/Servers method (see GET SSH Servers on page 969) or the GET /SSH/ServerGroups method (see GET SSH Server Groups on page 999) to determine ownership of a server or server group.  Example: Example Scenario One  • Server A is owned by Gina and server B is owned by John.
		<ul> <li>Gina is an SSH Server Admin but not an SSH Enterprise Admin.</li> <li>Dave has a logon on server B but not on server A.</li> </ul>
		Gina does a GET /SSH/Users with showOwnedAccess=false and looks at the results for Dave's user record. She sees Dave's user record, but sees no specific logon information for Dave (other than the LogonCount), because all Dave's logons are on servers that Gina does not own.  Gina does a GET /SSH/Users with showOwnedAccess=true and looks at the results for Dave's user record. Dave's user record does not appear.  The presence or absence of Dave's user record is controlled by showOwnedAccess. The presence or absence of logon information associated with Dave's user record is controlled by Gina's level of SSH permissions—with SSH Server Admin permissions, Gina will always see only logons for servers that she owns.
		<ul> <li>Example: Example Scenario Two</li> <li>Server A is owned by Gina and server B is owned by John.</li> <li>Gina is an SSH Server Admin but not an SSH Enterprise Admin.</li> <li>Dave has a logon on server B and a logon on server A.</li> <li>Gina does a GET /SSH/Users with showOwnedAccess=false and looks at the results for Dave's user record. She sees Dave's user record and she sees logon information for server A, but no logon information for server B. Because Gina does not own server B, logon information for that server is not visible to her.</li> <li>Gina does a GET /SSH/Users with showOwnedAccess=true and looks at the results for Dave's user record. She sees Dave's user record and she sees logon information for server A, but no logon information for server B. Because Gina does not own server B, logon information for that server is not visible to her.</li> </ul>

Name	In	Description
		Notice there is no difference here in the results whether you choose <i>true</i> or <i>false</i> because at least one logon for Dave is present on a server owned by Gina. The <i>showOwnedAccess</i> option only comes into play when a user has no logons on a server owned by the requesting user.  The presence or absence of logon information associated with Dave's user record is controlled by Gina's level of SSH permissions—with <i>SSH Server Admin</i> permissions, Gina will always see only logons for servers that she owns.
queryString	Query	A string containing a query to limit the results (e.g. field1 -eq value1 AND field2 - gt value2). The default is to return all records. Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns for the same feature. For querying guidelines, refer to the Keyfactor Command Reference Guide: Using the SSH Server Search. The query fields supported for this endpoint are:  • Email  • LogonServerGroupId  • Fingerprint  • LogonServerId  • ServiceAccountId  • KeyLength  • KeyType  • Username  • LogonCount
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>Username</i> .
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.

Name	Description			
Id	An integer indicating the Keyfactor Command reference ID of the SSH user.			
Key	An array containing ir	An array containing information about the key for the user. Key details include:		
	Name	Description		
	Id	An integer indicating the Keyfactor Command reference ID of the SSH user's key.		
	Fingerprint	A string indicating the fingerprint of the public key. Each SSH public key has a single cryptographic fingerprint that can be used to uniquely identify the key.		
	PublicKey	A string indicating the public key of the key pair for the SSH user.		
	КеуТуре	A string indicating the cryptographic algorithm used to generate the SSH key.  Possible values are:  RSA  ECDSA  Ed25519		
	KeyLength	An integer indicating the key length for the SSH key. The key length supported depends on the key type selected. Keyfactor Command supports 256 bits for Ed25519 and ECDSA and 2048 or 4096 bits for RSA.		
	CreationDate	The date, in UTC, on which the SSH key pair was created.		
	StaleDate	The date, in UTC, after which the SSH key pair is considered to be out of date based on the key lifetime defined by the Key Lifetime (days) application setting. See Application Settings: SSH Tab in the Keyfactor Command Reference Guide for more information.		
	Email	A string containing the email address of the user, for user accounts, or administrator or group of administrators responsible for managing the key, for service accounts. This email address is used to alert the user or administrator when the key pair is approaching the end of its lifetime.		
	Comments	An array containing one or more strings with the user-defined descriptive comments, if any, on the key. Although entry of an email address in the comment field of an SSH key is traditional, this is not a required format. The comment may can contain any characters supported for string fields, including spaces and most punctuation marks. Keys created through the Keyfactor Command Management Portal or with the POST /SSH/Keys/MyKey or POST		

Name	Description		
	Name	Description	
		/SSH/ServiceAccounts method will contain only one string in the array.	
	LogonCount	An integer indicating the number of Linux logons associated with the SSH key pair.	
Username	A string indicating the full username of the user or service account. For a user account, the username appears in DOMAIN\\username format (e.g. KEYEXAMPLE\\jsmith). For a service account, the username is made up of the user name and <i>ClientHostname</i> entered when the service account is created (e.g. myapp@appsrvr75).		
Access	An array containing information about the Linux logons mapped to the user. Linux logon mapping details include:		
	Name	Description	
	Id	An integer indicating the Keyfactor Command reference ID of the Linux logon.	
	KeyCount	An integer indicating the number of SSH keys associated with the Linux logon.	
	Access	An array containing information about the users mapped to the Linux logon.	
IsGroup	A Boolean indicating whether the user is an Active Directory group (true) or not (false).		

# Version 1

Version 1 of the GET /SSH/Users method includes the same capabilities as version 2, but offers more limited information on returned logons for the user.

Table 500: GET SSH Users v1 Input Parameters

Name	In	Description
showOwnedAccess C	Query	A Boolean that specifies whether to return only users that have logons on servers that the requesting user owns (true) or not (false). The default is false.  This option applies only to requesting users with SSH User or SSH Server Admin permissions; users with SSH Enterprise Admin permissions will see all users regardless of the configuration of this setting.  Use the GET /SSH/Servers method (see GET SSH Servers on page 969) or the GET /SSH/ServerGroups method (see GET SSH Server Groups on page 999) to determine ownership of a server or server group.  Example: Example Scenario One  • Server A is owned by Gina and server B is owned by John.
		<ul> <li>Gina is an SSH Server Admin but not an SSH Enterprise Admin.</li> <li>Dave has a logon on server B but not on server A.</li> </ul>
		Gina does a GET /SSH/Users with showOwnedAccess=false and looks at the results for Dave's user record. She sees Dave's user record, but sees no specific logon information for Dave (other than the LogonCount), because all Dave's logons are on servers that Gina does not own.  Gina does a GET /SSH/Users with showOwnedAccess=true and looks at the results for Dave's user record. Dave's user record does not appear.  The presence or absence of Dave's user record is controlled by showOwnedAccess. The presence or absence of logon information associated with Dave's user record is controlled by Gina's level of SSH permissions—with SSH Server Admin permissions, Gina will always see only logons for servers that she owns.
		<ul> <li>Example: Example Scenario Two</li> <li>Server A is owned by Gina and server B is owned by John.</li> <li>Gina is an SSH Server Admin but not an SSH Enterprise Admin.</li> <li>Dave has a logon on server B and a logon on server A.</li> <li>Gina does a GET /SSH/Users with showOwnedAccess=false and looks at the results for Dave's user record. She sees Dave's user record and she sees logon information for server A, but no logon information for server B. Because Gina does not own server B, logon information for that server is not visible to her.</li> <li>Gina does a GET /SSH/Users with showOwnedAccess=true and looks at the results for Dave's user record. She sees Dave's user record and she sees logon information for server A, but no logon information for server B. Because Gina does not own server B, logon information for that server is not visible to her.</li> </ul>

Name	In	Description
		Notice there is no difference here in the results whether you choose <i>true</i> or <i>false</i> because at least one logon for Dave is present on a server owned by Gina. The <i>showOwnedAccess</i> option only comes into play when a user has no logons on a server owned by the requesting user.  The presence or absence of logon information associated with Dave's user record is controlled by Gina's level of SSH permissions—with <i>SSH Server Admin</i> permissions, Gina will always see only logons for servers that she owns.
queryString	Query	A string containing a query to limit the results (e.g. field1 -eq value1 AND field2 - gt value2). The default is to return all records. Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns for the same feature. For querying guidelines, refer to the <i>Keyfactor Command Reference Guide: Using the SSH Server Search</i> .
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>Username</i> .
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.

Name	Description			
Id	An integer indicating the Keyfactor Command reference ID of the SSH user.			
Key	An array containing ir	An array containing information about the key for the user. Key details include:		
	Name	Description		
	Id	An integer indicating the Keyfactor Command reference ID of the SSH user's key.		
	Fingerprint	A string indicating the fingerprint of the public key. Each SSH public key has a single cryptographic fingerprint that can be used to uniquely identify the key.		
	PublicKey	A string indicating the public key of the key pair for the SSH user.		
	КеуТуре	A string indicating the cryptographic algorithm used to generate the SSH key.  Possible values are:  RSA  ECDSA  Ed25519		
	KeyLength	An integer indicating the key length for the SSH key. The key length supported depends on the key type selected. Keyfactor Command supports 256 bits for Ed25519 and ECDSA and 2048 or 4096 bits for RSA.		
	CreationDate	The date, in UTC, on which the SSH key pair was created.		
	StaleDate	The date, in UTC, after which the SSH key pair is considered to be out of date based on the key lifetime defined by the Key Lifetime (days) application setting. See Application Settings: SSH Tab in the Keyfactor Command Reference Guide for more information.		
	Email	A string containing the email address of the user, for user accounts, or administrator or group of administrators responsible for managing the key, for service accounts. This email address is used to alert the user or administrator when the key pair is approaching the end of its lifetime.		
	Comments	An array containing one or more strings with the user-defined descriptive comments, if any, on the key. Although entry of an email address in the comment field of an SSH key is traditional, this is not a required format. The comment may can contain any characters supported for string fields, including spaces and most punctuation marks. Keys created through the Keyfactor Command Management Portal or with the POST /SSH/Keys/MyKey or POST		

Name	Description		
	Name	Description	
		/SSH/ServiceAccounts method will contain only one string in the array.	
	LogonCount	An integer indicating the number of Linux logons associated with the SSH key pair.	
Username	A string indicating the full username of the user or service account. For a user account, the username appears in DOMAIN\\username format (e.g. KEYEXAMPLE\\jsmith). For a service account, the username is made up of the user name and <i>ClientHostname</i> entered when the service account is created (e.g. myapp@appsrvr75).		
Logonids	An array of Keyfactor Command reference IDs for the Linux logons mapped to the user to cause the user's SSH public key to be published out to the Linux servers on which those logons reside.		

### **POST SSH Users**

The POST /SSH/Users method is used to create a new SSH user in Keyfactor Command and, optionally, associate the user with one or more Linux logons during creation to allow the public key for the user to be published out to a Linux server—for servers in *inventory and publish policy* mode. This method returns HTTP 200 OK on a success with the details of the user to logon mapping, if any.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature:

SSH: ServerAdmin OR SSH: EnterpriseAdmin

SSH actions are affected by ownership on the server group with which user to logon mappings are associated and limited for users with only the *ServerAdmin* role. For more information, see *SSH Permissions* in the *Keyfactor Command Reference Guide*.

Table 502: POST SSH Users Input Parameters

Name	In	Description
Username	Body	Required. A string indicating the full username of the <i>user</i> or <i>service account</i> .  For a <i>user</i> account, the username is given in DOMAIN\\username format (e.g. KEYEXAMPLE\\jsmith). For a <i>service account</i> , the username is made up of a user name (e.g. svc_myapp) and client hostname reference for the service account. The client hostname is used for reference only and does not need to match an actual client hostname. The naming convention is to enter the hostname of the server on which the application that will use the private key resides (e.g. appsrvr12), but you can put anything you like in this field (e.g. cheesetoast). The full service account name is given in the form username@clienthostname (e.g. svc_myapp@appsrvr75).
Logonids	Body	An array of Keyfactor Command reference IDs for the Linux logons to map to the user to cause the user's SSH public key to be published out to the Linux servers on which those logons reside.  These are provided in the following format:  [12,27,39]  Use the GET /SSH/Logons method (see GET SSH Logons on page 957) to retrieve a list of all the SSH logons to determine the logon's ID(s).

Table 503: POST SSH Users Response Data

Name	Description
ID	An integer indicating the Keyfactor Command reference ID of the SSH user.
Username	A string indicating the full username of the <i>user</i> or <i>service account</i> .
LogonIds	An array of Keyfactor Command reference IDs for the Linux logons to map to the user to cause the user's SSH public key to be published out to the Linux servers on which those logons reside.

### **PUT SSH Users**

The PUT /SSH/Users method is used to update an existing SSH user in Keyfactor Command and, optionally, associate the user with one or more Linux logons to allow the public key for the user to be published out to a Linux server—for servers in *inventory and publish policy* mode. This method returns HTTP 200 OK on a success with the details of the user to logon mapping, if any.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature:

SSH: ServerAdmin OR SSH: EnterpriseAdmin



SSH actions are affected by ownership on the server group with which user to logon mappings are associated and limited for users with only the *ServerAdmin* role. For more information, see *SSH Permissions* in the *Keyfactor Command Reference Guide*.

Table 504: PUT SSH Users Input Parameters

Name	In	Description
ID	Body	<b>Required</b> . An integer indicating the Keyfactor Command reference ID of the SSH user.  Use the <i>GET /SSH/Users</i> method (see <u>GET SSH Users on page 1068</u> ) to retrieve a list of all the SSH users to determine the user's ID.
Logonids	Body	An array of Keyfactor Command reference IDs for the Linux logons to map to the user to cause the user's SSH public key to be published out to the Linux servers on which those logons reside.  These are provided in the following format:  [12,27,39]  Use the GET /SSH/Logons method (see GET SSH Logons on page 957) to retrieve a list of all the SSH logons to determine the logon's ID(s).  Important: Logon IDs you provide here replace any existing logon IDs associated with the user. To avoid accidentally removing access for users, check existing logons for the user (see GET SSH Users on page 1068) before updating and provide both existing and new logon IDs.

Table 505: POST SSH Users Response Data

Name	Description
ID	An integer indicating the Keyfactor Command reference ID of the SSH user.
Username	A string indicating the full username of the <i>user</i> or <i>service account</i> .
LogonIds	An array of Keyfactor Command reference IDs for the Linux logons to map to the user to cause the user's SSH public key to be published out to the Linux servers on which those logons reside.

### **POST SSH Users Access**

The POST /SSH/Users/Access method is used to create a mapping of one or more Linux logons to a Keyfactor Command user or service account. This method returns HTTP 200 OK on a success with the details of the user to logon mapping, if any.



**Tip:** The following permissions (see Security Overview) are required to use this feature:

SSH: ServerAdmin OR SSH: EnterpriseAdmin

SSH actions are affected by ownership on the server group with which user to logon mappings are associated and limited for users with only the *ServerAdmin* role. For more information, see *SSH Permissions* in the *Keyfactor Command Reference Guide*.



**Tip:** Before creating a logon to user mapping, be sure that you have switched the server to which you will add your mapping (or its server group) to *inventory and publish policy* mode so that the key for the user will be published to the server. If the server is in *inventory only* mode and you add a mapping for it in Keyfactor Command, the mapping will appear in Keyfactor Command only and the key for the user will not be published out to the server.

Table 506: POST SSH Users Access Input Parameters

Name	In	Description	
ID	Body	<b>Required</b> . An integer indicating the Keyfactor Command reference ID of the SSH user.  Use the <i>GET /SSH/Users</i> method (see <u>GET SSH Users on page 1068</u> ) to retrieve a list of all the SSH users to determine the user's ID.	
Logonids	Body	An array of Keyfactor Command reference IDs for the Linux logons to map to the user to cause the user's SSH public key to be published out to the Linux servers on which those logons reside.  These are provided in the following format:  [12,27,39]  Use the GET /SSH/Logons method (see GET SSH Logons on page 957) to retrieve a list of all the SSH logons to determine the logon's ID(s).  Important: Logon IDs you provide here replace any existing logon IDs associated with the user. To avoid accidentally removing access for users, check existing logons for the user (see GET SSH Users on page 1068) before updating and provide both existing and new logon IDs.	

Name	Description			
Id	An integer indicating the Keyfactor Command reference ID of the SSH user.			
Key	An array containing in	formation about the key for the user. Key details include:		
	Name	Description		
	Id	An integer indicating the Keyfactor Command reference ID of the SSH user's key.		
	Fingerprint	A string indicating the fingerprint of the public key. Each SSH public key has a single cryptographic fingerprint that can be used to uniquely identify the key.		
	PublicKey	A string indicating the public key of the key pair for the SSH user.		
	КеуТуре	A string indicating the cryptographic algorithm used to generate the SSH key.  Possible values are:  RSA  ECDSA  Ed25519		
	KeyLength	An integer indicating the key length for the SSH key. The key length supported depends on the key type selected. Keyfactor Command supports 256 bits for Ed25519 and ECDSA and 2048 or 4096 bits for RSA.		
	CreationDate	The date, in UTC, on which the SSH key pair was created.		
	StaleDate	The date, in UTC, after which the SSH key pair is considered to be out of date based on the key lifetime defined by the Key Lifetime (days) application setting. See Application Settings: SSH Tab in the Keyfactor Command Reference Guide for more information.		
	Email	A string containing the email address of the user, for user accounts, or administrator or group of administrators responsible for managing the key, for service accounts. This email address is used to alert the user or administrator when the key pair is approaching the end of its lifetime.		
	Comments	An array containing one or more strings with the user-defined descriptive comments, if any, on the key. Although entry of an email address in the comment field of an SSH key is traditional, this is not a required format. The		

Name	Description				
	Name	Description			
		comment may can contain any characters supported for string fields, including spaces and most punctuation marks. Keys created through the Keyfactor Command Management Portal or with the POST /SSH/Keys/MyKey or POST /SSH/ServiceAccounts method will contain only one string in the array.			
	LogonCount An integer indicating the number of Linux logons associated with the SSH key pair.				
Username	A string indicating the full username of the user or service account. For a user account, the username appears in DOMAIN\\username format (e.g. KEYEXAMPLE\\jsmith). For a service account, the username is made up of the user name and <i>ClientHostname</i> entered when the service account is created (e.g. myapp@appsrvr75).				
Access	An array containing information about the Linux logons mapped to the user. Linux logon mapping details include:				
	Name	Description			
	Id	An integer indicating the Keyfactor Command reference ID of the Linux logon.			
	Username	A string indicating the user's logon name on the Linux server.			
	KeyCount	An integer indicating the number of SSH keys associated with the Linux logon.			
	Access	An array containing information about the users mapped to the Linux logon.			
IsGroup	A Boolean indicating whether the user is an Active Directory group (true) or not (false).				

# 2.2.26 SMTP

The SMTP component of the Keyfactor API includes methods necessary to programmatically edit and retrieve the SMTP configuration profile and send a test email message. Editing the SMTP configuration profile in Keyfactor Command will only apply within the software. Only one SMTP profile may be configured.

Table 508: SMTP Endpoints

Endpoint	Method	Description	Link
/	GET	Returns information about the SMTP configuration profile.	GET SMTP on the next page
/	PUT	Updates settings for the SMTP configuration profile.	PUT SMTP on page 1083

Endpoint	Method	Description	Link
/Test	POST	Sends a test email message to confirm SMTP configuration.	POST SMTP Test on page 1086

### 2.2.26.1 GET SMTP

The GET /SMTP method is used to retrieve the SMTP configuration profile from Keyfactor Command. This method returns HTTP 200 OK on a success with details about the SMTP profile. Only one profile may be configured. There are no input parameters for this method.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: SystemSettings: *Read* 

Name	Description			
Host	A string indicating the fully qualified domain name of your SMTP host (e.g. corpexch02.keyexample.com).			
Id	An integer indicating the Keyfactor Command reference ID of the SMTP record. This will be 1 in most environments.			
Port	An integer indicating the SMTP port	(e.g. 25).		
RelayAuthenticationType	An integer indicating the type of autible values are:	hentication used to connect to the mail server. Poss-		
	Value	Description		
	0	Anonymous		
	2	Explicit Credentials		
RelayUsername	A string indicating the username of the account providing authentication to the mail server if <i>RelayAuthenticationType</i> is set to 2. The username should be provided in DOMAIN\username format.  For most mail server configurations, the username provided must have as a valid email address the email address you set in the <i>SenderAccount</i> parameter.			
SenderAccount	A string indicating the sender for email messages delivered from Keyfactor Command, in the form of an email address (e.g. jsmith@keyexample.com). Depending on the email configuration in your environment, the sender account may need to be a valid user on your mail server or you may be able to put anything in this field.			
SenderAddress	A string indicating the sender for email messages delivered from Keyfactor Command, in the form of an email address (e.g. jsmith@keyexample.com).  This is considered deprecated and may be removed in a future release.			
SenderName	A string indicating the name that appears as the "from" in the user's mail client (e.g. "Keyfactor Command"). This value is used for both configurations of <i>RelayAuthenticationType</i> .			
UseSSL	A Boolean indicating that mail shoul support this.	d be delivered over TLS/SSL. Not all mail servers		

# 2.2.26.2 PUT SMTP

The PUT /SMTP method is used to update the SMTP configuration profile information. This method returns HTTP 200 OK on a success with details about the SMTP configuration profile.



**Tip:** The following permissions (see Security Overview) are required to use this feature: SystemSettings: Modify



Warning: Any previously populated fields that are not submitted with their full existing data using this method will be cleared of their existing data. When using this method, you should first do a GET to retrieve all the values for the record you want to update, enter corrected data into the field(s) you want to update, and then submit all the fields using PUT, including the fields that contain values but which you are not changing.

Table 510: PUT SMTP Input Parameters

Name	In	Description		
Host	Body	<b>Required</b> . A string indicating the fully qualified domain name of your SMTP host (e.g. corpexch02.keyexample.com).		
Id	Body	<b>Required</b> . An integer indicating the Keyfactor Command reference ID of the SMTP record. This will be 1 in most environments.		
Port	Body	An integer indicating the SMTP port (e.g. 25).		
RelayAuthenticationType	Body	An integer indicating the type of server. Possible values are:	of authentication used to connect to the mail	
		Value	Description	
		0	Anonymous	
		2	Explicit Credentials	
RelayPassword	Body	Required*. A string indicating the password of the user specified by RelayUsername if RelayAuthenticationType is set to 2. This field is required if RelayAuthenticationType is set to 2. No data is output in this field on a GET.		
RelayUsername	Body	Required*. A string indicating the username of the account providing authentication to the mail server if <i>RelayAuthenticationType</i> is set to 2. The username should be provided in DOMAIN\\username format. This field is required if <i>RelayAuthenticationType</i> is set to 2.  For most mail server configurations, the username provided must have as a valid email address the email address you set in the <i>SenderAccount</i> parameter.		
SenderAccount	Body	Required. A string indicating the sender for email messages delivered from Keyfactor Command, in the form of an email address (e.g. jsmith@keyexample.com). Depending on the email configuration in your environment, the sender account may need to be a valid user on your mail server or you may be able to put anything in this field.		
SenderName	Body	<b>Required</b> . A string indicating the name that appears as the "from" in the user's mail client (e.g. "Keyfactor Command"). This value is used for both configurations of <i>RelayAuthenticationType</i> .		
UseSSL	Body	A Boolean indicating that mail should be delivered over TLS/SSL. Not all mail servers support this.		

Table 511: POST SMTP Test Response Data

Name	Description			
Host	A string indicating the fully qualified domain name of your SMTP host (e.g. corpexch02.keyexample.com).			
Id	An integer indicating the Keyfactor ( be 1 in most environments.	Command reference ID of the SMTP record. This will		
Port	An integer indicating the SMTP port	(e.g. 25).		
RelayAuthenticationType	An integer indicating the type of autible values are:	hentication used to connect to the mail server. Poss-		
	Value	Description		
	0	Anonymous		
	2 Explicit Credentials			
RelayUsername	A string indicating the username of the account providing authentication to the mail server if <i>RelayAuthenticationType</i> is set to 2. The username should be provided in DOMAIN\username format.  For most mail server configurations, the username provided must have as a valid email address the email address you set in the <i>SenderAccount</i> parameter.			
SenderAccount	A string indicating the sender for email messages delivered from Keyfactor Command, in the form of an email address (e.g. jsmith@keyexample.com). Depending on the email configuration in your environment, the sender account may need to be a valid user on your mail server or you may be able to put anything in this field.			
SenderName	A string indicating the name that appears as the "from" in the user's mail client (e.g. "Keyfactor Command"). This value is used for both configurations of <i>RelayAuthenticationType</i> .			
UseSSL	A Boolean indicating that mail shoul support this.	d be delivered over TLS/SSL. Not all mail servers		

## 2.2.26.3 POST SMTP Test

The POST /SMTP/Test method is used to test the SMTP settings by sending a test email message. This method returns HTTP 200 OK on a success with details about the SMTP profile.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: SystemSettings: *Modify* 

Table 512: POST SMTP Test Input Parameters

Name	In	Description		
Host	Body	<b>Required</b> . A string indicating the fully qualified domain name of your SMTP host (e.g. corpexch02.keyexample.com).		
Id	Body	An integer indicating the Keyfactor Command reference ID of the SMTP record. This will be 1 in most environments.		
Port	Body	Required. An integer indicating the SMTP port (e.g. 25).		
RelayAuthenticationType	Body	An integer indicating the type of server. Possible values are:	of authentication used to connect to the mail	
		Value	Description	
		0	Anonymous	
		2	Explicit Credentials	
RelayPassword	Body	Required*. A string indicating the password of the user specified by RelayUsername if RelayAuthenticationType is set to 2. This field is required if RelayAuthenticationType is set to 2. No data is output in this field on a GET.		
RelayUsername	Body	Required*. A string indicating the username of the account providing authentication to the mail server if <i>RelayAuthenticationType</i> is set to 2. The username should be provided in DOMAIN\\username format. This field is required if <i>RelayAuthenticationType</i> is set to 2.  For most mail server configurations, the username provided must have as a valid email address the email address you set in the <i>SenderAccount</i> parameter.		
SenderAccount	Body	Required. A string indicating the sender for email messages delivered from Keyfactor Command, in the form of an email address (e.g. jsmith@keyexample.com). Depending on the email configuration in your environment, the sender account may need to be a valid user on your mail server or you may be able to put anything in this field.		
SenderAddress	Body	A string indicating the sender for email messages delivered from Keyfactor Command, in the form of an email address (e.g. jsmith@keyexample.com).  This is considered deprecated and may be removed in a future release.		
SenderName	Body	A string indicating the name that appears as the "from" in the user's mail client (e.g. "Keyfactor Command"). This value is used for both configurations of <i>RelayAuthenticationType</i> .		

Name	In	Description
TestRecipient	Body	<b>Required</b> . A string indicating the recipient name, in email format (e.g. mjones@keyexample.com), for a test message to be sent using the SMTP configuration to confirm functionality.
UseSSL	Body	A Boolean indicating that mail should be delivered over TLS/SSL. Not all mail servers support this.

Table 513: POST SMTP Test Response Data

Name	Description			
Host	A string indicating the fully qualified domain name of your SMTP host (e.g. corpexch02.keyexample.com).			
ld	An integer indicating the Keyfactor (be 1 in most environments.	An integer indicating the Keyfactor Command reference ID of the SMTP record. This will be 1 in most environments.		
Port	An integer indicating the SMTP port	(e.g. 25).		
RelayAuthenticationType	An integer indicating the type of autible values are:	hentication used to connect to the mail server. Poss-		
	Value	Description		
	0	Anonymous		
	2 Explicit Credentials			
RelayUsername	A string indicating the username of the account providing authentication to the mail server if <i>RelayAuthenticationType</i> is set to 2. The username should be provided in DOMAIN\\username format.  For most mail server configurations, the username provided must have as a valid email address the email address you set in the <i>SenderAccount</i> parameter.			
SenderAccount	A string indicating the sender for email messages delivered from Keyfactor Command, in the form of an email address (e.g. jsmith@keyexample.com). Depending on the email configuration in your environment, the sender account may need to be a valid user on your mail server or you may be able to put anything in this field.			
SenderName	A string indicating the name that appears as the "from" in the user's mail client (e.g. "Keyfactor Command"). This value is used for both configurations of <i>RelayAuthenticationType</i> .			
TestRecipient	A string indicating the recipient name, in email format (e.g. mjones@keyexample.com), for a test message to be sent using the SMTP configuration to confirm functionality.			
UseSSL	A Boolean indicating that mail shoul support this.	d be delivered over TLS/SSL. Not all mail servers		

# 2.2.27 SSL

The SSL component of the Keyfactor API includes methods necessary to programmatically create, delete, edit, and list SSL networks, network ranges, and endpoints found in an SSL scan.

Endpoint	Method	Description	Link
/Parts/{id}	GET	Returns detailed information about a scan job for SSL discovery or monitoring.	GET SSL Parts ID on the next page
/Endpoints/{id}	GET	Returns the details about a single endpoint discovered during SSL scanning.	GET SSL Endpoints ID on page 1093
/NetworkRanges/{id}	DELETE	Removes all network ranges from the specified SSL network.	DELETE SSL  NetworkRanges ID on page 1094
/NetworkRanges/{id}	GET	Returns network range information about the specified SSL network.	GET SSL NetworkRanges ID on page 1094
/Networks/{identifier}	GET	Returns information about the specified SSL network.	GET SSL Networks Identifier on page 1095
1	GET	Returns the results of an SSL scan based on query information.	GET SSL on page 1104
/Networks	GET	Returns information about all SSL networks in Keyfactor Command.	GET SSL Networks on page 1106
/Networks	POST	Creates a new SSL network.	POST SSL Networks on page 1115
/Networks	PUT	Updates an existing SSL network.	PUT SSL Networks on page 1127
/Endpoints/{id}/History	GET	Returns a list of all the SSL scanning endpoint histories for an endpoint with the given ID.	GET SSL Endpoints ID History on page 1139
/Networks/{id}/Parts	GET	Returns the scan job information for SSL discovery or monitoring.	GET SSL Networks ID Parts on page 1145
/NetworkRanges	POST	Adds network ranges to the specified SSL network.	POST SSL  NetworkRanges on page 1146
/NetworkRanges	PUT	Updates network range information on the specified SSL network.	PUT SSL NetworkRanges on page 1147
/Endpoints/ReviewStatus	PUT	Used to change the <i>reviewed</i> status for a given SSL endpoint.	PUT SSL Endpoints

Endpoint	Method	Description	Link
			Review Status on page 1147
/Endpoints/MonitorStatus	PUT	Used to change the <i>monitoring</i> status for a given SSL endpoint.	PUT SSL Endpoints  Monitor Status on page 1148
/Endpoints/ReviewAll	PUT	Used to change the <i>reviewed</i> status for all given SSL endpoints to true.	PUT SSL Endpoints Review All on page 1148
/Endpoints/MonitorAll	PUT	Used to change the <i>monitoring</i> status for all given SSL endpoints to true.	PUT SSL Endpoints  Monitor All on page 1149
/Networks/{id}/Scan	POST	Starts an SSL discovery or monitoring scan job manually.	POST SSL Networks ID Scan on page 1149
/NetworkRanges/Validate	POST	Validates all SSL networks given.	POST SSL  NetworkRanges  Validate on page 1150
/Networks/{id}	DELETE	Removes an SSL network from Keyfactor Command.	DELETE SSL Networks ID on page 1151

## 2.2.27.1 GET SSL Parts ID

The GET /SSL/Parts/{id} method retrieves information for a specific job scan segment (see GET SSL Networks ID Parts on page 1145). This method returns HTTP 200 OK on a success with details about the specified scan job segment.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: SslManagement: *Read* 

Table 515: GET SSL Parts {id} Input Parameters

Name	In	Description
id	Path	Required. The Keyfactor Command reference GUID for the SSL scan job segment to be retrieved.  Use the GET /SSL/Networks/{id}/Parts method (see GET SSL Networks ID Parts on page 1145) to retrieve a list of all the scan job segments in an SSL network to determine the SSL scan job segment's GUID.

Table 516: GET SSL Parts {id} Response Data

Parameter Name	Description		
ScanJobPartId	The Keyfactor Command reference	e GUID for the scan job segment.	
LogicalScanJobId	The Keyfactor Command reference	e GUID for the scan job as a whole.	
AgentJobId		e GUID for the orchestrator that ran the job nent has not yet started scanning, this will show	
Estimated Endpoint Count	segment estimated in preparation The number of endpoints per segr	ment is configurable (see the SSL Maximum Scan in the Application Settings: Agents Tab section	
Status	An integer indicating the status of the scan job segment. Possible values are:		
	Value	Description	
	1	Not Started	
	2	In Progress	
	3	Complete	
StatTotalEndpointCount	An integer indicating the number segment. This value will be null if	of endpoints that were be scanned for the the scan is not yet complete.	
StatTimedOutConnectingCount	An integer indicating the number connections. This value will be nul	of endpoints that timed out while attempting II if the scan is not yet complete.	
StatConnectionRefusedCount		of endpoints that received a connection refused is value will be null if the scan is not yet	
StatTimedOutDownloadingCount		of endpoints that timed out while downloading is value will be null if the scan is not yet	
StatExceptionDownloadingCount	An integer indicating the number of endpoints that encountered an exception while attempting connections. This value will be null if the scan is not yet complete.		

Parameter Name	Description
StatNotSslCount	An integer indicating the number of endpoints that made a connection and were considered not SSL (connection on a non-SSL port such as 22 or 636). This value will be null if the scan is not yet complete.
StatBadSslHandshakeCount	An integer indicating the number of endpoints that had a bad handshake while attempting connections. This value will be null if the scan is not yet complete.
StatCertificateFoundCount	An integer indicating the number of endpoints where a certificate was found. This value will be null if the scan is not yet complete.
StatNoCertificateCount	An integer indicating the number of endpoints where the handshake got to the part of the TLS where a certificate should be returned, but did not find a certificate. This is an uncommon occurrence, so will usually be zero.
ScanJobPartsDefinitions	This is no longer in use and will always return "null".
StartTime	The date and time at which the scan job segment started in UTC. For jobs that have not yet started, this value will be null.
EndTime	The date and time at which the scan job segment finished in UTC. For jobs that have not yet started, this value will be null.

# 2.2.27.2 GET SSL Endpoints ID

The GET /SSL/Endpoints/{id} method is used to retrieve information about an endpoint found in an SSL discover or monitor scan using the EndpointId. This method returns HTTP 200 OK on a success with details of the SSL endpoints.



Table 517: GET SSL Endpoints {id} Input Parameters

Name	In	Description
id	Path	<b>Required</b> . The Keyfactor Command reference GUID for the SSL endpoint to be retrieved. Use the <i>GET /SSL</i> method (see <u>GET SSL on page 1104</u> ) to retrieve a list of all the SSL endpoints to determine the SSL endpoint's GUID.

Table 518: GET SSL Endpoints {id} Response Data

Name	Description
EndpointId	The Keyfactor Command reference GUID for the endpoint.
NetworkId	The Keyfactor Command reference GUID for the SSL network that scanned the endpoint.
LastHistoryId	The Keyfactor Command reference GUID for the last history entry on the endpoint.
IpAddressBytes	The IP address for the endpoint as bytes.
Port	An integer indicating the port on which this endpoint was found.
SNIName	A string indicating the server name indication (SNI) of the endpoint, if found.
EnableMonitor	A Boolean indicating whether monitoring is enabled on this endpoint (true) or not (false).
Reviewed	A Boolean indicating whether the endpoint has been reviewed (true) or not (false).

## 2.2.27.3 DELETE SSL NetworkRanges ID

The DELETE /SSL/NetworkRanges/{id} method is used to delete all the network ranges for an SSL network with the specified GUID from Keyfactor Command. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: SslManagement: *Modify* 



**Tip:** To delete some but not all of the network ranges for a network, use the *PUT /SSL/Networks* method to update the network and submit the request with only those network ranges you wish to retain (see <u>PUT SSL Networks</u> on page 1127).

Table 519: DELETE SSL Network Ranges {id} Input Parameters

Name	In	Description
id	Path	Required. The Keyfactor Command reference GUID for the SSL network for which to delete network ranges.  Use the GET /SSL/Networks method (see GET SSL Networks on page 1106) to retrieve a list of all the SSL networks to determine the SSL network's GUID.

# 2.2.27.4 GET SSL NetworkRanges ID

The GET /SSL/NetworkRanges/{id} method is used to retrieve the network ranges for an SSL network with the specified GUID from Keyfactor Command. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: SslManagement: *Read* 

Table 520: GET SSL Network Ranges {id} Input Parameters

Name	In	Description
id	Path	<b>Required</b> . The Keyfactor Command reference GUID for the SSL network for which to retrieve network ranges.  Use the <i>GET /SSL/Networks</i> method (see <u>GET SSL Networks on page 1106</u> ) to retrieve a list of all the SSL networks to determine the SSL network's GUID.

Table 521: GET SSL Network Ranges {id} Response Data

Name	Description			
ItemType	An integer indicating the type of network range. Possible values are:			
	Value	Description		
	0	Unknown		
	1	IP Address		
	2	Host Name		
	3	Network Notation		
Value	A string indicating the value for the network range, including the IP address, network notation or host name followed by the port or ports for scanning (e.g. 192.168.12.0/24:443).			

## 2.2.27.5 GET SSL Networks Identifier

The GET /SSL/Networks/{identifier} method is used to retrieve a defined SSL network according to the provided name from Keyfactor Command. This method returns HTTP 200 OK on a success with details about the SSL network.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: SslManagement: *Read* 

Table 522: GET SSL Networks {id} Input Parameters

Name	In	Description
id	Path	<b>Required</b> . The Keyfactor Command reference GUID for the SSL network to be retrieved. Use the <i>GET /SSL/Networks</i> method (see <u>GET SSL Networks on page 1106</u> ) to retrieve a list of all the SSL networks to determine the SSL network's GUID.

Table 523: GET SSL Networks {id} Response Data

Name	Description		
NetworkId	The Keyfactor Command reference GUID for the SSL network. This GUID is automatically set by Keyfactor Command.		
Name	A string indicatin	ng the name for the SSL network.	
AgentPoolName	ŭ	ng the name of the orchestrator pool assigned to the SSL network. See <i>Orches-inition</i> in the <i>Keyfactor Command Reference Guide</i> for more information.	
AgentPoolId	The Keyfactor Co	ommand reference GUID for the orchestrator pool assigned to the SSL network.	
Description	A string indicatin	ng the description of the SSL network.	
Enabled	A Boolean that indicates whether scanning is enabled for the SSL network (true) or not (false). If this is set to false, no new network scans will be scheduled but any current scan will finish if one was in progress when the status was changed from true to false.		
DiscoverSchedule  An array providing the discovery schedule for the SSL network group. The schedule continues (unset) or one of the supported values. Supported schedule values are:			
	Name	Description	
	Immediate	A Boolean that indicates a job scheduled to run immediately (true) or not (false).	
		Tip: In some instances, jobs initially scheduled as <i>Immediate</i> will appear on a GET as <i>null</i> .	
		A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database.	
		Name Description	
		Minutes An integer indicating the number of minutes between each interval.	
		For example, every hour:	

Name	Description		
	Name	Description	
		"Interval": "Minutes }	
	Daily	A dictionary that	t indicates a job scheduled to run every day at the same arameter:
		Name	Description
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
		For example, da	illy at 11:30 pm:
		"Daily": {     "Time": }	"2022-02-25T23:30:00Z"
	Weekly		t indicates a job scheduled to run on a specific day or days he same time with the parameters:
		Name	Description
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
		Days	An array of values representing the days of the week on which to run the job. These can either be entered as integers (0 for Sunday, 1 for Monday, etc.) or as days of the week (e.g. "Sunday").
		For example, ev	ery Monday, Wednesday and Friday at 5:30 pm:
		"Weekly": {     "Days":     "Mond	1

# Name Description Name Description "Wednesday", "Friday" ], "Time": "2022-02-27T17:30:00Z" A dictionary that indicates a job scheduled to run on a specific day or days Monthly every month at the same time with the parameters: Name **Description** Time The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z). The number of the day, in the month, to run the job. Day For example, on the first of every month at 5:30 pm: "Monthly": { "Day": 1 "Time": "2022-02-27T17:30:00Z" ExactlyOnce A dictionary that indicates a job scheduled to run at the time specified with the parameter: Description Name Time The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z). For example, exactly once at 11:45 am: "ExactlyOnce": { "Time": "2022-02-27T11:45:00Z" Tip: In some instances, jobs initially scheduled as *Immediate* will appear on a GET as ExactlyOnce.

Name	Description			
MonitorSchedule	An array providing the monitoring schedule for the SSL network group. The schedule can be off (unset) or one of the supported values. Supported schedule values are:			
	Name	Description		
	Immediate	A Boolean that i (false).	ndicates a job scheduled to run immediately (true) or not	
		N/Z	some instances, jobs initially scheduled as <i>Immediate</i> will on a GET as <i>null</i> .	
	Interval	specified param	t indicates a job scheduled to run every x minutes with the eter. Any interval that is selected in the UI will be nutes when stored in the database.	
		Name	Description	
	Daily	Minutes	An integer indicating the number of minutes between each interval.	
		For example, every hour:		
		"Interval": "Minutes }		
		A dictionary that indicates a job scheduled to run every day at the same time with the parameter:		
		Name	Description	
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
		For example, da	ily at 11:30 pm:	
		"Daily": {     "Time": }	"2022-02-25T23:30:00Z"	

Name	Description			
	Name	Description		
	Weekly	A dictionary that indicates a job scheduled to run on a specific day or days every week at the same time with the parameters:		
		Name	Description	
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
		Days	An array of values representing the days of the week on which to run the job. These can either be entered as integers (0 for Sunday, 1 for Monday, etc.) or as days of the week (e.g. "Sunday").	
		"Weekly": {     "Days":     "Mono	[ day", nesday",	
	Monthly	A dictionary tha	"2022-02-27T17:30:00Z"  at indicates a job scheduled to run on a specific day or days the same time with the parameters:	
		Name	the same time with the parameters:  Description	
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
		Day	The number of the day, in the month, to run the job.	
		For example, or "Monthly": "Day": 1		

Name	Description		
	Name	Description	
		"Time": }	"2022-02-27T17:30:00Z"
	ExactlyOnce	A dictionary tha the parameter:	t indicates a job scheduled to run at the time specified with
		Name	Description
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
		"ExactlyOnc	actly once at 11:45 am: ee": { "2022-02-27T11:45:00Z"
		N/Z	some instances, jobs initially scheduled as <i>Immediate</i> will on a GET as <i>ExactlyOnce</i> .
Discov- erPercentComplete	be zero for smal completion of ea	l jobs for the entire ach segment of a se	ge complete for a discovery job. The percentage complete will e duration of the job because this value is updated upon can job (and small jobs generally consist of only one at completion. The counter resets when a new job begins.
Monit- orPercentComplete	will be zero for s completion of ea	mall jobs for the each segment of a se	ge complete for a monitoring job. The percentage complete ntire duration of the job because this value is updated upon can job (and small jobs generally consist of only one at completion. The counter resets when a new job begins.
DiscoverStatus	An integer indica	ating the status of	the discovery job. Possible values are:
	Value		Description
	0		Unknown
	1		Not Scheduled

Name	Description		
	Value	Description	
	2	Running	
	3	Previously Scanned	
	4	Scheduled	
	5	Disabled	
	6	In Quiet Hours	
MonitorStatus	An integer indicating the status of the	monitoring job. Possible values are:	
	Value	Description	
	0	Unknown	
	1	Not Scheduled	
	2	Running	
	3	Previously Scanned	
	4	Scheduled	
	5	Disabled	
	6	In Quiet Hours	
DiscoverLastScanned	A string indicating the date and time, in lated as soon as the job is initiated and	n UTC, of the most recent discovery job. This field is populupdated when the job completes.	
MonitorLastScanned	A string indicating the date and time, in UTC, of the most recent monitoring job. This field is populated as soon as the job is initiated and updated when the job completes.		
SslAlertRecipients	An array of strings providing the list of recipients who will receive email messages regarding the status of SSL discovery and monitoring jobs.		
	Note: To improve performance in requests, data is not returned in this field for the GET /SSL/Networks method. Use the GET /SSL/Networks/{id} method to return data in this field.		
AutoMonitor	A Boolean that indicates whether automatic monitoring of discovered endpoints is enabled (true) or not (false).		

Name	Description
GetRobots	A Boolean that indicates whether orchestrators should perform a GET /robots.txt request during scans in order to behave like a webcrawler and provide an explanation of network activity (true) or not (false).
DiscoverTimeoutMs	An integer that indicates the amount of time (in milliseconds) the scan will wait (before timing out) to discover the endpoint. Shorter timeout periods will increase the overall scanning throughput, however they will also increase the chance of missing a certificate on a slow or congested network.
MonitorTimeoutMs	An integer that indicates the amount of time (in milliseconds) the scan will wait (before timing out) to receive the discovered endpoint certificate expiration details.
ExpirationAlertDays	An integer that indicates the number of days within which to begin providing warnings regarding upcoming expiration in notification email messages.
DiscoverJobParts	An integer that indicates the number of job parts that have been created for a discovery job.
MonitorJobParts	An integer that indicates the number of job parts that have been created for a monitoring job.
QuietHours	An array providing the list of scheduled quiet hour periods.

## 2.2.27.6 GET SSL

The GET /SSL method is used to return a list of all discovered SSL endpoints, limited by the provided parameters. This method returns HTTP 200 OK on a success with details about the requested endpoints.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: SslManagement: *Read* 

Table 524: GET SSL Input Parameters

Name	In	Description
queryString	Query	A string containing a query to limit the results (e.g. field1 -eq value1 AND field2 -gt value2). Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns. For querying guidelines, refer to the Keyfactor Command Reference Guide Using the Discovery Results Search Feature section. The query fields supported for this endpoint are:  • AgentPoolName • CertificateCN • ReverseDNS • Reviewed (True, False) • Status (6-Certificate Found, 1- Timed Out Connecting, 2-Exception Connecting, 3-Timed Out Downloading, 5-Not SSL, 7- Exception in Sql, 8-Invalid or Unreachable Host, 9-Connection Refused, 10-Bad SSL Handshake, 11-Client Authentication Failed, 12-No Certificate, 13-SSL Refused, 14-Not Probed, 0- Unknown) • IpAddress • IsMonitored (True, False) • IssuerDN • SelfSigned (True, False) • SNIName
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>ReverseDNS</i> .
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.

Table 525: GET SSL Response Data

Name	Description
EndpointId	The Keyfactor Command reference GUID for the endpoint.
ReverseDNS	A string indicating the DNS name resolved for the endpoint based on the discovered IP address. If a host name could not be resolved, this will be the IP address.
SNIName	A string indicating the server name indication (SNI) of the endpoint, if found.
IpAddress	A string indicating the IP address of the endpoint.
Port	An integer indicating the port at which the endpoint was found.
CertificateFound	A Boolean indicating whether a certificate was found at the endpoint (true) or not (false).
AgentPoolName	A string indicating the name of the orchestrator pool that performed a scan (discovery or monitoring) on the endpoint.
NetworkName	A string indicating the name of the SSL network that performed a scan (discovery or monitoring) on the endpoint.
MonitorStatus	A Boolean indicating whether the endpoint should be monitored (true) or not (false).
CertificateCN	A string indicating the common name of the certificate that was found at the endpoint.
Reviewed	A Boolean indicating whether the endpoint has been reviewed (true) or not (false).

#### 2.2.27.7 GET SSL Networks

The GET /SSL/Networks method is used to retrieve one or more SSL networks from Keyfactor Command. Results can be limited to selected SSL networks using filtering, and URL parameters can be used to specify paging and the level of information detail. This method returns HTTP 200 OK on a success with details about the specified SSL networks.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: SslManagement: *Read* 

Table 526: GET SSL Networks Input Parameters

Name	In	Description	
queryString	Query	A string containing a query to limit the results (e.g. field1 -eq value1 AND field2 -gt value2). The default is to return all records. Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns for the same feature. For querying guidelines, refer to the Keyfactor Command Reference Guide: Using the Network Scan Details Search. The query fields supported for this endpoint are:  • Name  • Pool	
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.	
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.	
sortField	Query	A string containing the property by which the results should be sorted. Fields availab for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>Name</i> .	
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending. This field is optional.	

Table 527: GET SSL Networks Response Data

Name	Description				
NetworkId	The Keyfactor Co	ommand reference GUID for the SSL network. This GUID is automatically set by nand.			
Name	A string indicating the name for the SSL network.				
AgentPoolName	A string indicating the name of the orchestrator pool assigned to the SSL network. See <i>Orchestrator Pools Definition</i> in the <i>Keyfactor Command Reference Guide</i> for more information.				
AgentPoolId	The Keyfactor Co	ommand reference GUID for the orchestrator pool assigned to the SSL network.			
Description	A string indicatin	ng the description of the SSL network.			
Enabled	this is set to false	ndicates whether scanning is enabled for the SSL network (true) or not (false). If e, no new network scans will be scheduled but any current scan will finish if one when the status was changed from true to false.			
DiscoverSchedule	, ,	ng the discovery schedule for the SSL network group. The schedule can be off f the supported values. Supported schedule values are:			
	Name	Description			
	Immediate	A Boolean that indicates a job scheduled to run immediately (true) or not (false).			
	Interval	<b>Tip:</b> In some instances, jobs initially scheduled as <i>Immediate</i> will appear on a GET as <i>null</i> .			
		A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database.			
		Name Description			
		Minutes An integer indicating the number of minutes between each interval.			
		For example, every hour:			

Name	Description		
	Name	Description	
		"Interval": "Minutes }	
	Daily	A dictionary that	t indicates a job scheduled to run every day at the same arameter:
		Name	Description
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
		For example, da	illy at 11:30 pm:
		"Daily": {     "Time": }	"2022-02-25T23:30:00Z"
	Weekly		t indicates a job scheduled to run on a specific day or days he same time with the parameters:
		Name	Description
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
		Days	An array of values representing the days of the week on which to run the job. These can either be entered as integers (0 for Sunday, 1 for Monday, etc.) or as days of the week (e.g. "Sunday").
		For example, ev	ery Monday, Wednesday and Friday at 5:30 pm:
		"Weekly": {     "Days":     "Mond	1

# Name Description Name Description "Wednesday", "Friday" ], "Time": "2022-02-27T17:30:00Z" A dictionary that indicates a job scheduled to run on a specific day or days Monthly every month at the same time with the parameters: Name **Description** Time The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z). The number of the day, in the month, to run the job. Day For example, on the first of every month at 5:30 pm: "Monthly": { "Day": 1 "Time": "2022-02-27T17:30:00Z" ExactlyOnce A dictionary that indicates a job scheduled to run at the time specified with the parameter: Description Name Time The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z). For example, exactly once at 11:45 am: "ExactlyOnce": { "Time": "2022-02-27T11:45:00Z" Tip: In some instances, jobs initially scheduled as *Immediate* will appear on a GET as ExactlyOnce.

Name	Description					
MonitorSchedule	An array providing the monitoring schedule for the SSL network group. The schedule can be off (unset) or one of the supported values. Supported schedule values are:					
	Name	Description				
	Immediate	A Boolean that i (false).	ndicates a job scheduled to run immediately (true) or not			
		N/Z	some instances, jobs initially scheduled as <i>Immediate</i> will on a GET as <i>null</i> .			
	Interval	specified param	t indicates a job scheduled to run every x minutes with the eter. Any interval that is selected in the UI will be nutes when stored in the database.			
		Name	Description			
		Minutes	An integer indicating the number of minutes between each interval.			
		For example, ev	ery hour:			
		"Interval": "Minutes }				
	Daily	A dictionary that indicates a job scheduled to run every day at the same time with the parameter:				
		Name	Description			
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).			
		For example, da	ily at 11:30 pm:			
		"Daily": {     "Time": }	"2022-02-25T23:30:00Z"			

Name	Description				
	Name	Description			
	Weekly	A dictionary that indicates a job scheduled to run on a specific day or days every week at the same time with the parameters:			
		Name	Description		
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).		
		Days	An array of values representing the days of the week on which to run the job. These can either be entered as integers (0 for Sunday, 1 for Monday, etc.) or as days of the week (e.g. "Sunday").		
		For example, ev	very Monday, Wednesday and Friday at 5:30 pm:		
		"Fric	[ day", nesday",		
	Monthly		t indicates a job scheduled to run on a specific day or days the same time with the parameters:		
		Name	Description		
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).		
		Day	The number of the day, in the month, to run the job.		
		For example, or "Monthly": "Day": 1			

Name	Description				
	Name	Description			
		"Time": }	"2022-02-27T17:30:00Z"		
	ExactlyOnce	A dictionary that indicates a job scheduled to run at the time specified with the parameter:			
		Name	Description		
		Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).		
		"ExactlyOnc" "Time": }	actly once at 11:45 am:  ce": { "2022-02-27T11:45:00Z"  some instances, jobs initially scheduled as <i>Immediate</i> will		
		N/	on a GET as ExactlyOnce.		
Discov- erPercentComplete	An integer indicating the percentage complete for a discovery job. The percentage complete will be zero for small jobs for the entire duration of the job because this value is updated upon completion of each segment of a scan job (and small jobs generally consist of only one segment). All jobs will show 100% at completion. The counter resets when a new job begins.				
Monit- orPercentComplete	An integer indicating the percentage complete for a monitoring job. The percentage complete will be zero for small jobs for the entire duration of the job because this value is updated upon completion of each segment of a scan job (and small jobs generally consist of only one segment). All jobs will show 100% at completion. The counter resets when a new job begins.				
DiscoverStatus	An integer indica	ating the status of	the discovery job. Possible values are:		
	Value		Description		
	0		Unknown		
	1		Not Scheduled		

Name	Description			
	Value	Description		
	2	Running		
	3	Previously Scanned		
	4	Scheduled		
	5	Disabled		
	6	In Quiet Hours		
MonitorStatus	An integer indicating the status of the	monitoring job. Possible values are:		
	Value	Description		
	0	Unknown		
	1	Not Scheduled		
	2	Running		
	3	Previously Scanned		
	4	Scheduled		
	5	Disabled		
	6	In Quiet Hours		
DiscoverLastScanned	A string indicating the date and time, in lated as soon as the job is initiated and	n UTC, of the most recent discovery job. This field is populupdated when the job completes.		
MonitorLastScanned	A string indicating the date and time, in UTC, of the most recent monitoring job. This field is populated as soon as the job is initiated and updated when the job completes.			
SslAlertRecipients	An array of strings providing the list of recipients who will receive email messages regarding the status of SSL discovery and monitoring jobs.			
	Note: To improve performance in requests, data is not returned in this field for the GET /SSL/Networks method. Use the GET /SSL/Networks/{id} method to return data in this field.			
AutoMonitor	A Boolean that indicates whether auto (true) or not (false).	matic monitoring of discovered endpoints is enabled		

Name	Description
GetRobots	A Boolean that indicates whether orchestrators should perform a GET /robots.txt request during scans in order to behave like a webcrawler and provide an explanation of network activity (true) or not (false).
DiscoverTimeoutMs	An integer that indicates the amount of time (in milliseconds) the scan will wait (before timing out) to discover the endpoint. Shorter timeout periods will increase the overall scanning throughput, however they will also increase the chance of missing a certificate on a slow or congested network.
MonitorTimeoutMs	An integer that indicates the amount of time (in milliseconds) the scan will wait (before timing out) to receive the discovered endpoint certificate expiration details.
ExpirationAlertDays	An integer that indicates the number of days within which to begin providing warnings regarding upcoming expiration in notification email messages.
DiscoverJobParts	An integer that indicates the number of job parts that have been created for a discovery job.
MonitorJobParts	An integer that indicates the number of job parts that have been created for a monitoring job.
QuietHours	An array providing the list of scheduled quiet hour periods.

## 2.2.27.8 POST SSL Networks

The POST /SSL/Networks method is used to create an SSL network in Keyfactor Command. This method returns HTTP 200 OK on a success with details for the new SSL network.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: SslManagement: *Modify* 

Table 528: POST SSL Networks Input Parameters

Name	In	Description		
NetworkId	Body	The Keyfactor Command reference GUID for the SSL network. This GUID is automatically set by Keyfactor Command.		
Name	Body	Required. A string indicating the name for the SSL network.		
AgentPoolName	Body		ng indicating the name of the orchestrator pool assigned to the e in the Keyfactor Command Reference Guide for more information.	
AgentPoolId	Body	The Keyfactor C SSL network.	command reference GUID for the orchestrator pool assigned to the	
Description	Body	Required. A stri	ng indicating the description of the SSL network.	
Enabled	Body	A Boolean that indicates whether scanning is enabled for the SSL network (true) or not (false). If this is set to false, no new network scans will be scheduled but any current scan will finish if one was in progress when the status was changed from true to false.		
DiscoverSchedule	Body	An array providing the discovery schedule for the SSL network group. The schedule can be off (unset) or one of the supported values. Supported schedule values are:		
		Name	Description	
		Immediate A Boolean that indicates a job scheduled to run immediately (true not (false).		
			<b>Tip:</b> In some instances, jobs initially scheduled as <i>Imme-diate</i> will appear on a GET as <i>null</i> .	
		Interval	A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database.	
			Name Description	
			Minutes An integer indicating the number of minutes between each interval.	
			For example, every hour:	
			"Interval": {     "Minutes": 60	

Name	In	Description		
		Name	Description	
			}	
		Daily	A dictionary tha same time with	t indicates a job scheduled to run every day at the the parameter:
			Name	Description
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
			For example, da	ily at 11:30 pm:
			"Daily": {     "Time": }	"2022-02-25T23:30:00Z"
		Weekly		t indicates a job scheduled to run on a specific day or at the same time with the parameters:
			Name	Description
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
			Days	An array of values representing the days of the week on which to run the job. These can either be entered as integers (0 for Sunday, 1 for Monday, etc.) or as days of the week (e.g. "Sunday").
			For example, ev "Weekly": {     "Days":     "Mond	[

Name	In	Description		
		Name	Description	
			"Frid	esday", ay" "2022-02-27T17:30:00Z"
		Monthly		t indicates a job scheduled to run on a specific day or th at the same time with the parameters:
			Name	Description
		ExactlyOnc- e	Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
			Day	The number of the day, in the month, to run the job.
			"Monthly": "Day": 1	
			A dictionary tha specified with the	t indicates a job scheduled to run at the time ne parameter:
			Name	Description
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
			"ExactlyOnc	e": { "2022-02-27T11:45:00Z"

Name	In	Description		
		Name	Description	
			Tip: In some instances, jobs initially scheduled as <i>Immediate</i> will appear on a GET as <i>ExactlyOnce</i> .	
MonitorSchedule	MonitorSchedule Body		ling the monitoring schedule for the SSL network group. The schedule can or one of the supported values. Supported schedule values are:	
		Name	Description	
		Immediate	A Boolean that indicates a job scheduled to run immediately (true) or not (false).	
			Tip: In some instances, jobs initially scheduled as <i>Immediate</i> will appear on a GET as <i>null</i> .	
		Interval	A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database.	
			Name Description	
			Minutes An integer indicating the number of minutes between each interval.	
			For example, every hour:	
	Daily		"Interval": {     "Minutes": 60 }	
				A dictionary that indicates a job scheduled to run every day at the same time with the parameter:
			Name Description	
				Time The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).

Name	In	Description		
		Name	Description	
			For example, da	ily at 11:30 pm:
			"Daily": {     "Time": }	"2022-02-25T23:30:00Z"
		Weekly		t indicates a job scheduled to run on a specific day or k at the same time with the parameters:
			Name	Description
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
			Days	An array of values representing the days of the week on which to run the job. These can either be entered as integers (0 for Sunday, 1 for Monday, etc.) or as days of the week (e.g. "Sunday").
			"Weekly": {     "Days":     "Mond     "Wedn     "Frid	[ day", nesday",
		Monthly		t indicates a job scheduled to run on a specific day or th at the same time with the parameters:
			Name	Description
			Time	The date and time to next run the job. The date

Name	In	Description			
		Name	Description		
			Name	Description	
				and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
			Day	The number of the day, in the month, to run the job.	
			"Monthly": "Day": 1		
		ExactlyOnc- e	A dictionary that indicates a job scheduled to run at the time specified with the parameter:		
			Name	Description	
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
			For example, ex	actly once at 11:45 am:	
			"ExactlyOnd "Time":	ce": { "2022-02-27T11:45:00Z"	
				some instances, jobs initially scheduled as <i>Imme-</i> ill appear on a GET as <i>ExactlyOnce</i> .	
Discov- erPercentComplete	Body	An integer indicating the percentage complete for a discovery job. The percentage complete will be zero for small jobs for the entire duration of the job because this value is updated upon completion of each segment of a scan job (and small jobs generally consist of only one segment). All jobs will show 100% at completion. The counter resets when a new job begins. This field is for reference and is not configurable.			
Monit-	Body	An integer indic	cating the percent	age complete for a monitoring job. The percentage	

Name	In	Description		
orPercentComplete		complete will be zero for small jobs for the entire duration of the job because this value is updated upon completion of each segment of a scan job (and small jobs generally consist of only one segment). All jobs will show 100% at completion. The counter resets when a new job begins. This field is for reference and is not configurable.		
DiscoverStatus	Body	An integer indicating the status of the discovery job. Possible values are:		
		Value	Description	
		0	Unknown	
		1	Not Scheduled	
		2	Running	
		3	Previously Scanned	
		4	Scheduled	
		5	Disabled	
		6	In Quiet Hours	
MonitorStatus	Body	An integer indicating the status of the monitoring job. Possible values are:		
		Value	Description	
		0	Unknown	
		1	Not Scheduled	
		2	Running	
		3	Previously Scanned	
		4	Scheduled	
		5	Disabled	
		6	In Quiet Hours	
Discov- erLastScanned	Body	A string indicating the date and time, in UTC, of the most recent discovery job. This field is populated as soon as the job is initiated and updated when the job completes. This field is for reference and is not configurable.		
MonitorLastScanned	Body	A string indicating the date and time, in UTC, of the most recent monitoring job. This field is populated as soon as the job is initiated and updated when the job completes.		

Name	In	Description		
		This field is for reference and is not configurable.		
SsIAlertRecipients	Body	An array of strings providing the list of recipients who will receive email messages regarding the status of SSL discovery and monitoring jobs.		
		Note: To improve performance in requests, data is not returned in this field for the GET /SSL/Networks method. Use the GET /SSL/Networks/{id} method to return data in this field.		
AutoMonitor	Body	A Boolean that indicates whether automatic monitoring of discovered endpoints is enabled (true) or not (false).		
GetRobots	Body	A Boolean that indicates whether orchestrators should perform a GET /robots.txt request during scans in order to behave like a webcrawler and provide an explanation of network activity (true) or not (false).		
DiscoverTimeoutMs	Body	An integer that indicates the amount of time (in milliseconds) the scan will wait (before timing out) to discover the endpoint. Shorter timeout periods will increase the overall scanning throughput, however they will also increase the chance of missing a certificate on a slow or congested network.		
MonitorTimeoutMs	Body	An integer that indicates the amount of time (in milliseconds) the scan will wait (before timing out) to receive the discovered endpoint certificate expiration details.		
ExpirationAlertDays	Body	An integer that indicates the number of days within which to begin providing warnings regarding upcoming expiration in notification email messages.		
DiscoverJobParts	Body	An integer that indicates the number of job parts that have been created for a discovery job. This field is for reference and is not configurable.		
MonitorJobParts	Body	An integer that indicates the number of job parts that have been created for a monitoring job. This field is for reference and is not configurable.		
QuietHours	Body	An array providing the list of scheduled quiet hour periods. For example:		
		<pre>"QuietHours": [</pre>		

Name	In	Description		
		"EndTime": "2022-11-27T16:00:08Z" } ]		

Table 529: POST SSL Networks Response Data

Name	Description			
NetworkId	The Keyfactor Command reference GUID for the SSL network. This GUID is automatically set by Keyfactor Command.			
Name	A string indicating the name for the SSL network.			
AgentPoolName	A string indicating the name of the orchestrator pool assigned to the SSL network. See Orchestrator Pools Definition in the Keyfactor Command Reference Guide for more information.			
AgentPoolId	The Keyfactor Command reference GUID for the orchestrator pool assigned to the SSL network.			
Description	A string indicating the description of the SSL network.			
Enabled	A Boolean that indicates whether scanning is enabled for the SSL network (true) or not (false). If this is set to false, no new network scans will be scheduled but any current scan will finish if one was in progress when the status was changed from true to false.			
DiscoverSchedule	An array providing the discovery schedule for the SSL network group.			
MonitorSchedule	An array providing the monitoring schedule for the SSL network group.			
DiscoverPercentComplete	An integer indicating the percentage complete for a discovery job. The percentage complete will be zero for small jobs for the entire duration of the job because this value is updated upon completion of each segment of a scan job (and small jobs generally consist of only one segment). All jobs will show 100% at completion. The counter resets when a new job begins.			
MonitorPercentComplete	An integer indicating the percentage complete for a monitoring job. The percentage complete will be zero for small jobs for the entire duration of the job because this value is updated upon completion of each segment of a scan job (and small jobs generally consist of only one segment). All jobs will show 100% at completion. The counter resets when a new job begins.			
DiscoverStatus	An integer indicating the status of the discovery job. Possible values are:			
	Value Description			
	0 Unknown			

Name	Description			
	Value	Description		
	1	Not Scheduled		
	2	Running		
	3	Previously Scanned		
	4	Scheduled		
	5	Disabled		
	6	In Quiet Hours		
MonitorStatus	An integer indicating the status of t	he monitoring job. Possible values are:		
	Value	Description		
	0	Unknown		
	1	Not Scheduled		
	2	Running		
	3	Previously Scanned		
	4	Scheduled		
	5	Disabled		
	6	In Quiet Hours		
DiscoverLastScanned	A string indicating the date and time, in UTC, of the most recent discovery job. This field is populated as soon as the job is initiated and updated when the job completes.			
MonitorLastScanned	A string indicating the date and time, in UTC, of the most recent monitoring job. This field is populated as soon as the job is initiated and updated when the job completes.			
SslAlertRecipients	An array of strings providing the list of recipients who will receive email messages regarding the status of SSL discovery and monitoring jobs.			
	Note: To improve performance in requests, data is not returned in this field for the GET /SSL/Networks method. Use the GET /SSL/Networks/{id} method to return data in this field.			
AutoMonitor	A Boolean that indicates whether a	utomatic monitoring of discovered endpoints is		

Name	Description			
	enabled (true) or not (false).			
GetRobots	A Boolean that indicates whether orchestrators should perform a GET /robots.txt request during scans in order to behave like a webcrawler and provide an explanation of network activity (true) or not (false).			
Discover Timeout Ms	An integer that indicates the amount of time (in milliseconds) the scan will wait (before timing out) to discover the endpoint. Shorter timeout periods will increase the overall scanning throughput, however they will also increase the chance of missing a certificate on a slow or congested network.			
MonitorTimeoutMs	An integer that indicates the amount of time (in milliseconds) the scan will wait (before timing out) to receive the discovered endpoint certificate expiration details.			
ExpirationAlertDays	An integer that indicates the number of days within which to begin providing warnings regarding upcoming expiration in notification email messages.			
DiscoverJobParts	An integer that indicates the number of job parts that have been created for a discovery job.			
MonitorJobParts	An integer that indicates the number of job parts that have been created for a monitoring job.			
QuietHours	An array providing the list of scheduled quiet hour periods.			

### 2.2.27.9 PUT SSL Networks

The PUT /SSL/Networks method is used to update an SSL network in Keyfactor Command. This method returns HTTP 200 OK on a success with details for the SSL network.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: SslManagement: Modify



Warning: Any previously populated fields that are not submitted with their full existing data using this method will be cleared of their existing data. When using this method, you should first do a GET to retrieve all the values for the record you want to update, enter corrected data into the field(s) you want to update, and then submit all the fields using PUT, including the fields that contain values but which you are not changing.

Table 530: PUT SSL Networks Input Parameters

Name	In	Description		
NetworkId	Body	The Keyfactor Command reference GUID for the SSL network. This GUID is automatically set by Keyfactor Command.		
Name	Body	Required. A stri	ing indicating the name for the SSL network.	
AgentPoolName	Body		ing indicating the name of the orchestrator pool assigned to the e in the Keyfactor Command Reference Guide for more information.	
AgentPoolId	Body	The Keyfactor C SSL network.	Command reference GUID for the orchestrator pool assigned to the	
Description	Body	Required. A stri	ing indicating the description of the SSL network.	
Enabled	Body	A Boolean that indicates whether scanning is enabled for the SSL network (true) or not (false). If this is set to false, no new network scans will be scheduled but any current scan will finish if one was in progress when the status was changed from true to false.		
DiscoverSchedule	Body	An array providing the discovery schedule for the SSL network group. The schedule can be off (unset) or one of the supported values. Supported schedule values are:		
		Name  Description  Immediate  A Boolean that indicates a job scheduled to run immediately (true) not (false).		
			<b>Tip:</b> In some instances, jobs initially scheduled as <i>Immediate</i> will appear on a GET as <i>null</i> .	
		Interval	A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database.	
			Name Description	
			Minutes An integer indicating the number of minutes between each interval.	
			For example, every hour:	
			"Interval": {     "Minutes": 60	

Name	In	Description		
		Name	Description	
			}	
		Daily	A dictionary tha same time with	t indicates a job scheduled to run every day at the the parameter:
			Name	Description
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
			For example, da	ily at 11:30 pm:
			"Daily": {     "Time": }	"2022-02-25T23:30:00Z"
		Weekly		t indicates a job scheduled to run on a specific day or at the same time with the parameters:
			Name	Description
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
			Days	An array of values representing the days of the week on which to run the job. These can either be entered as integers (0 for Sunday, 1 for Monday, etc.) or as days of the week (e.g. "Sunday").
			For example, ev "Weekly": {     "Days":     "Mond	[

Name	In	Description		
		Name	Description	
			"Frid	esday", ay" "2022-02-27T17:30:00Z"
		Monthly		t indicates a job scheduled to run on a specific day or the the same time with the parameters:
			Name	Description
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
			Day	The number of the day, in the month, to run the job.
			"Monthly": "Day": 1	
		ExactlyOnc- e	A dictionary that specified with th	t indicates a job scheduled to run at the time ne parameter:
			Name	Description
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
			"ExactlyOnc	e": { "2022-02-27T11:45:00Z"

Name	In	Description		
		Name	Description	
			Tip: In some instances, jobs initially scheduled as <i>Immediate</i> will appear on a GET as <i>ExactlyOnce</i> .	
MonitorSchedule	Body		ling the monitoring schedule for the SSL network group. The schedule can or one of the supported values. Supported schedule values are:	
		Name Description		
		Immediate	A Boolean that indicates a job scheduled to run immediately (true) or not (false).	
			Tip: In some instances, jobs initially scheduled as <i>Imme-diate</i> will appear on a GET as <i>null</i> .	
		Interval	A dictionary that indicates a job scheduled to run every x minutes with the specified parameter. Any interval that is selected in the UI will be converted to minutes when stored in the database.	
			Name Description	
			For example, every hour:	
			"Interval": {     "Minutes": 60 }	
		Daily	A dictionary that indicates a job scheduled to run every day at the same time with the parameter:	
			Name Description	
			Time The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	

Name	In	Description		
		Name	Description	
			For example, da	ily at 11:30 pm:
			"Daily": {     "Time": }	"2022-02-25T23:30:00Z"
		Weekly		t indicates a job scheduled to run on a specific day or k at the same time with the parameters:
			Name	Description
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
			Days	An array of values representing the days of the week on which to run the job. These can either be entered as integers (0 for Sunday, 1 for Monday, etc.) or as days of the week (e.g. "Sunday").
			"Weekly": {     "Days":     "Mond     "Wedn     "Frid	[ day", nesday",
		Monthly		t indicates a job scheduled to run on a specific day or th at the same time with the parameters:
			Name	Description
			Time	The date and time to next run the job. The date

Name	In	Description			
		Name	Description		
			Name	Description	
				and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
			Day	The number of the day, in the month, to run the job.	
			"Monthly": "Day": 1		
		ExactlyOnc- e	A dictionary that indicates a job scheduled to run at the time specified with the parameter:		
			Name	Description	
				Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).
			For example, ex	actly once at 11:45 am:	
			"ExactlyOnd "Time":	ce": { "2022-02-27T11:45:00Z"	
				some instances, jobs initially scheduled as <i>Imme-</i> ill appear on a GET as <i>ExactlyOnce</i> .	
Discov- erPercentComplete	Body	complete will b is updated upor consist of only	e zero for small jo n completion of ea one segment). All	age complete for a discovery job. The percentage bs for the entire duration of the job because this value ach segment of a scan job (and small jobs generally jobs will show 100% at completion. The counter resets is for reference and is not configurable.	
Monit-	Body	An integer indic	cating the percent	age complete for a monitoring job. The percentage	

Name	In	Description		
orPercentComplete		complete will be zero for small jobs for the entire duration of the job because this value is updated upon completion of each segment of a scan job (and small jobs generally consist of only one segment). All jobs will show 100% at completion. The counter resets when a new job begins. This field is for reference and is not configurable.		
DiscoverStatus	Body	An integer indicating the status of the discovery job. Possible values are:		
		Value	Description	
		0	Unknown	
		1	Not Scheduled	
		2	Running	
		3	Previously Scanned	
		4	Scheduled	
		5	Disabled	
		6	In Quiet Hours	
MonitorStatus	Body	An integer indicating the status of the monitoring job. Possible values are:		
		Value	Description	
		0	Unknown	
		1	Not Scheduled	
		2	Running	
		3	Previously Scanned	
		4	Scheduled	
		5	Disabled	
		6	In Quiet Hours	
Discov- erLastScanned	Body	A string indicating the date and time, in UTC, of the most recent discovery job. This field is populated as soon as the job is initiated and updated when the job completes. This field is for reference and is not configurable.		
MonitorLastScanned	Body	A string indicating the date and time, in UTC, of the most recent monitoring job. This field is populated as soon as the job is initiated and updated when the job completes.		

Name	In	Description	
		This field is for reference and is not configurable.	
SsIAlertRecipients	Body	An array of strings providing the list of recipients who will receive email messages regarding the status of SSL discovery and monitoring jobs.	
		Note: To improve performance in requests, data is not returned in this field for the GET /SSL/Networks method. Use the GET /SSL/Networks/{id} method to return data in this field.	
AutoMonitor	Body	A Boolean that indicates whether automatic monitoring of discovered endpoints is enabled (true) or not (false).	
GetRobots	Body	A Boolean that indicates whether orchestrators should perform a GET /robots.txt request during scans in order to behave like a webcrawler and provide an explanation of network activity (true) or not (false).	
DiscoverTimeoutMs	Body	An integer that indicates the amount of time (in milliseconds) the scan will wait (before timing out) to discover the endpoint. Shorter timeout periods will increase the overall scanning throughput, however they will also increase the chance of missing a certificate on a slow or congested network.	
MonitorTimeoutMs	Body	An integer that indicates the amount of time (in milliseconds) the scan will wait (before timing out) to receive the discovered endpoint certificate expiration details.	
ExpirationAlertDays	Body	An integer that indicates the number of days within which to begin providing warnings regarding upcoming expiration in notification email messages.	
DiscoverJobParts	Body	An integer that indicates the number of job parts that have been created for a discovery job. This field is for reference and is not configurable.	
MonitorJobParts	Body	An integer that indicates the number of job parts that have been created for a monitoring job. This field is for reference and is not configurable.	
QuietHours	Body	An array providing the list of scheduled quiet hour periods. For example:	
		<pre>"QuietHours": [</pre>	

Name	In	Description	
		"EndTime": "2022-11-27T16:00:08Z" } ]	

Table 531: PUT SSL Networks Response Data

Name	Description	
NetworkId	The Keyfactor Command reference GUID for the SSL network. This GUID is automatically set by Keyfactor Command.	
Name	A string indicating the name for the SSL network.	
AgentPoolName	A string indicating the name of the orchestrator pool assigned to the SSL network. See Orchestrator Pools Definition in the Keyfactor Command Reference Guide for more information.	
AgentPoolId	The Keyfactor Command reference GUID for the orchestrator pool assigned to the SSL network.	
Description	A string indicating the description of the SSL network.	
Enabled	A Boolean that indicates whether scanning is enabled for the SSL network (true) or not (false). If this is set to false, no new network scans will be scheduled but any current scan will finish if one was in progress when the status was changed from true to false.	
DiscoverSchedule	An array providing the discovery schedule for the SSL network group.	
MonitorSchedule	An array providing the monitoring schedule for the SSL network group.	
DiscoverPercentComplete	An integer indicating the percentage complete for a discovery job. The percentage complete will be zero for small jobs for the entire duration of the job because this value is updated upon completion of each segment of a scan job (and small jobs generally consist of only one segment). All jobs will show 100% at completion. The counter resets when a new job begins.	
MonitorPercentComplete	An integer indicating the percentage complete for a monitoring job. The percentage complete will be zero for small jobs for the entire duration of the job because this value is updated upon completion of each segment of a scan job (and small jobs generally consist of only one segment). All jobs will show 100% at completion. The counter resets when a new job begins.	
DiscoverStatus	An integer indicating the status of the discovery job. Possible values are:	
	Value Description	
	0 Unknown	

Name	Description		
	Value	Description	
	1	Not Scheduled	
	2	Running	
	3	Previously Scanned	
	4	Scheduled	
	5	Disabled	
	6	In Quiet Hours	
MonitorStatus	An integer indicating the status of t	he monitoring job. Possible values are:	
	Value	Description	
	0	Unknown	
	1	Not Scheduled	
	2	Running	
	3	Previously Scanned	
	4	Scheduled	
	5	Disabled	
	6	In Quiet Hours	
DiscoverLastScanned	A string indicating the date and time, in UTC, of the most recent discovery job. This field is populated as soon as the job is initiated and updated when the job completes.		
MonitorLastScanned	A string indicating the date and time, in UTC, of the most recent monitoring job. This field is populated as soon as the job is initiated and updated when the job completes.		
SslAlertRecipients	An array of strings providing the list of recipients who will receive email messages regarding the status of SSL discovery and monitoring jobs.		
	Note: To improve performance in requests, data is not returned in this field for the GET /SSL/Networks method. Use the GET /SSL/Networks/{id} method to return data in this field.		
AutoMonitor	A Boolean that indicates whether a	utomatic monitoring of discovered endpoints is	

Name	Description
	enabled (true) or not (false).
GetRobots	A Boolean that indicates whether orchestrators should perform a GET /robots.txt request during scans in order to behave like a webcrawler and provide an explanation of network activity (true) or not (false).
Discover Timeout Ms	An integer that indicates the amount of time (in milliseconds) the scan will wait (before timing out) to discover the endpoint. Shorter timeout periods will increase the overall scanning throughput, however they will also increase the chance of missing a certificate on a slow or congested network.
MonitorTimeoutMs	An integer that indicates the amount of time (in milliseconds) the scan will wait (before timing out) to receive the discovered endpoint certificate expiration details.
ExpirationAlertDays	An integer that indicates the number of days within which to begin providing warnings regarding upcoming expiration in notification email messages.
DiscoverJobParts	An integer that indicates the number of job parts that have been created for a discovery job.
MonitorJobParts	An integer that indicates the number of job parts that have been created for a monitoring job.
QuietHours	An array providing the list of scheduled quiet hour periods.

## 2.2.27.10 GET SSL Endpoints ID History

The GET /SSL/Endpoints/{id}/History method is used to return a list of history found for a given SSL endpoint. URL parameters can be used to specify paging and the level of information detail. This method returns HTTP 200 OK on a success with details for the specified endpoint.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: SslManagement: *Read* 

Table 532: GET SSL Endpoints {id} History Input Parameters

Name	In	Description
id	Path	Required. The Keyfactor Command reference GUID for the SSL endpoint for which to return history information.  Use the GET /SSL method (see GET SSL on page 1104) to retrieve a list of all the SSL endpoints to determine the GUID of the desired endpoint.
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.

Table 533: GET SSL Endpoints {id} History Response Data

Name	Description		
HistoryId	The Keyfactor Command reference GUID for the history entry.		
EndpointId	The Keyfactor Command refere	ence GUID for the endpoint with which the history is associated.	
AuditId	The Keyfactor Command ID use	ed to track progress during scan jobs.	
Timestamp	The date and time the history of	entry was created.	
Status	An integer containing the statu values are:	is of the scan for which the history item was created. The possible	
	Value	Description	
	0	Unknown	
	1	TimeOutConnecting	
	2	ExceptionConnecting	
	3	TimeoutDownloading	
	4	ExceptionDownloading	
	5	NotSsl	
	6	CertificateFound	
	7	ExceptionInSql	
	8	InvalidOrUnreachableHost	
	9	ConnectionRefused	
	10	BadSslHandshake	
	11	ClientAuthenticationFailed	
	12	NoCertificate	
	13	SslRefused	
	14	NotProbed	

Name	Description			
JobType	An integer containing the type of scan job from which the history entry was created. The possible values are:			
	Value	Description		
	0	Unknown		
	1	Discovery		
	2	Monitoring		
	3	Compliance		
ProbeType	An integer containing the type history entry was created. The	e of connection made to the endpoint for the scan from which the e possible values are:		
	Value	Description		
	2	SSLv2		
	3	TLS		
ReverseDNS	A string indicating the DNS name of the endpoint resolved based on the discovered IP address at the time the history entry was created. If a host name could not be resolved, this will be the IP address.			
HistoryCertificates	An array of certificates found a created. Information includes	at the endpoint during the scan from which the history entry was s:		
	Name	Description		
	Id	An integer indicating the Keyfactor Command reference ID of the certificate.		
	IssuedDN	A string indicating the distinguished name of the certificate.		
	SerialNumber	A string indicating the serial number of the certificate.		
	NotBefore	The date, in UTC, on which the certificate was issued by the certificate authority.		
	NotAfter	The date, in UTC, on which the certificate expires.		
	SigningAlgorithm	A string indicating the algorithm used to sign the certificate.		

Name	Description		
	Name	Description	
	Thumbprint	A string indicating the thumbprint of the certificate.	
	IssuerDN	A string indicating the distinguished name of the issuer.	
	IssuedCN	A string indicating the common name of the certificate.	

Name	Description			
	Name Description			
	SubjectAltNameElements	An array containing the subject alternative name elements of the certificate. SAN data includes:		
		Name	Description	
		Id		aining the Keyfactor rence ID of the SAN
		Value	A string indicati Element.	ng the value of the SAN
		Туре		aining the type of SAN ossible values are:
			Value	Description
			0	Other Name
			1	RFC 822 Name
			2	DNS Name
			3	X400 Address
			4	Directory Name
			5	Ediparty Name
			6	Uniform Resource Iden- tifier
			7	IP Address
			8	Registered Id
			100	MS_NTPrincipalName
			101	MS_NTDSReplication
			999	Unknown
		ValueHash	A string indicati	ng a hash of the SAN value.

#### 2.2.27.11 GET SSL Networks ID Parts

The GET /SSL/Networks/{id}/Parts method returns a list of scan job segments for an SSL network defined in Keyfactor Command. This method returns HTTP 200 OK on a success with the scan job segments for the specified SSL network. The results will only include more than one segment if the SSL management job was broken up into segments due to the number of endpoints it contained. The number of endpoints per segment is configurable (see the SSL Maximum Discovery Scan Job Size and SSL Maximum Monitoring Scan Job Size settings in Application Settings: Agents Tab in the Keyfactor Command Reference Guide). The results from this method are of the currently in progress job or the latest completed job.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: SslManagement: *Read* 

Table 534: GET SSL Networks {id} Parts Input Parameters

Name	In	Description
ID	Path	<b>Required</b> . The Keyfactor Command reference GUID for the SSL network for which to retrieve scan job segments.  Use the <i>GET /SSL/Networks</i> method (see <u>GET SSL Networks on page 1106</u> ) to retrieve a list of all the SSL networks to determine the SSL network's GUID.
queryString	Query	A string containing a query to limit the results (e.g. field1 -eq value1 AND field2 -gt value2). The default is to return all records. Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns for the same feature. For querying guidelines, refer to the Keyfactor Command Reference Guide: Using the Network Scan Details Search.
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>Status</i> .
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.

Table 535: GET SSL Networks {id} Parts Response Data

Name	Description	
ScanJobPartId	A string indicating the Keyfactor Command reference GUID for the scan job segment.	
Agent	A string indicating the client machine nam	ne of the orchestrator that ran the scan job segment.
Status	An integer indicating the status of the sca	n job segment. Possible values are:
	Value	Description
	1	Not Started
	2	In Progress
	3	Complete
StartTime	The date and time at which the scan job s this value will be null.	egment started in UTC. For jobs that have not yet started,
EndTime	The date and time at which the scan job s value will be null.	egment finished in UTC. For jobs that are in progress, this
EndpointCount	An integer indicating the number of endp	oints scanned for the segment.

# 2.2.27.12 POST SSL NetworkRanges

The POST /SSL/NetworkRanges method is used to add network ranges to a specified SSL network. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: SslManagement: *Modify* 

Table 536: POST SSL Network Ranges Input Parameters

Name	In	Description
NetworkId	Body	<b>Required</b> . The Keyfactor Command reference GUID for the SSL network.  Use the GET /SSL/Networks method (see <u>GET SSL Networks on page 1106</u> ) to retrieve a list of your defined SSL networks to determine the GUID of the SSL network you want to use.
Ranges	Ranges Body	<b>Required</b> . An array of strings indicating the value(s) for the network range(s), including the IP address, network notation or host name followed by the port or ports for scanning (e.g. 192.168.12.0/24:443).  For example:
		"Ranges": [ "192.168.12.0/24:443", "keyexample.com:443", "222.33.44.55:443" ]

### 2.2.27.13 PUT SSL NetworkRanges

The PUT /SSL/NetworkRanges method is used to update network ranges for a specified SSL network. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: SslManagement: *Modify* 



Warning: Any previously populated fields that are not submitted with their full existing data using this method will be cleared of their existing data. When using this method, you should first do a GET to retrieve all the values for the record you want to update, enter corrected data into the field(s) you want to update, and then submit all the fields using PUT, including the fields that contain values but which you are not changing.

Table 537: PUT SSL Network Ranges {id} Input Parameters

Name	In	Description
NetworkId	Body	Required. The Keyfactor Command reference GUID for the SSL network.  Use the GET /SSL/Networks method (see GET SSL Networks on page 1106) to retrieve a list of your defined SSL networks to determine the GUID of the SSL network you want to use.
Ranges	Ranges Body	<b>Required</b> . An array of strings indicating the value(s) for the network range(s), including the IP address, network notation or host name followed by the port or ports for scanning (e.g. 192.168.12.0/24:443).  For example:
		"Ranges": [ "192.168.12.0/24:443", "keyexample.com:443", "222.33.44.55:443" ]

#### 2.2.27.14 PUT SSL Endpoints Review Status

The PUT /SSL/Endpoints/ReviewStatus method is used to update the reviewed status of the specified endpoint. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: SslManagement: *Modify* 

Table 538: PUT SSL Endpoints Review Status Input Parameters

Name	In	Description
Id	Body	Required. A string indicating the Keyfactor Command reference GUID for the endpoint to be updated.  Use the GET /SSL method (see GET SSL on page 1104) to retrieve a list of all the SSL endpoints to determine the GUID of the desired endpoint.
Status	Body	<b>Required</b> . A Boolean indicating whether the endpoint should be marked as reviewed (true) or not (false).

### 2.2.27.15 PUT SSL Endpoints Monitor Status

The PUT /SSL/Endpoints/MonitorStatus method is used to update the monitoring status of the specified endpoint. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: SslManagement: *Modify* 

Table 539: PUT SSL Endpoints Monitor Status Input Parameters

Name	In	Description
Id	Body	Required. A string indicating the Keyfactor Command reference GUID for the endpoint to be updated.  Use the GET /SSL method (see GET SSL on page 1104) to retrieve a list of all the SSL endpoints to determine the GUID of the desired endpoint.
Status	Body	<b>Required</b> . A Boolean indicating whether monitoring should be enabled on this endpoint (true) or not (false).

## 2.2.27.16 PUT SSL Endpoints Review All

The PUT /SSL/Endpoints/ReviewAll method is used to update all endpoints in the given query to set the reviewed status to true. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see  $\underline{\text{Security Overview}}$ ) are required to use this feature: SslManagement:  $\underline{\textit{Modify}}$ 

Table 540: PUT SSL Endpoints Review All Input Parameter

Name	In	Description
Query	Query	A string containing a query to limit the endpoints that will be marked as reviewed (e.g. field1 -eq value1 AND field2 -gt value2). If this parameter is not supplied, all endpoints will be marked as reviewed. Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns. For querying guidelines, refer to the <i>Keyfactor Command Reference Guide</i> Using the Discovery Results Search Feature section.

### 2.2.27.17 PUT SSL Endpoints Monitor All

The PUT /SSL/Endpoint/MonitorAll method is used to update all endpoints in the given query to set the monitoring status to true. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: SslManagement: *Modify* 

Table 541: PUT SSL Endpoints Monitor All Input Parameter

Name	In	Description
Query	Query	A string containing a query to limit the endpoints that will be marked as monitored (e.g. field1 -eq value1 AND field2 -gt value2). If this parameter is not supplied, all endpoints will be marked as monitored. Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns. For querying guidelines, refer to the <i>Keyfactor Command Reference Guide</i> Using the Discovery Results Search Feature section.

#### 2.2.27.18 POST SSL Networks ID Scan

The POST /SSL/Networks/{id}/Scan method is used to initiate a scan job for an SSL network defined in Keyfactor Command. A scan may be manually initiated for a configured network at any time that a scan is not already running for the network or the network is not in quiet hours. When you initiate a scan, you can choose whether to run a discovery scan, a monitoring scan, or both. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: SslManagement: *Modify* 

Table 542: POST SSL Networks {id} Scan Input Parameters

Name	In	Description
id	Path	<b>Required</b> . A string indicating the Keyfactor Command reference GUID for the SSL network for which to initiate a manual scan.  Use the GET /SSL/Networks method (see GET SSL Networks on page 1106) to retrieve a list of all the SSL networks to determine the SSL network's GUID.
Discovery	Body	A Boolean indicating whether to initiate a manual discovery scan (true) or not (false).
Monitoring	Body	A Boolean indicating whether to initiate a manual monitoring scan (true) or not (false).

#### 2.2.27.19 POST SSL Networks ID Reset

The POST /SSL/Networks/{id}/Reset method is used to reset an SSL scan. Reset deletes all scan jobs, scan job parts, logical scan jobs, and current schedules associated with the selected network. The agent job status relating to the SSL scans is set to failed and completed, and the agent is forced to register for a new session. Afterward, *Scan Now* is enabled to allow you to initiate a manual scan. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: SslManagement: *Modify* 

Table 543: POST SSL Networks {id} Reset Input Parameters

Name	In	Description
id	Path	<b>Required</b> . A string indicating the Keyfactor Command reference GUID for the SSL network for which to reset.  Use the <i>GET /SSL/Networks</i> method (see <u>GET SSL Networks on page 1106</u> ) to retrieve a list of all the SSL networks to determine the SSL network's GUID.

## 2.2.27.20 POST SSL NetworkRanges Validate

The POST /SSL/NetworkRanges/Validate method ensures that network ranges supplied in the request are of valid structure. This endpoint returns 204 with no content upon success. Use this method to test a proposed network range before using POST /SSL/NetworkRanges or PUT /SSL/NetworkRanges to configure it for an SSL network.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: SslManagement: *Read* 

Table 544: POST SSL Network Ranges Validate Input Parameters

Name	In	Description
networkRangesToVerify	Body	Required. An array of network ranges to validate. For example:  ["10.5.4.0/24:443","192.168.12.0/16:443,22","keyexample.co m:443"]

#### 2.2.27.21 DELETE SSL Networks ID

The DELETE /SSL/Networks/{id} method is used to delete an SSL network with the specified GUID from Keyfactor Command. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: SslManagement: *Modify* 

Table 545: DELETE SSL Networks {id} Input Parameters

Name	In	Description
id	Path	<b>Required</b> . A string indicating the Keyfactor Command reference GUID for the SSL network to be deleted.  Use the <i>GET /SSL/Networks</i> method (see <u>GET SSL Networks on page 1106</u> ) to retrieve a list of all the SSL networks to determine the SSL network's GUID.

### 2.2.28 Status

The Status component of the Keyfactor API includes methods necessary to retrieve the current list of Keyfactor API endpoints.

Table 546: Status Endpoints

Endpoint	Method	Description	Link
/Endpoints	GET	Returns a list of the Keyfactor API endpoints.	GET Status Endpoints below

## 2.2.28.1 GET Status Endpoints

The GET /Status/Endpoints method returns a list of all the endpoints currently available for use in the Keyfactor API. There are no input parameters for this method. This method returns HTTP 200 OK on a success with a list of all the API endpoints available in the Keyfactor API.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: None

# 2.2.29 Templates

The Templates component of the Keyfactor API includes methods necessary to programmatically edit, import and retrieve templates. Editing a template in Keyfactor Command will only apply within the software.

Table 547: Templates Endpoints

Endpoint	Method	Description	Link
/{id}	GET	Returns information about the specified template.	GET Templates ID below
/Settings	GET	Returns the global template policy settings.	GET Templates Settings on page 1165
/Settings	PUT	Sets global values for template policy.	PUT Templates Settings on page 1171
/SubjectParts	GET	Returns a list of supported subject parts for template regular expressions and default subjects.	GET Templates Subject Parts on page 1184
/	GET	Returns a list of templates.	GET Templates on page 1185
/	PUT	Updates selected settings for the specified template.	PUT Templates on page 1195
/Import	POST	Import templates from a specified configuration tenant into Keyfactor Command	POST Templates/Import on page 1222

## 2.2.29.1 GET Templates ID

The GET /Templates/{id} method is used to retrieve a specified template from Keyfactor Command. This method returns HTTP 200 OK on a success with details about the requested template.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: PkiManagement: *Read* 

Table 548: GET Templates {id} Input Parameters

Name	In	Description	
id	Path	<b>Required</b> . An integer specifying the ID of the template in Keyfactor Command.	
		Use the $GET/Templates$ method (see $GET$ Templates on page 1185) to retrieve a list of all the templates to determine the template ID.	

Table 549: GET Templates {id} Response Data

Name	Description		
Id	An integer indicating the ID of the template in Keyfactor Command.		
CommonName	A string containing the common name (short name) of the template. This name typically does not contain spaces. For a template created using a Microsoft management tool, this will be the Microsoft template name. For a template generated for an EJBCA CA, this will be built using a naming scheme of <end entity="" name="" profile="">_<certificate name="" profile="">.This field is populated based on information retrieved from the CA and is not configurable.</certificate></end>		
TemplateName	A string containing the name of the template. For a template created using a Microsoft management tool, this will be the Microsoft template display name. For a template generated for an EJBCA CA, this will be built using a naming scheme of <end entity="" name="" profile=""> (<certificate name="" profile="">). This field is populated based on information retrieved from the CA and is not configurable.</certificate></end>		
Oid	A string containing the object ID of the template in Active Directory. For Microsoft templates, this field is populated from Active Directory. For EJBCA templates, this field is generated within Keyfactor Command as an object identifier, but does not follow official OID conventions. The field is not configurable.		
KeySize	A string indicating the minimum supported key size of the template as defined by the CA. The field is not configurable.		
КеуТуре	A string indicating the key type of the template as defined by the CA. The field is not configurable.		
ForestRoot	A string indicating the forest root of the template. For Microsoft templates, this field is populated from Active Directory and is not configurable.		
	Note: The ForestRoot has been replaced by the ConfigurationTenant from release 10, but is retained for backwards compatibility.		
ConfigurationTenant	A string indicating the configuration tenant of the template. For Microsoft templates, this field is populated from Active Directory. For EJBCA templates, this field is populated from the Keyfactor Command CA record. The field is not configurable.		
FriendlyName	A string indicating the Keyfactor Command friendly name of the template. Template friendly names, if configured, appear in the dropdowns for PFX enrollment, CSR enrollment, and CSR generation in place of the template names. This can be useful in environments where the template names are long or not very human readable.		
KeyRetention	A string indicating the type of key retention certificates enrolled with this template will use to		

Name	Description				
	store their private key in Keyfactor Command. The key retention object contains the following parameters:				
	Value	Description			
	None	The private key will not be retained.			
	Indefinite	The private key will be retained until it is explicitly deleted.			
	AfterExpiration	The private key will be retained until the specified number of days after the certificate expires ( <i>KeyRetentionDays</i> ), at which point it will be scheduled for deletion.			
	FromIssuance	The private key will be retained until the specified number of days after the date on which the certificate was issued (KeyRetentionDays), at which point it will be scheduled for deletion.			
KeyRetentionDays	An integer indicating the number of days a certificate's private key will be retained in Keyfactor Command before being scheduled for deletion, if private key retention is enabled.				
KeyArchival	A Boolean indicating whether the template has been configured with the key archival setting in Active Directory (true) or not (false). This is a reference field and is not configurable.				
EnrollmentFields	allow you to submit cu request attributes to th fits as:	ustom enrollment fields. These are configured on a per-template basis to stom fields with CSR enrollments and PFX enrollments to supply custom ne CA during the enrollment process. This functionality offers such bene-			
	<ul> <li>Preventing users requirements pe</li> </ul>	from requesting invalid certificates, based on your specific certificate r template.			
	Providing additional information to the CA with the CSR.				
	Once created on the template, these values are shown in Keyfactor Command on the CSR enrollment pages in the <i>Additional Enrollment Fields</i> section. The fields are mand during enrollment. The data will appear on the CA / Issued Certificates attribute table ficates enrolled with a template configured with Keyfactor Command enrollment field				
	database, but s	Note: These are not metadata fields, so they are not stored in the Keyfactor Command database, but simply passed through to the CA. The CA in turn could, via a gateway or policy module, use this data to perform required actions.			
	The enrollment fields object contains the following parameters:				

Name	Description			
	Name	Description		
	Id	An integer indicating the ID of the custom enrollment field.		
	Name	A string indicating the name of the custom enrollment field. This name will appear on the enrollment pages.		
	Options	For multiple choice values, an array of strings containing the value choices.		
	DataType	An integer indicating the parameter type. The options are:		
		Value Description		
		1 String: A free-form data entry field.		
		2 Multiple Choice: Provides a list of acceptable values for the field. The multiple choice values are provided in the <i>Options</i> parameter.		
MetadataFields	<ul> <li>An object containing template-level metadata field settings. Template-level metadata field configurations can override global metadata field configurations in these possible ways: <ul> <li>Configuration on the metadata field of required, optional or hidden.</li> <li>The default value for the metadata field.</li> <li>A regular expression defined for the field (string fields only) against which entered data will be validated along with its associated message.</li> <li>For fields of data type multiple choice, the list of values that appear in multiple choice dropdowns.</li> </ul> </li> <li>Metadata field settings defined on a template apply to enrollments made with that template only. Template-level metadata field settings, if defined, take precedence over global-level metadata field settings.</li> <li>The metadata fields object contains the following parameters:</li> </ul>			
	Name	Description		
	Id	The Keyfactor Command reference ID of the template-specific metadata setting.		
	DefaultValue	A string containing the default value defined for the metadata field for the specific template.		

template-specific settings.

Metadatald

An integer indicating the global metadata field associated with the

Name	Description		
	Name	Description	
	Validation	which data enterenters informated specified regular specified in the 'a-za-za (keyexam This regular expectonsist of some lowercase letterescores, periods, "@keyexample"	ting the template-specific regular expression against ered in a string field will be validated. When a user tion in a metadata field that does not match the expression, he or she will see the warning message to the message field. For example:  10-9'_\.\-]*@  10
	Enrollment	An integer that indicates how metadata fields should be handled on the PFX and CSR Enrollment pages. Possible values are:	
		Value	Description
		0	Optional Users have the option to either enter a value or not enter a value in the field.
		1	Required Users are required to enter data in the field when populating metadata fields on the PFX and CSR Enrollment pages. The field is not required on the certificate details or Add Certificate page.
		2	Hidden The field is hidden and does not appear on the PFX and CSR Enrollment pages. This field still appears on the certificate details and the Add Certificate page.
	Message	ation in a meta	ning a message to present when a user enters informdata field that does not match the template-specific ion (Validation field).
	Options	appear in the fi	ning a comma separated list of values that should eld dropdown for multiple choice fields.  y supported for metadata fields with data type multiple

Name	Description		
	Name	Description	
		choice.	
AllowedEn- rollmentTypes	options causes the Management Po appear in dropde configured for each	ating the type of enrollment allowed for the certificate template. Setting these he template to appear in dropdowns in the corresponding section of the ortal. In the case of CSR Enrollment and PFX Enrollment, the templates only owns on the enrollment pages if they are available for enrollment from a CA also nrollment within Keyfactor Command. See Adding or Modifying a CA Record in ammand Reference Guide for more information. Possible values are:	
	Value	Description	
	0	None	
	1	PFX Enrollment	
	2	CSR Enrollment	
	3	CSR Enrollment & PFX Enrollment	
	4	CSR Generation	
	5	CSR Generation & PFX Enrollment	
	6	CSR Generation & CSR Enrollment	
	7	CSR Enrollment, PFX Enrollment & CSR Generation	
TemplateRegexes	subject data. Reg template only. T regular expression	ning individual template-level regular expressions against which to validate the gular expressions defined on a template apply to enrollments made with that remplate-level regular expressions, if defined, take precedence over system-wide ons. For more information about system-wide regular expressions, see	

Name	Description		
	Name	Description	
RegEx		indicated subject par Keyfactor Command method will be valid: Use the GET/Templo Parts on page 1184)	ne regular expression against which data entered in the rt field (e.g. CN) in the enrollment pages of the Management Portal or using an API enrollment ated.  Intes/SubjectParts method (see GET Templates Subject to retrieve a list of all the supported subject parts.  Interest of the support
		Subject Part	Example
		CN (Common Name)	This regular expression specifies that the data entered in the field must consist of some number of characters in the first portion of the field made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly ".keyexample.com":  ^[a-zA-Z0-9' \.\-]*\.keyexample\.com\$  The default value for the Common Name regular expression is: .+  This requires entry of at least one character in the Common Name field in the enrollment pages.
		O (Organization)	This regular expression requires that the organization name entered in the field be one of "Key Example Inc."; "Key Example" or "Key Example Inc.":  ^(?:Key Example Inc Key Example Key Example, Inc\.)\$ The period in the final company name (Key Example, Inc.) needs to be escaped in the regular expression with a slash ("\") but the comma does not.
		OU (Organ- ization Unit)	This regular expression requires that the organizational unit entered in the field be one of these four departments:

Name Descript	ion			
Name	Description	Description		
	Subject Part	Example		
		^(?:IT HR Accounting E-Commerce)\$		
	L (City/Locality)	This regular expression requires that the city entered in the field be one of these five cities:  ^(?:Boston Chicago New York London Dallas)\$		
	ST (State/Province)	This regular expression requires that the state entered in the field be one of these eight states:  ^(?:Massachusetts Illinois New York Ontario Texas)\$		
	C (Country)	This regular expression requires that the country entered in the field be either US or CA:  ^(?:US CA)\$		
	E (Email)	This regular expression specifies that the data entered in the field must consist of some number of characters prior to the "@" made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly "@keyexample.com":  ^[a-zA-Z0-9'_ \.\-]*@keyexample\.com\$		
	DNS (Subject Alternative Name: DNS Name)	This regular expression specifies that the data entered in the field must consist of some number of characters in the first portion of the field made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly either ".keyexample1.com" or ".keyexample2.com":  ^[a-zA-Z0-9'_\.\-]*\. (?:keyexample1\.com keyexample2\.com)\$		
	IPv4 (Subject Alternative	This regular expression specifies that the data		

Name	Description		
	Name	Description	
		Subject Part	Example
		Name: IPv4 Address)	entered in the field must be exactly "130.101." followed by anywhere between 1 and 3 numbers followed by exactly "." followed by anywhere between 1 and 3 numbers:  ^130\.101\.(?:[0-9]{1,3})\.(?:[0-9]{1,3})\shape This regular expression specifies only that the IPv4 address is made up of 4 sets of between 1 and 3 numbers separated by periods:  ^(?:[0-9]{1,3}\.){3}[0-9]{1,3}\$
		IPv6 (Subject Alternative Name: IPv6 Address)	This regular expression specifies that the data entered in the field must be made up of eight sets of between one and four numbers and/or uppercase letters separated by colons:  ^(?:[A-F0-9]{1,4}:){7}[A-F0-9] {1,4}\$
	MAIL (Subject Alternative Name: Email)	This regular expression specifies that the data entered in the field must consist of some number of characters prior to the "@" made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly "@keyexample.com":  ^[a-zA-Z0-9'_ \.\-]*@keyexample\.com\$	
		UPN (Subject Alternative Name: User Prin- cipal Name)	This regular expression specifies that the data entered in the field must consist of some number of characters prior to the "@" made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly "@keyexample.com":  ^[a-zA-Z0-9'_ \.\-]*@keyexample\.com\$
	Error		e error message displayed to the user when the subject e CSR or entered for a PFX enrollment does not match

Name	Description		
	Name	Description	
		the given regular expression. Note that the error message already includes a leading string with the subject part (e.g. "Common Name:" or "Invalid CN provided:" depending on the interface used). Your custom message follows this.	
Template Defaults	An object containing individual template-level template default settings. Template defaults defined on a template apply to enrollments made with that template only. Template-level defaults, if defined, take precedence over system-wide template defaults. For more information about system-wide template defaults, see <a href="Metaplates-Settings-On-page 1165">GET Templates Settings on page 1165</a> . The template default object contains the following parameters:		
	Value	Description	
	SubjectPart	A string indicating the portion of the subject the default applies to (e.g. L for City/Locality).  Use the GET /Templates/SubjectParts method (see GET Templates  Subject Parts on page 1184) to retrieve a list of all the supported subject parts.	
	Value	A string containing the value to assign as the default for that subject part (e.g. Chicago).	
TemplatePolicy	An object containing the individual template-level template policy settings. Template policies defined on a template apply to enrollments made with that template only. Template-level policies, if defined, take precedence over system-wide template policies. For more information about system-wide template policies, see		

Name	Description		
	Value	Description	
		algorithms for ECC templates. These may be specified using the well-known OIDs for ECC algorithms or by friendly name. Well-known OIDs include:  • 1.2.840.10045.3.1.7 = P-256/prime256v1/secp256r1  • 1.3.132.0.34 = P-384/secp384r1  • 1.3.132.0.35 = P-521/secp521r1  When specifying by friendly name, do not include a slash (use "P-256", not "P-256/prime256v1/secp256r1").	
	AllowKeyReuse	A Boolean that indicates whether private key reuse is allowed (true) or not (false). This option applies to certificate renewals. By default, this is set to <i>true</i> at a system-wide level.	
	AllowWildcards	A Boolean that indicates whether wildcards are allowed (true) or not (false). By default, this is set to <i>true</i> at a system-wide level.	
	RFCEnforcement	A Boolean that indicates whether RFC 2818 compliance enforcement is enabled (true) or not (false). When this option is set to true, certificate enrollments made through Keyfactor Command for this template must include at least one DNS SAN. In the Keyfactor Command Management Portal, this causes the CN entered in PFX enrollment to automatically be replicated as a SAN, which the user can either change or accept. For CSR enrollment, if the CSR does not have a SAN that matches the CN, one will automatically be added to the certificate if this is set. By default, this is set to false at a system-wide level.	
	AllowEd448	A Boolean that indicates whether Ed448 key type is allowed (true) or not (false).	
	AllowEd25519	A Boolean that indicates whether Ed25519 key type is allowed (true) or not (false).	
UseAl- lowedRequesters	A Boolean that indicates whether the Restrict Allowed Requesters option should be enabled (true) or not (false). The Restrict Allowed Requesters option is used to select Keyfactor Command security roles that a user must belong to in order to successfully enroll for certificates in Keyfactor Command using this template. This is typically used for EJBCA templates and Microsoft templates that are not in the local Active Directory forest, since in these cases, Keyfactor Command cannot make use of the access control model of the CA itself to determine which users can enroll for certificates; this setting replaces that functionality. This setting is similar to setting request certificates for the selected security roles at the template level on a Microsoft CA. In addition to granting permissions at the template level, you need enable the		

Name	Description		
	Restrict Allowed Requesters option to grant permissions at the CA level. See <i>Adding or Modifying a CA Record</i> in the <i>Keyfactor Command Reference Guide</i> for more information.		
AllowedRequesters	An object containing the list of Keyfactor Command security roles—as strings—that have been granted enroll permission on the template.		
DisplayName	A string indicating the Keyfactor Command display name of the template. If a template friendly name is configured, this is used as the display name. If not, the template name is used. The display name appears in the dropdowns for PFX enrollment, CSR enrollment, and CSR generation. The display name is a generated field and is not directly configurable.		
RequiresApproval	A Boolean indicating whether the template has been configured with the Microsoft <i>CA certificate manager approval</i> option enabled ( <i>true</i> ) or not ( <i>false</i> ).		
	Important: Any templates that are configured on the Microsoft CA Issuance Requirements tab for CA certificate manager approval cannot be used for enrollment and associated alerting in Keyfactor Command without configuring private key retention. Any of the enabled private key retention settings (settings other than none as described for KeyRetention) will allow a template requiring manager approval to work with Keyfactor Command PFX and CSR enrollment.    Corp Web Server - RA Properties		
KeyUsage	An integer indicating the total key usage of the certificate. Key usage is stored in Active Directory as a single value made of a combination of values. The values that make up the key usage value include:		
	Value	Function	Description
	0	None	No key usage parameters.
	1	Encipherment Only	The key can be used for encryption only.
	2	CRL Signing	The key can be used to sign a certificate revocation list (CRL).

Name	Description			
	Value	Function	Description	
	4	Key Certificate Signing	The key can be used to sign certificates.	
	8	Key Agreement	The key can be used to determine key agreement, such as a key created using the Diffie-Hellman key agreement algorithm.	
	16	Data Encipherment	The key can be used for data encryption.	
	32	Key Encipherment	The key can be used for key encryption.	
	64	Nonrepudiation	The key can be used for authentication.	
	128	Digital Signature	The key can be used as a digital signature.	
	32768	Decipherment Only	The key can be used for decryption only.	
	For example, a value of 160 would represent a key usage of digital signature with key ement. A value of 224 would add nonrepudiation to those.			
ExtendedKeyUsages	An object containing the extended key usage information for the template. This field is populated from the CA and is not configurable. The extended key usage object contains the follow parameters:			
	Name	Description		
	Id	An integer indic Directory.	An integer indicating the ID of the extended key usage in Active Directory.	
	Oid	A string containing the object ID of the extended key usage.		
	DisplayName A string specifying the Server Authentication		ng the display name of the extended key usage (e.g. cation).	
Curve	A string indicating the OID of the elliptic curve algorithm configured for the template, for ECC templates. Well-known OIDs include:  • 1.2.840.10045.3.1.7 = P-256/prime256v1/secp256r1  • 1.3.132.0.34 = P-384/secp384r1  • 1.3.132.0.35 = P-521/secp521r1			

## 2.2.29.2 GET Templates Settings

The GET /Templates/Settings method is used to retrieve the global template policy settings Keyfactor Command. This method returns HTTP 200 OK on a success with details about the global template policy settings.



**Tip:** Template policies may also be set at an individual template level to apply to a single template (see <u>PUT Templates on page 1195</u>). Template policies set at the individual template level take precedence over template policies set at the global level.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: PkiManagement: *Read* 

There are no input parameters for this method.

TomplatoBogovos			Description		
TemplateRegexes	An object containing the system-wide template regular expression settings. These apply to all enrollments that are not otherwise overridden by individual template settings, including those that do not use a template (e.g. from a standalone CA). Regular expression details are:				
	Name	Description			
	SubjectPart	A string indicating the portion of the subject the regular expression applies (e.g. CN).			
	RegEx	A string specifying the regular expression against which data entered in the indicated subject part field (e.g. CN) in the enrollment pages of the Keyfactor Command Management Portal or using an API enrollment method will be validated.  Use the GET /Templates/SubjectParts method (see GET Templates Subject Parts on page 1184) to retrieve a list of all the supported subject parts.  The following are some regular expression examples:			
		Subject Part	Example		
		CN (Common Name)	This regular expression specifies that the data entered in the field must consist of some number of characters in the first portion of the field made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly ".keyexample.com":		
			^[a-zA-Z0-9'_ \.\-]*\.keyexample\.com\$  The default value for the Common Name regular expression is: .+  This requires entry of at least one character in the		
		O (Organization)	Common Name field in the enrollment pages.		
		O (Organization)	This regular expression requires that the organization name entered in the field be one of "Key Example Inc", "Key Example" or "Key Example Inc.":		
			^(?:Key Example Inc Key Example Key Example, Inc\.)\$ The period in the final company name (Key Example,		

Value	Description		
	Name	Description	
		Subject Part	Example
			Inc.) needs to be escaped in the regular expression with a slash ("\") but the comma does not.
		OU (Organization Unit)	This regular expression requires that the organizational unit entered in the field be one of these four departments:  ^(?:IT HR Accounting E-Commerce)\$
		L (City/Locality)	This regular expression requires that the city entered in the field be one of these five cities:  ^(?:Boston Chicago New York London Dallas)\$
		ST (State/Province)	This regular expression requires that the state entered in the field be one of these eight states:  ^(?:Massachusetts Illinois New York Ontario Texas)\$
		C (Country)	This regular expression requires that the country entered in the field be either US or CA:  ^(?:US CA)\$
		E (Email)	This regular expression specifies that the data entered in the field must consist of some number of characters prior to the "@" made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly "@keyexample.com":  ^[a-zA-Z0-9'_\.\-]*@keyexample\.com\$
		DNS (Subject Alternative Name: DNS Name)	This regular expression specifies that the data entered in the field must consist of some number of characters in the first portion of the field made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly either ".keyexample1.com" or ".keyexample2.com":

Value	Description		
	Name	Description	
		Subject Part	Example
			^[a-zA-Z0-9'_\.\-]*\. (?:keyexample1\.com keyexample2\.com )\$
		IPv4 (Subject Alternative Name: IPv4 Address)	This regular expression specifies that the data entered in the field must be exactly "130.101." followed by anywhere between 1 and 3 numbers followed by exactly "." followed by anywhere between 1 and 3 numbers:  ^130\.101\.(?:[0-9]{1,3})\.(?:[0-9]{1,3})\.(?:[0-9]{1,3})\$  This regular expression specifies only that the IPv4 address is made up of 4 sets of between 1 and 3 numbers separated by periods:  ^(?:[0-9]{1,3}\.){3}[0-9]{1,3}\$
		IPv6 (Subject Alternative Name: IPv6 Address)	This regular expression specifies that the data entered in the field must be made up of eight sets of between one and four numbers and/or uppercase letters separated by colons:  ^(?:[A-F0-9]{1,4}:){7}[A-F0-9]{1,4}\$
		MAIL (Subject Alternative Name: Email)	This regular expression specifies that the data entered in the field must consist of some number of characters prior to the "@" made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly "@keyexample.com":  ^[a-zA-Z0-9'_\.\-]*@keyexample\.com\$
		UPN (Subject Alternative Name: User Prin- cipal Name)	This regular expression specifies that the data entered in the field must consist of some number of characters prior to the "@" made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly "@keyexample.com":  ^[a-zA-Z0-9'_\.\-]*@keyexample\.com\$

Value	Description			
	Name	Description		
	Error	A string specifying the error message displayed to the user when the subject part referenced in the CSR or entered for a PFX enrollment does not match the given regular expression. Note that the error message already includes a leading string with the subject part (e.g. "Common Name:" or "Invalid CN provided:" depending on the interface used). Your custom message follows this.		
	For example:			
	<pre>"TemplateRegexes": [     {         "SubjectPart": "0",         "Regex": "^(?:Key Example Company Key Example Inc\.)\$",         "Error": "Organization must be Key Example, Inc or Key Example Company."     } ]</pre>			
TemplateDefaults	An object containing the system-wide template default settings. These apply to all enrollments that are not otherwise overridden by individual template settings, including those that do not use a template (e.g. from a standalone CA). Template default details are:			
	Value	Description		
	SubjectPart	A string indicating the portion of the subject the default applies to (e.g. L for City/Locality).		
	Value	A string containing the value to assign as the default for that subject part (e.g. Chicago).		
	For example:			
	<pre>"TemplateDefaults": [     {         "SubjectPart": "L",         "Value": "Denver"     },     {         "SubjectPart": "ST",         "Value": "Colorado"     } ]</pre>			

Note: See also the Subject Format application setting, which takes precedence over enroll-

Value	Description		
	ment defaults at both the system-wide and template level (see <i>Application Settings: Enroll-ment Tab</i> in the <i>Keyfactor Command Reference Guide</i> ) but does not apply to enrollment requests done through the Keyfactor API.		
TemplatePolicy	not otherwise overridden	ystem-wide template policy settings. These apply to all enrollments that are by individual template settings, including those that do not use a template A). Template policy details are:	
	Value	Description	
	RSAValidKeySizes	An object containing a comma-delimited list of integers defining the valid RSA key sizes supported for all templates used for enrollment. The supported values are:  • 2048 • 4096	
	ECCValidCurves	An object containing a list of strings defining the valid elliptic curve algorithms for ECC templates. These may be specified using the well-known OIDs for ECC algorithms or by friendly name. Well-known OIDs include:  • 1.2.840.10045.3.1.7 = P-256/prime256v1/secp256r1  • 1.3.132.0.34 = P-384/secp384r1  • 1.3.132.0.35 = P-521/secp521r1  When specifying by friendly name, do not include a slash (use "P-256", not "P-256/prime256v1/secp256r1").	
	AllowKeyReuse	A Boolean that indicates whether private key reuse is allowed (true) or not (false). This option allows to certificate renewals.	
	AllowWildcards	A Boolean that indicates whether wildcards are allowed (true) or not (false).	
	RFCEnforcement	A Boolean that indicates whether RFC 2818 compliance enforcement is enabled (true) or not (false). When this option is set to <i>true</i> , certificate enrollments made through Keyfactor Command for this template must include at least one DNS SAN. In the Keyfactor Command Management Portal, this causes the CN entered in PFX enrollment to automatically be replicated as a SAN, which the user can either change or accept. For CSR enrollment, if the CSR does not have a SAN that matches the CN, one will automatically be added to the certificate if this is set.	

Value	Description		
	Value	Description	
	AllowEd448	A Boolean that indicates whether Ed448 key type is allowed (true) or not (false).	
	AllowEd25519	A Boolean that indicates whether Ed25519 key type is allowed (true) or not (false).	
	For example:		
	"TemplatePolicy": {     "RSAValidKeySize         2048,         4096 ],     "ECCValidCurves"         "1.2.840.1004         "1.3.132.0.34         "1.3.132.0.35 ],     "AllowKeyReuse":     "AllowWildcards"     "RFCEnforcement"     "AllowEd448": fa     "AllowEd25519": }	s": [  : [ 5.3.1.7",  "  false, : true, : true, lse,	

## 2.2.29.3 PUT Templates Settings

The PUT /Templates/Settings method is used to create or update the global template policy settings in Keyfactor Command. This method returns HTTP 200 OK on a success with details about the template policy settings.



**Tip:** Template policies may also be set at an individual template level to apply to a single template (see <u>PUT Templates on page 1195</u>). Template policies set at the individual template level take precedence over template policies set at the global level.



**Note:** Global template settings replaced and expanded upon select enrollment-related applications settings in release 10.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: PkiManagement: *Modify* 



Warning: Any previously populated fields that are not submitted with their full existing data using this method will be cleared of their existing data. When using this method, you should first do a GET to retrieve all the values for the record you want to update, enter corrected data into the field(s) you want to update, and then submit all the fields using PUT, including the fields that contain values but which you are not changing.

Table 551: PUT Templates Settings Input Parameters

Value	Description		
TemplateRegexes	An object containing the system-wide template regular expression settings. These apply to all enrollments that are not otherwise overridden by individual template settings, including those that do not use a template (e.g. from a standalone CA). Regular expression details are:		
	Name	Description	
	SubjectPart	A string indicating the (e.g. CN).	portion of the subject the regular expression applies to
	RegEx	A string specifying the regular expression against which data entered in the indicated subject part field (e.g. CN) in the enrollment pages of the Keyfactor Command Management Portal or using an API enrollment method will be validated.  Use the GET /Templates/SubjectParts method (see GET Templates Subject Parts on page 1184) to retrieve a list of all the supported subject parts.  The following are some regular expression examples:	
		Subject Part	Example
		CN (Common Name)	This regular expression specifies that the data entered in the field must consist of some number of characters in the first portion of the field made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly ".keyexample.com":
			^[a-zA-Z0-9'_ \.\-]*\.keyexample\.com\$  The default value for the Common Name regular expression is: .+  This requires entry of at least one character in the
		0.(0	Common Name field in the enrollment pages.
		O (Organization)	This regular expression requires that the organization name entered in the field be one of "Key Example Inc", "Key Example" or "Key Example Inc.":
			^(?:Key Example Inc Key Example Key Example, Inc\.)\$ The period in the final company name (Key Example,
			Example, Inc\.)\$

Value	Description		
	Name	Description	
		Subject Part	Example
			Inc.) needs to be escaped in the regular expression with a slash ("\") but the comma does not.
		OU (Organization Unit)	This regular expression requires that the organizational unit entered in the field be one of these four departments:  ^(?:IT HR Accounting E-Commerce)\$
		L (City/Locality)	This regular expression requires that the city entered in the field be one of these five cities:  ^(?:Boston Chicago New York London Dallas)\$
		ST (State/Province)	This regular expression requires that the state entered in the field be one of these eight states:  ^(?:Massachusetts Illinois New York Ontario Texas)\$
		C (Country)	This regular expression requires that the country entered in the field be either US or CA:  ^(?:US CA)\$
		E (Email)	This regular expression specifies that the data entered in the field must consist of some number of characters prior to the "@" made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly "@keyexample.com":  ^[a-zA-Z0-9'_\.\-]*@keyexample\.com\$
		DNS (Subject Alternative Name: DNS Name)	This regular expression specifies that the data entered in the field must consist of some number of characters in the first portion of the field made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly either ".keyexample1.com" or ".keyexample2.com":

Value	Description		
	Name	Description	
		Subject Part	Example
			^[a-zA-Z0-9'_\.\-]*\. (?:keyexample1\.com keyexample2\.com )\$
		IPv4 (Subject Alternative Name: IPv4 Address)	This regular expression specifies that the data entered in the field must be exactly "130.101." followed by anywhere between 1 and 3 numbers followed by exactly "." followed by anywhere between 1 and 3 numbers:  ^130\.101\.(?:[0-9]{1,3})\.(?:[0-9]{1,3})\.(?:[0-9]{1,3})\$  This regular expression specifies only that the IPv4 address is made up of 4 sets of between 1 and 3 numbers separated by periods:  ^(?:[0-9]{1,3}\.){3}[0-9]{1,3}\$
		IPv6 (Subject Alternative Name: IPv6 Address)	This regular expression specifies that the data entered in the field must be made up of eight sets of between one and four numbers and/or uppercase letters separated by colons:  ^(?:[A-F0-9]{1,4}:){7}[A-F0-9]{1,4}\$
		MAIL (Subject Alternative Name: Email)	This regular expression specifies that the data entered in the field must consist of some number of characters prior to the "@" made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly "@keyexample.com":  ^[a-zA-Z0-9'_\.\-]*@keyexample\.com\$
		UPN (Subject Alternative Name: User Prin- cipal Name)	This regular expression specifies that the data entered in the field must consist of some number of characters prior to the "@" made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly "@keyexample.com":  ^[a-zA-Z0-9'_\.\-]*@keyexample\.com\$

Value	Description			
	Name	Description		
	1	A string specifying the error message displayed to the user when the subject part referenced in the CSR or entered for a PFX enrollment does not match the given regular expression. Note that the error message already includes a leading string with the subject part (e.g. "Common Name:" or "Invalid CN provided:" depending on the interface used). Your custom message follows this.		
	For example:			
	"TemplateRegexes": [ {			
TemplateDefaults	are not otherwise o	g the system-wide template default settings. These apply to all enrollments that overridden by individual template settings, including those that do not use a a standalone CA). Template default details are:		
	Value	Description		
	SubjectPart	A string indicating the portion of the subject the default applies to (e.g. L for City/Locality).		
	Value	A string containing the value to assign as the default for that subject part (e.g. Chicago).		
	For example:			
	<pre>"TemplateDefaults": [</pre>			

Note: See also the Subject Format application setting, which takes precedence over enroll-

Value	Description		
	ment defaults at both the system-wide and template level (see <i>Application Settings: Enroll-ment Tab</i> in the <i>Keyfactor Command Reference Guide</i> ) but does not apply to enrollment requests done through the Keyfactor API.		
TemplatePolicy	not otherwise overridde	system-wide template policy settings. These apply to all enrollments that are in by individual template settings, including those that do not use a template CA). Template policy details are:	
	Value	Description	
	RSAValidKeySizes	An object containing a comma-delimited list of integers defining the valid RSA key sizes supported for all templates used for enrollment. The supported values are:  • 2048 • 4096	
	ECCValidCurves	An object containing a list of strings defining the valid elliptic curve algorithms for ECC templates. These may be specified using the well-known OIDs for ECC algorithms or by friendly name. Well-known OIDs include:  • 1.2.840.10045.3.1.7 = P-256/prime256v1/secp256r1  • 1.3.132.0.34 = P-384/secp384r1  • 1.3.132.0.35 = P-521/secp521r1  When specifying by friendly name, do not include a slash (use "P-256", not "P-256/prime256v1/secp256r1").	
	AllowKeyReuse	A Boolean that indicates whether private key reuse is allowed (true) or not (false). This option allows to certificate renewals.	
	AllowWildcards	A Boolean that indicates whether wildcards are allowed (true) or not (false).	
	RFCEnforcement	A Boolean that indicates whether RFC 2818 compliance enforcement is enabled (true) or not (false). When this option is set to <i>true</i> , certificate enrollments made through Keyfactor Command for this template must include at least one DNS SAN. In the Keyfactor Command Management Portal, this causes the CN entered in PFX enrollment to automatically be replicated as a SAN, which the user can either change or accept. For CSR enrollment, if the CSR does not have a SAN that matches the CN, one will automatically be added to the certificate if this is set.	

Description	Description			
Value	Description			
AllowEd448	A Boolean that indicates whether Ed448 key type is allowed (true) or not (false).			
AllowEd25519 A Boolean that indicates whether Ed25519 key type is allowed (tr not (false).				
For example:	For example:			
"TemplatePolicy": {     "RSAValidKeySizes": [         2048,         4096 ],     "ECCValidCurves": [         "1.2.840.10045.3.1.7",         "1.3.132.0.34"         "1.3.132.0.35" ],     "AllowKeyReuse": false,     "AllowWildcards": true,     "RFCEnforcement": true,     "AllowEd448": false,				
			"Allow!	d25519": false

Table 552: PUT Templates Settings Response Data

Value	Description		
TemplateRegexes	ments that are no	ot otherwise overridden	nplate regular expression settings. These apply to all enroll- by individual template settings, including those that do not A). Regular expression details are:
	Name	Description	
	SubjectPart	A string indicating the (e.g. CN).	portion of the subject the regular expression applies to
	RegEx	A string specifying the regular expression against which data entered in the indicated subject part field (e.g. CN) in the enrollment pages of the Keyfactor Command Management Portal or using an API enrollment method will be validated.  Use the GET /Templates/SubjectParts method (see GET Templates Subject Parts on page 1184) to retrieve a list of all the supported subject parts.  The following are some regular expression examples:	
		Subject Part	Example
		CN (Common Name)	This regular expression specifies that the data entered in the field must consist of some number of characters in the first portion of the field made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly ".keyexample.com":  ^[a-zA-Z0-9' \.\-]*\.keyexample\.com\$  The default value for the Common Name regular expression is:  .+  This requires entry of at least one character in the Common Name field in the enrollment pages.
		O (Organization)	This regular expression requires that the organization name entered in the field be one of "Key Example Inc", "Key Example" or "Key Example Inc.":

Value	Description				
	Name	Description			
		Subject Part	Example		
			^(?:Key Example Inc Key Example Key Example, Inc\.)\$  The period in the final company name (Key Example, Inc.) needs to be escaped in the regular expression with a slash ("\") but the comma does not.		
		OU (Organization Unit)	This regular expression requires that the organizational unit entered in the field be one of these four departments:  ^(?:IT HR Accounting E-Commerce)\$		
		L (City/Locality)	This regular expression requires that the city entered in the field be one of these five cities:  ^(?:Boston Chicago New York London Dallas)\$		
		ST (State/Province)	This regular expression requires that the state entered in the field be one of these eight states:  ^(?:Massachusetts Illinois New York Ontario Texas)\$		
		C (Country)	This regular expression requires that the country entered in the field be either US or CA:  ^(?:US CA)\$		
		E (Email)	This regular expression specifies that the data entered in the field must consist of some number of characters prior to the "@" made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly "@keyexample.com":  ^[a-zA-Z0-9'_\.\-]*@keyexample\.com\$		
		DNS (Subject Alternative Name: DNS Name)	This regular expression specifies that the data entered in the field must consist of some number of characters in the first portion of the field made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens		

Value	Description			
	Name	Description		
		Subject Part	Example	
			followed by exactly either ".keyexample1.com" or  ".keyexample2.com":  ^[a-zA-Z0-9'_\.\-]*\. (?:keyexample1\.com keyexample2\.com )\$	
		IPv4 (Subject Alternative Name: IPv4 Address)	This regular expression specifies that the data entered in the field must be exactly "130.101." followed by anywhere between 1 and 3 numbers followed by exactly "." followed by anywhere between 1 and 3 numbers:  ^130\.101\.(?:[0-9]{1,3})\.(?:[0-9]{1,3})\\$  This regular expression specifies only that the IPv4 address is made up of 4 sets of between 1 and 3 numbers separated by periods:  ^(?:[0-9]{1,3}\.){3}[0-9]{1,3}\$	
		IPv6 (Subject Alternative Name: IPv6 Address)	This regular expression specifies that the data entered in the field must be made up of eight sets of between one and four numbers and/or uppercase letters separated by colons:  ^(?:[A-F0-9]{1,4}:){7}[A-F0-9]{1,4}\$	
		MAIL (Subject Alternative Name: Email)	This regular expression specifies that the data entered in the field must consist of some number of characters prior to the "@" made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly "@keyexample.com":  ^[a-zA-Z0-9'_\.\-]*@keyexample\.com\$	
		UPN (Subject Alternative Name: User Prin- cipal Name)	This regular expression specifies that the data entered in the field must consist of some number of characters prior to the "@" made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens	

Value	Description			
	Name	Description		
		Subject Part	Example	
			followed by exactly "@keyexample.com":  ^[a-zA-Z0-9'_\.\-]*@keyexample\.com\$	
	Error	A string specifying the error message displayed to the user when the subject part referenced in the CSR or entered for a PFX enrollment does not match the given regular expression. Note that the error message already includes a leading string with the subject part (e.g. "Common Name:" or "Invalid CN provided:" depending on the interface used). Your custom message follows this.		
	For example:			
	<pre>"TemplateRegexes": [     {         "SubjectPart": "0",         "Regex": "^(?:Key Example Company Key Example Inc\.)\$",         "Error": "Organization must be Key Example, Inc or Key Example Company."     } ]</pre>			
TemplateDefaults	are not otherwise	e overridden by individu	nplate default settings. These apply to all enrollments that all template settings, including those that do not use a mplate default details are:	
	Value	Description		
	SubjectPart	A string indicating the portion of the subject the default applies to (e.g. L City/Locality).		
	Value	A string containing the value to assign as the default for that subject part (e.g. Chicago).		
	For example:			
	"TemplateDefaults": [ {     "SubjectPart": "L",     "Value": "Denver" }, {			

Value	Description
	"SubjectPart": "ST", "Value": "Colorado" }  Note: See also the Subject Format application setting, which takes precedence over enrollment defaults at both the system-wide and template level (see Application Settings: Enrollment Tab in the Keyfactor Command Reference Guide) but does not apply to enrollment requests done through the Keyfactor API.
TemplatePolicy	An array containing the system-wide template policy settings. These apply to all enrollments that are not otherwise overridden by individual template settings, including those that do not use a template (e.g. from a standalone CA). Template policy details are:

	algorithms for ECC templates. These may be specified using the well-known OIDs for ECC algorithms or by friendly name. Well-known OIDs include:  • 1.2.840.10045.3.1.7 = P-256/prime256v1/secp256r1  • 1.3.132.0.34 = P-384/secp384r1  • 1.3.132.0.35 = P-521/secp521r1  When specifying by friendly name, do not include a slash (use "P-256", not "P-256/prime256v1/secp256r1").
AllowKeyReuse	A Boolean that indicates whether private key reuse is allowed (true) or not (false). This option allows to certificate renewals.
AllowWildcards	A Boolean that indicates whether wildcards are allowed (true) or not (false).
RFCEnforcement	A Boolean that indicates whether RFC 2818 compliance enforcement is enabled (true) or not (false). When this option is set to <i>true</i> , certificate

Value	Description		
	Value	Description	
		enrollments made through Keyfactor Command for this template must include at least one DNS SAN. In the Keyfactor Command Management Portal, this causes the CN entered in PFX enrollment to automatically be replicated as a SAN, which the user can either change or accept. For CSR enrollment, if the CSR does not have a SAN that matches the CN, one will automatically be added to the certificate if this is set.	
	AllowEd448	A Boolean that indicates whether Ed448 key type is allowed (true) or not (false).	
	AllowEd25519	A Boolean that indicates whether Ed25519 key type is allowed (true) or not (false).	
	For example:		
	"TemplatePolicy": {     "RSAValidKeySize	s": [  : [ 5.3.1.7",  "  false, : true, : true,	

### 2.2.29.4 GET Templates Subject Parts

The GET /Templates/SubjectParts method is used to retrieve a list of the certificate subject parts that are supported for regular expressions (TemplateRegexes) and defaults (TemplateDefaults). This method returns HTTP 200 OK on a success with the list of supported certificate subject part fields. This method has no input parameters.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: PkiManagement: *Read* 

Table 553: GET Templates Subject Parts Response Data

Name	Description
SubjectPart	A string indicating the supported subject part code (e.g. L for City/Locality).
SubjectPartName	A string containing a friendly name for the subject part (e.g. City/Locality).

# 2.2.29.5 GET Templates

The GET /Templates method is used to retrieve one or more templates from Keyfactor Command. Results can be limited to selected templates using filtering, and URL parameters can be used to specify paging and the level of information detail. This method returns HTTP 200 OK on a success with details about the specified templates.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: PkiManagement: *Read* 

Table 554: GET Templates Input Parameters

Name	In	Description	
queryString	Query	A string containing a query to limit the results (e.g. field1 -eq value1 AND field2 -gt value2). The default is to return all records. Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns for the same feature. For querying guidelines, refer to the Keyfactor Command Reference Guide: Using the Template Search Feature. The query fields supported for this endpoint are:  • AllowedEnrollmentType (1-PFX Enrollment, 2-CSR Enrollment, 3-CSR Generation, 0-None)  • DisplayName  • FriendlyName  • ForestRoot (deprecated)  • ConfigurationTenant  • HasPrivateKeyRetention (True, False)  • IsDefaultTemplate (True, False)  • KeyType (Unknown, RSA, DSA, ECC, DH)  • ShortName  Tip: To filter out all the built-in Active Directory templates and display only your custom templates, use the following query:  IsDefaultTemplate -eq "false"  To filter out all templates that are not configured for either PFX Enrollment or CSR Enrollment, use the following query:  AllowedEnrollmentType -eq "3"  A value of 1 will filter out all templates except those configured for PFX Enrollment. A value of 2 will filter out all templates except those configured for CSR Enrollment.	
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.	
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.	
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>CommonName</i> .	
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.	

Table 555: GET Templates Response Data

Name	Description
Id	An integer indicating the ID of the template in Keyfactor Command.
CommonName	A string containing the common name (short name) of the template. This name typically does not contain spaces. For a template created using a Microsoft management tool, this will be the Microsoft template name. For a template generated for an EJBCA CA, this will be built using a naming scheme of <end entity="" name="" profile="">_<certificate name="" profile="">. This field is populated based on information retrieved from the CA and is not configurable.</certificate></end>
TemplateName	A string containing the name of the template. For a template created using a Microsoft management tool, this will be the Microsoft template display name. For a template generated for an EJBCA CA, this will be built using a naming scheme of <end entity="" name="" profile=""> (<certificate name="" profile="">). This field is populated based on information retrieved from the CA and is not configurable.</certificate></end>
Oid	A string containing the object ID of the template in Active Directory. For Microsoft templates, this field is populated from Active Directory. For EJBCA templates, this field is generated within Keyfactor Command as an object identifier, but does not follow official OID conventions. The field is not configurable.
KeySize	A string indicating the minimum supported key size of the template as defined by the CA. The field is not configurable.
КеуТуре	A string indicating the key type of the template as defined by the CA. The field is not configurable.
ForestRoot	A string indicating the forest root of the template. For Microsoft templates, this field is populated from Active Directory and is not configurable.
	Note: The ForestRoot has been replaced by the ConfigurationTenant from release 10, but is retained for backwards compatibility.
ConfigurationTenant	A string indicating the configuration tenant of the template. For Microsoft templates, this field is populated from Active Directory. For EJBCA templates, this field is populated from the Keyfactor Command CA record. The field is not configurable.
FriendlyName	A string indicating the Keyfactor Command friendly name of the template. Template friendly names, if configured, appear in the dropdowns for PFX enrollment, CSR enrollment, and CSR generation in place of the template names. This can be useful in environments where the template names are long or not very human readable.
KeyRetention	A string indicating the type of key retention certificates enrolled with this template will use to

Name	Description		
	store their private key in Keyfactor Command. The key retention object contains the following parameters:		
	Value	Description	
	None	The private key will not be retained.	
	Indefinite	The private key will be retained until it is explicitly deleted.	
	AfterExpiration	The private key will be retained until the specified number of days after the certificate expires ( <i>KeyRetentionDays</i> ), at which point it will be scheduled for deletion.	
	FromIssuance	The private key will be retained until the specified number of days after the date on which the certificate was issued (KeyRetentionDays), at which point it will be scheduled for deletion.	
KeyRetentionDays	An integer indicating the number of days a certificate's private key will be retained in Keyfactor Command before being scheduled for deletion, if private key retention is enabled.		
KeyArchival	A Boolean indicating whether the template has been configured with the key archival setting in Active Directory (true) or not (false). This is a reference field and is not configurable.		
EnrollmentFields	An object containing custom enrollment fields. These are configured on a per-template basis to allow you to submit custom fields with CSR enrollments and PFX enrollments to supply custom request attributes to the CA during the enrollment process. This functionality offers such benefits as:  • Preventing users from requesting invalid certificates, based on your specific certificate requirements per template.		
	<ul> <li>Providing addition</li> </ul>	nal information to the CA with the CSR.	
	Once created on the template, these values are shown in Keyfactor Command on the PFX CSR enrollment pages in the <i>Additional Enrollment Fields</i> section. The fields are mandato during enrollment. The data will appear on the CA / Issued Certificates attribute tab for c ficates enrolled with a template configured with Keyfactor Command enrollment fields.  Note: These are not metadata fields, so they are not stored in the Keyfactor Com database, but simply passed through to the CA. The CA in turn could, via a gatew policy module, use this data to perform required actions.		
	The enrollment fields object contains the following parameters:		

Name	Description		
	Name	Description	
	Id	An integer indicating the ID of the custom enrollment field.	
	Name	A string indicating the name of the custom enrollment field. This name will appear on the enrollment pages.	
	Options	For multiple choice values, an array of strings containing the value choices.	
	DataType	An integer indicating the parameter type. The options are:	
		Value Description	
		1 String: A free-form data entry field.	
		2 Multiple Choice: Provides a list of acceptable values for the field. The multiple choice values are provided in the <i>Options</i> parameter.	
AllowedEn- rollmentTypes	options causes th Management Por appear in dropdo configured for en	e template to appear in dropdowns in the corresponding section of the tal. In the case of CSR Enrollment and PFX Enrollment, the templates only wns on the enrollment pages if they are available for enrollment from a CA also rollment within Keyfactor Command. See Adding or Modifying a CA Record in mmand Reference Guide for more information. Possible values are:	
	Value	Description	
	0	None	
	1	PFX Enrollment	
	2	CSR Enrollment	
	3	CSR Enrollment & PFX Enrollment	
	4	CSR Generation	
	5	CSR Generation & PFX Enrollment	
	6	CSR Generation & CSR Enrollment	
	7	CSR Enrollment, PFX Enrollment & CSR Generation	
TemplateRegexes	An object contain	ing individual template-level regular expressions against which to validate the	

Name	Description			
	subject data. Regular expressions defined on a template apply to enrollments made with that template only. Template-level regular expressions, if defined, take precedence over system-wide regular expressions. For more information about system-wide regular expressions, see <a href="Million Settings">GET</a> <a href="Templates Settings">Templates Settings</a> on page 1165. The template regular expression object contains the following parameters:			
	Name	Description		
	TemplateId	The Keyfactor Command reference ID of the certificate template the regula expression is associated with.		
	SubjectPart	A string indicating the portion of the subject the regular expression applies to (e.g. CN).		
	RegEx	A string specifying the regular expression against which data entered indicated subject part field (e.g. CN) in the enrollment pages of the Keyfactor Command Management Portal or using an API enrollment method will be validated.  Use the GET /Templates/SubjectParts method (see GET Templates Steparts on page 1184) to retrieve a list of all the supported subject part The following are some regular expression examples:		
		CN (Common Name)	This regular expression specifies that the data entered in the field must consist of some number of characters in the first portion of the field made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly  ".keyexample.com":  ^[a-zA-Z0-9' \.\-]*\.keyexample\.com\$  The default value for the Common Name regular expression is: .+  This requires entry of at least one character in the Common Name field in the enrollment pages.	
		O (Organization)	This regular expression requires that the organization name entered in the field be one of "Key	

Name	Description					
	Name	Description				
		Subject Part	Example			
			Example Inc", "Key Example" or "Key Example Inc.":  ^(?:Key Example Inc Key Example Key Example, Inc\.)\$ The period in the final company name (Key Example, Inc.) needs to be escaped in the regular expression with a slash ("\") but the comma does not.			
		OU (Organ- ization Unit)	This regular expression requires that the organizational unit entered in the field be one of these four departments:  ^(?:IT HR Accounting E-Commerce)\$			
		L (City/Locality)	This regular expression requires that the city entered in the field be one of these five cities:  ^(?:Boston Chicago New York London Dallas)\$			
		ST (State/Province)	This regular expression requires that the state entered in the field be one of these eight states:  ^(?:Massachusetts Illinois New York Ontario Texas)\$			
		C (Country)	This regular expression requires that the country entered in the field be either US or CA:  ^(?:US CA)\$			
		E (Email)	This regular expression specifies that the data entered in the field must consist of some number of characters prior to the "@" made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly "@keyexample.com":  ^[a-zA-Z0-9'_ \.\-]*@keyexample\.com\$			

Name	Description					
	Name	Description				
		Subject Part	Example			
	DNS (Subject Alternative Name: DNS Name)	This regular expression specifies that the data entered in the field must consist of some number of characters in the first portion of the field made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly either ".keyexample1.com" or ".keyexample2.com":  ^[a-zA-Z0-9'_\.\-]*\. (?:keyexample1\.com keyexample2\.com)\$				
		IPv4 (Subject Alternative Name: IPv4 Address)	This regular expression specifies that the data entered in the field must be exactly "130.101." followed by anywhere between 1 and 3 numbers followed by exactly "." followed by anywhere between 1 and 3 numbers: $ ^{130}.101.(?:[0-9]\{1,3\}).(?:[0-9]\{1,3\}). $ This regular expression specifies only that the IPv4 address is made up of 4 sets of between 1 and 3 numbers separated by periods: $ ^{(?:[0-9]\{1,3\}\setminus.)\{3\}[0-9]\{1,3\}\$} $			
		IPv6 (Subject Alternative Name: IPv6 Address)	This regular expression specifies that the data entered in the field must be made up of eight sets of between one and four numbers and/or uppercase letters separated by colons:  ^(?:[A-F0-9]{1,4}:){7}[A-F0-9] {1,4}\$			
		MAIL (Subject Alternative Name: Email)	This regular expression specifies that the data entered in the field must consist of some number of characters prior to the "@" made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly "@keyexample.com":  ^[a-zA-Z0-9'_			

Name	Description				
	Name	Description			
		Subject Part	Example		
			\.\-]*@keyexample\.com\$		
		UPN (Subject Alternative Name: User Prin- cipal Name)	This regular expression specifies that the data entered in the field must consist of some number of characters prior to the "@" made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly "@keyexample.com":  ^[a-zA-Z0-9'_ \.\-]*@keyexample\.com\$		
	Error	part referenced in th the given regular exp leading string with th	e error message displayed to the user when the subject e CSR or entered for a PFX enrollment does not match pression. Note that the error message already includes a ne subject part (e.g. "Common Name:" or "Invalid CN g on the interface used). Your custom message follows		
UseAl- lowedRequesters	A Boolean that indicates whether the Restrict Allowed Requesters option should be enabled (true) or not (false). The Restrict Allowed Requesters option is used to select Keyfactor Command security roles that a user must belong to in order to successfully enroll for certificates in Keyfactor Command using this template. This is typically used for EJBCA templates and Microsoft templates that are not in the local Active Directory forest, since in these cases, Keyfactor Command cannot make use of the access control model of the CA itself to determine which users can enroll for certificates; this setting replaces that functionality. This setting is similar to setting request certificates for the selected security roles at the template level on a Microsoft CA. In addition to granting permissions at the template level, you need enable the Restrict Allowed Requesters option to grant permissions at the CA level. See Adding or Modifying a CA Record in the Keyfactor Command Reference Guide for more information.				
AllowedRequesters	An object containing the list of Keyfactor Command security roles—as strings—that have been granted enroll permission on the template.				
DisplayName	A string indicating the Keyfactor Command display name of the template. If a template friendly name is configured, this is used as the display name. If not, the template name is used. The display name appears in the dropdowns for PFX enrollment, CSR enrollment, and CSR generation. The display name is a generated field and is not directly configurable.				
RequiresApproval		ting whether the temp	late has been configured with the Microsoft <i>CA certi-</i> d ( <i>true</i> ) or not ( <i>false</i> ).		

## Description Name Important: Any templates that are configured on the Microsoft CA Issuance Requirements tab for CA certificate manager approval cannot be used for enrollment and associated alerting in Keyfactor Command without configuring private key retention. Any of the enabled private key retention settings (settings other than none as described for KeyRetention) will allow a template requiring manager approval to work with Keyfactor Command PFX and CSR enrollment. Corp Web Server - RA Properties × Superseded Templates Extensions Security Server General Compatibility Request Handling Cryptography Key Attestation Subject Name Issuance Requirements Require the following for enrollment: CA certificate manager approval ☐ This number of authorized signatures: 0 If you require more than one signature, autoenrollment is not allowed. Figure 3: Microsoft Issuance Requirements on a Template for Manager Approval KeyUsage An integer indicating the total key usage of the certificate. Key usage is stored in Active Directory as a single value made of a combination of values. The values that make up the key usage value include:

Value	Function	Description
0	None	No key usage parameters.
1	Encipherment Only	The key can be used for encryption only.
2	CRL Signing	The key can be used to sign a certificate revocation list (CRL).
4	Key Certificate Signing	The key can be used to sign certificates.
8	Key Agreement	The key can be used to determine key agreement, such as a key created using the Diffie-Hellman key agreement algorithm.
16	Data Encipherment	The key can be used for data encryption.
32	Key Encipherment	The key can be used for key encryption.
64	Nonrepudiation	The key can be used for authentication.

Name	Description	Description					
	Value	Function	Description				
	128	Digital Signature	The key can be used as a digital signature.				
	32768	Decipherment Only	The key can be used for decryption only.				
	For example, a value of 160 would represent a key usage of digital signature with key enciposent. A value of 224 would add nonrepudiation to those.						
ExtendedKeyUsages	An object containing the extended key usage information for the template. This fiel lated from the CA and is not configurable. The extended key usage object contains parameters:						
	Name	Description					
	Id	An integer indication	ating the ID of the extended key usage in Active				
	Oid	A string containi	A string containing the object ID of the extended key usage.				
	DisplayName	0 , ,	A string specifying the display name of the extended key usage (e.g. Server Authentication).				

#### 2.2.29.6 PUT Templates

The PUT /Templates method is used to update selected information about a certificate template. This method returns HTTP 200 OK on a success with details about the specified template.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: PkiManagement: *Modify* 



**Warning:** Any previously populated fields that are not submitted with their full existing data using this method will be cleared of their existing data. When using this method, you should first do a GET to retrieve all the values for the record you want to update, enter corrected data into the field(s) you want to update, and then submit all the fields using PUT, including the fields that contain values but which you are not changing.

Table 556: PUT Templates Input Parameters

Name	In	Description					
Id	Body	Required. An integer indicating the ID of the template in Keyfactor Command.					
KeySize	Body	A string indicating the minimum supported key size of the template as defined by the CA. The field is not configurable.					
КеуТуре	Body	A string indicating the k configurable.	ey type of the template as defined by the CA. The field is not				
FriendlyName	Body	A string indicating the Keyfactor Command friendly name of the template. Template friendly names, if configured, appear in the dropdowns for PFX enrollment, CSR enrollment, and CSR generation in place of the template names. This can be useful in environments where the template names are long or not very human readable.					
KeyRetention	Body	A string indicating the type of key retention certificates enrolled with this template will use to store their private key in Keyfactor Command. The key retention object contains the following parameters:					
		Value Description					
			None	The private key will not be retained.			
			Indefinite	The private key will be retained until it is explicitly deleted.			
		FromIssuance	The private key will be retained until the specified number of days after the date on which the certificate was issued ( <i>KeyRetentionDays</i> ), at which point it will be scheduled for deletion.				
KeyRetentionDays	Body	An integer indicating the number of days a certificate's private key will be retained in Keyfactor Command before being scheduled for deletion, if private key retention is enabled.					
KeyArchival	Body	A Boolean indicating whether the template has been configured with the key archival setting in Active Directory (true) or not (false). This is a reference field and is not configurable.					
EnrollmentFields	Body	basis to allow you to su	stom enrollment fields. These are configured on a per-template bmit custom fields with CSR enrollments and PFX enrollments to attributes to the CA during the enrollment process. This func-nefits as:				

Name	In	Description			
		<ul> <li>Preventing users from requesting invalid certificates, based on your specific certificate requirements per template.</li> <li>Providing additional information to the CA with the CSR.</li> </ul>			
		Once created on the template, these values are shown in Keyfactor Command on the PFX and CSR enrollment pages in the <i>Additional Enrollment Fields</i> section. The fields mandatory during enrollment. The data will appear on the CA / Issued Certificates attribute tab for certificates enrolled with a template configured with Keyfactor Command enrollment fields.			
		Note: These are not metadata fields, so they are not stored in the Ke Command database, but simply passed through to the CA. The CA in via a gateway or policy module, use this data to perform required act			
		The enrollment fi	elds object contai	ns the following parameters:	
		Name	Description		
		Id	An integer indic	eating the ID of the custom enrollment field.	
		Name		ng the name of the custom enrollment field. This ar on the enrollment pages.	
		Options	For multiple cho	pice values, an array of strings containing the value	
		DataType	An integer indic	cating the parameter type. The options are:	
			Value	Description	
			1	String: A free-form data entry field.	
			2	Multiple Choice: Provides a list of acceptable values for the field. The multiple choice values are provided in the <i>Options</i> parameter.	
		For example:			
		<pre>"EnrollmentFields": [</pre>			

Name	In	Description		
		]		
MetadataFields	Body	<ul> <li>An object containing template-level metadata field settings. Template-level metadata field configurations can override global metadata field configurations in these possible ways: <ul> <li>Configuration on the metadata field of required, optional or hidden.</li> <li>The default value for the metadata field.</li> <li>A regular expression defined for the field (string fields only) against which entered data will be validated along with its associated message.</li> <li>For fields of data type multiple choice, the list of values that appear in multiple choice dropdowns.</li> </ul> </li> <li>Metadata field settings defined on a template apply to enrollments made with that template only. Template-level metadata field settings, if defined, take precedence over global-level metadata field settings.</li> <li>The metadata fields object contains the following parameters:</li> </ul>		
		Name	Description	
		Id	The Keyfactor Command reference ID of the template-specific metadata setting.	
		DefaultValue	A string containing the default value defined for the metadata field for the specific template.	
		Metadatald	An integer indicating the global metadata field associated with the template-specific settings.	
		Validation	A string containing the template-specific regular expression against which data entered in a string field will be validated. When a user enters information in a metadata field that does not match the specified regular expression, he or she will see the warning message specified in the <i>Message</i> field. For example:  ^[a-zA-Z0-9'_\.\-]*@ (keyexample\.org keyexample\.com)\$  This regular expression specifies that the data entered in the field must consist of some number of characters prior to the "@" made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly either "@keyexample.org" or "keyexample.com".	

Name	In	Description			
		Name	Description		
			This field is only string.	This field is only supported for metadata fields with data type <i>string</i> .	
		Enrollment	_	indicates how metadata fields should be PFX and CSR Enrollment pages. Possible values	
			Value	Description	
			0	Optional Users have the option to either enter a value or not enter a value in the field.	
			1	Required Users are required to enter data in the field when populating metadata fields on the PFX and CSR Enrollment pages. The field is not required on the certificate details or Add Certificate page.	
			2	Hidden The field is hidden and does not appear on the PFX and CSR Enrollment pages. This field still appears on the certificate details and the Add Certificate page.	
		Message	information in a	ning a message to present when a user enters a metadata field that does not match the fic regular expression ( <i>Validation</i> field).	
		Options	should appear i	ning a comma separated list of values that in the field dropdown for multiple choice fields. y supported for metadata fields with data type	
		For example:			
		"MetadataFields' { "Id": 4, "DefaultVa		wallace@keyexample.com",	

Name	In	Description			
		<pre>"MetadataId": 4,     "Validation": "^[a-zA-Z0-9'_\\.\-]*@(keyexample\\.or- g keyexample\\.com)\$",     "Enrollment": 1,     "Message": "Your email address must be of the form user- @keyexample.com or fname.lname@keyexample.com."     },     {         "Id": 13,         "DefaultValue": "E-Business",         "MetadataId": 5,         "Validation": "",         "Enrollment": 0,         "Message": "",         "Options": "Accounting,E-Busi- ness,Executive,HR,IT,Marketing,R&amp;D,Sales"     } ]</pre>			
AllowedEn- rollmentTypes	Body	An integer indicating the type of enrollment allowed for the certificate template. Setting these options causes the template to appear in dropdowns in the corresponding section of the Management Portal. In the case of CSR Enrollment and PFX Enrollment, the templates only appear in dropdowns on the enrollment pages if they are available for enrollment from a CA also configured for enrollment within Keyfactor Command. See <i>Adding or Modifying a CA Record</i> in the <i>Keyfactor Command Reference Guide</i> for more information. Possible values are:			
		Value	Description		
		0	None		
		1	PFX Enrollment		
		2	CSR Enrollment		
		3	CSR Enrollment & PFX Enrollment		
		4 CSR Generation 5 CSR Generation & PFX Enrollment 6 CSR Generation & CSR Enrollment 7 CSR Enrollment, PFX Enrollment & CSR Generation			
TemplateRegexes	Body		ng individual template-level regular expressions against which to t data. Regular expressions defined on a template apply to enroll-		

Name	In	Description				
		ments made with that template only. Template-level regular expressions, if defined, take precedence over system-wide regular expressions. For more information about system-wide regular expressions, see <a href="METTEMPLATES">GET Templates Settings on page 1165</a> . The template regular expression object contains the following parameters:				
		Name	Description			
	Templatel-	The Keyfactor Comi	mand reference ID of the certificate template the is associated with.			
		SubjectPa- rt	A string indicating t applies to (e.g. CN).	he portion of the subject the regular expression		
	RegEx	A string specifying the regular expression against which data entered in the indicated subject part field (e.g. CN) in the enrollment pages of the Keyfactor Command Management Portal or using an API enrollment method will be validated.  Use the GET /Templates/SubjectParts method (see GET Templates Subject Parts on page 1184) to retrieve a list of all the supported subject parts.  The following are some regular expression examples:				
			Subject Part	Example		
			CN (Common Name)	This regular expression specifies that the data entered in the field must consist of some number of characters in the first portion of the field made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly ".keyexample.com":  ^[a-zA-Z0-9'_		
			\.\-]*\.keyexample\.com\$  The default value for the Common Name regular expression is:     .+  This requires entry of at least one character in the Common Name field in the enrollment pages.			
			O (Organ-	This regular expression requires that the		

Name	In	Description		
		Name	Description	
			Subject Part	Example
			ization)	organization name entered in the field be one of "Key Example Inc", "Key Example" or "Key Example Inc.":  ^(?:Key Example Inc Key Example Key Example, Inc\.)\$ The period in the final company name (Key Example, Inc.) needs to be escaped in the regular expression with a slash ("\") but the comma does not.
			OU (Organ- ization Unit)	This regular expression requires that the organizational unit entered in the field be one of these four departments:  ^(?:IT HR Accounting E-Commerce)\$
			L (City/Locality)	This regular expression requires that the city entered in the field be one of these five cities:  ^(?:Boston Chicago New York London Dallas)\$
			ST (State/Provinc- e)	This regular expression requires that the state entered in the field be one of these eight states:  ^(?:Massachusetts Illinois New York Ontario Texas)\$
			C (Country)	This regular expression requires that the country entered in the field be either US or CA:  ^(?:US CA)\$
			E (Email)	This regular expression specifies that the data entered in the field must consist of some number of characters prior to the "@" made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores,


Name	In	Description		
		Name	Description	
			Subject Part	Example
				periods, and/or hyphens followed by exactly "@keyexample.com":  ^[a-zA-Z0-9'_ \.\-]*@keyexample\.com\$
			DNS (Subject Alternative Name: DNS Name)	This regular expression specifies that the data entered in the field must consist of some number of characters in the first portion of the field made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly either  ".keyexample1.com" or ".keyexample2.com":  ^[a-zA-Z0-9'_\\-]*\. (?:keyexample1\.com keyexample2\.com)\$
			IPv4 (Subject Alternative Name: IPv4 Address)	This regular expression specifies that the data entered in the field must be exactly "130.101." followed by anywhere between 1 and 3 numbers followed by exactly "." followed by anywhere between 1 and 3 numbers: $ ^130 \\. 101\\. (?:[0-9]{1,3})\\$ This regular expression specifies only that the IPv4 address is made up of 4 sets of between 1 and 3 numbers separated by periods: $ ^(?:[0-9]{1,3}\\.){3}[0-9] \\ \{1,3\}$$
			IPv6 (Subject Alternative Name: IPv6 Address)	This regular expression specifies that the data entered in the field must be made up of eight sets of between one and four numbers and/or uppercase letters separated by colons:  ^(?:[A-F0-9]{1,4}:){7}[A-F0-9] {1,4}\$

Name	In	Description		
		Name	Description	
			Subject Part	Example
			MAIL (Subject Alternative Name: Email)	This regular expression specifies that the data entered in the field must consist of some number of characters prior to the "@" made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly "@keyexample.com":  ^[a-zA-Z0-9'_ \.\-]*@keyexample\.com\$
			UPN (Subject Alternative Name: User Principal Name)	This regular expression specifies that the data entered in the field must consist of some number of characters prior to the "@" made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly "@keyexample.com":  ^[a-zA-Z0-9'_ \.\-]*@keyexample\.com\$
		Error	subject part reference does not match the message already in "Common Name:"	the error message displayed to the user when the need in the CSR or entered for a PFX enrollment e given regular expression. Note that the error cludes a leading string with the subject part (e.g. or "Invalid CN provided:" depending on the interstom message follows this.
		For example:		
		"Sub "Reg	plateId": 57, jectPart": "O", ex": "^(?:Key Exam	nple Company Key Example Inc\.)\$", n must be Key Example, Inc or Key Example
TemplateDefaults	Body	An object conta	aining individual temp	plate-level template default settings. Template

Name	In	Description	
		Template-level defa defaults. For more in	a template apply to enrollments made with that template only.  ults, if defined, take precedence over system-wide template  nformation about system-wide template defaults, see GET Templates  55. The template default object contains the following parameters:
		Value	Description
			A string indicating the portion of the subject the default applies to (e.g. L for City/Locality).  Use the GET /Templates/SubjectParts method (see GET Templates Subject Parts on page 1184) to retrieve a list of all the supported subject parts.
		Value	A string containing the value to assign as the default for that subject part (e.g. Chicago).
		For example:	
		"Value": }, { "Subject	Part": "L", "Denver"  Part": "ST", "Colorado"
TemplatePolicy			a template apply to enrollments made with that template only.  cies, if defined, take precedence over system-wide template policies.  an about system-wide template policies, see GET Templates Settings
		Value	Description
		TempalteId	The Keyfactor Command reference ID of the certificate template the policy is associated with.
		RSAValidKeySizes	An object containing a comma-delimited list of integers defining the valid RSA key sizes supported for all templates used for enrollment. The supported values are:

Name	In	Description	
		Value	Description
			<ul><li>2048</li><li>4096</li></ul>
		ECCValidCurves	An object containing a list of strings defining the valid elliptic curve algorithms for ECC templates. These may be specified using the well-known OIDs for ECC algorithms or by friendly name. Well-known OIDs include:  • 1.2.840.10045.3.1.7 = P- 256/prime256v1/secp256r1  • 1.3.132.0.34 = P-384/secp384r1  • 1.3.132.0.35 = P-521/secp521r1  When specifying by friendly name, do not include a slash (use "P-256", not "P-256/prime256v1/secp256r1").
		AllowKeyReuse	A Boolean that indicates whether private key reuse is allowed (true) or not (false). This option applies to certificate renewals. By default, this is set to <i>true</i> at a systemwide level.
		AllowWildcards	A Boolean that indicates whether wildcards are allowed (true) or not (false). By default, this is set to <i>true</i> at a system-wide level.
		RFCEnforcement	A Boolean that indicates whether RFC 2818 compliance enforcement is enabled (true) or not (false). When this option is set to <i>true</i> , certificate enrollments made through Keyfactor Command for this template must include at least one DNS SAN. In the Keyfactor Command Management Portal, this causes the CN entered in PFX enrollment to automatically be replicated as a SAN, which the user can either change or accept. For CSR enrollment, if the CSR does not have a SAN that matches the CN, one will automatically be added to the certificate if this is set. By default, this is set to <i>false</i> at a system-wide level.
		AllowEd448	A Boolean that indicates whether Ed448 key type is allowed (true) or not (false).
		AllowEd25519	A Boolean that indicates whether Ed25519 key type is allowed (true) or not (false).
		For example:	

Name	In	Description	
		"TemplatePolicy": {     "TemplateId": 17,     "RSAValidKeySizes": [         2048,         4096 ],     "ECCValidCurves": [         "1.2.840.10045.3.1.7",         "1.3.132.0.34"         "1.3.132.0.35" ],     "AllowKeyReuse": false,     "AllowWildcards": true,     "RFCEnforcement": true,     "AllowEd448": false,     "AllowEd25519": false }	
UseAl- lowedRequesters	Body	A Boolean that indicates whether the Restrict Allowed Requesters option should be enabled (true) or not (false). The Restrict Allowed Requesters option is used to select Keyfactor Command security roles that a user must belong to in order to successfully enroll for certificates in Keyfactor Command using this template. This is typically used for EJBCA templates and Microsoft templates that are not in the local Active Directory forest, since in these cases, Keyfactor Command cannot make use of the access control model of the CA itself to determine which users can enroll for certificates; this setting replaces that functionality. This setting is similar to setting request certificates for the selected security roles at the template level on a Microsoft CA. In addition to granting permissions at the template level, you need enable the Restrict Allowed Requesters option to grant permissions at the CA level. See Adding or Modifying a CA Record in the Keyfactor Command Reference Guide for more information.	
AllowedRequesters	Body	An object containing the list of Keyfactor Command security roles—as strings—that have been granted enroll permission on the template.  For example:  "AllowedRequesters": [     "Administrator",     "Power Users",     "Revokers" ]	
RequiresApproval	Body	A Boolean indicating whether the template has been configured with the Microsoft Cocertificate manager approval option enabled (true) or not (false).  Important: Any templates that are configured on the Microsoft CA Issuance	



Name	In	Description
		For example, a value of 160 would represent a key usage of <i>digital signature</i> with <i>key encipherment</i> . A value of 224 would add <i>nonrepudiation</i> to those.
Curve	Body	A string indicating the OID of the elliptic curve algorithm configured for the template, for ECC templates. Well-known OIDs include:  • 1.2.840.10045.3.1.7 = P-256/prime256v1/secp256r1  • 1.3.132.0.34 = P-384/secp384r1  • 1.3.132.0.35 = P-521/secp521r1

Table 557: PUT Templates Response Body

Name	Description	
Id	An integer indicating the ID of the template in Keyfactor Command.	
CommonName	A string containing the common name (short name) of the template. This name typically does not contain spaces. For a template created using a Microsoft management tool, this will be the Microsoft template name. For a template generated for an EJBCA CA, this will be built using a naming scheme of <end entity="" name="" profile="">_<certificate name="" profile="">.This field is populated based on information retrieved from the CA and is not configurable.</certificate></end>	
TemplateName	A string containing the name of the template. For a template created using a Microsoft management tool, this will be the Microsoft template display name. For a template generated for an EJBCA CA, this will be built using a naming scheme of <end entity="" name="" profile=""> (<certificate name="" profile="">). This field is populated based on information retrieved from the CA and is not configurable.</certificate></end>	
Oid	A string containing the object ID of the template in Active Directory. For Microsoft templates, this field is populated from Active Directory. For EJBCA templates, this field is generated within Keyfactor Command as an object identifier, but does not follow official OID conventions. The field is not configurable.	
KeySize	A string indicating the minimum supported key size of the template as defined by the CA. The field is not configurable.	
КеуТуре	A string indicating the key type of the template as defined by the CA. The field is not configurable.	
ForestRoot	A string indicating the forest root of the template. For Microsoft templates, this field is populated from Active Directory and is not configurable.	
	Note: The ForestRoot has been replaced by the ConfigurationTenant from release 10, but is retained for backwards compatibility.	
ConfigurationTenant	A string indicating the configuration tenant of the template. For Microsoft templates, this field is populated from Active Directory. For EJBCA templates, this field is populated from the Keyfactor Command CA record. The field is not configurable.	
FriendlyName	A string indicating the Keyfactor Command friendly name of the template. Template friendly names, if configured, appear in the dropdowns for PFX enrollment, CSR enrollment, and CSR generation in place of the template names. This can be useful in environments where the template names are long or not very human readable.	
KeyRetention	A string indicating the type of key retention certificates enrolled with this template will use to	

Name	Description			
	store their private key in Keyfactor Command. The key retention object contains the following parameters:			
	Value	Description		
	None	The private key will not be retained.		
	Indefinite	The private key will be retained until it is explicitly deleted.		
	AfterExpiration	The private key will be retained until the specified number of days after the certificate expires ( <i>KeyRetentionDays</i> ), at which point it will be scheduled for deletion.		
	FromIssuance	The private key will be retained until the specified number of days after the date on which the certificate was issued (KeyRetentionDays), at which point it will be scheduled for deletion.		
KeyRetentionDays	An integer indicating the number of days a certificate's private key will be retained in Keyfactor Command before being scheduled for deletion, if private key retention is enabled.			
KeyArchival	_	hether the template has been configured with the key archival setting in or not (false). This is a reference field and is not configurable.		
EnrollmentFields	An object containing custom enrollment fields. These are configured on a per-template basis to allow you to submit custom fields with CSR enrollments and PFX enrollments to supply custom request attributes to the CA during the enrollment process. This functionality offers such benefits as:			
	<ul> <li>Preventing users requirements pe</li> </ul>	from requesting invalid certificates, based on your specific certificate r template.		
	<ul> <li>Providing addition</li> </ul>	nal information to the CA with the CSR.		
	Once created on the template, these values are shown in Keyfactor Command on the FCSR enrollment pages in the Additional Enrollment Fields section. The fields are manda during enrollment. The data will appear on the CA / Issued Certificates attribute tab for ficates enrolled with a template configured with Keyfactor Command enrollment fields			
	Note: These are not metadata fields, so they are not stored in the Keyfactor Command database, but simply passed through to the CA. The CA in turn could, via a gateway or policy module, use this data to perform required actions.			
	The enrollment fields of	The enrollment fields object contains the following parameters:		

Name	Description			
	Name	Description		
	Id	An integer indicating the ID of the custom enrollment field.		
	Name	A string indicating the name of the custom enrollment field. This name will appear on the enrollment pages.		
	Options	For multiple choice values, an array of strings containing the value choices.		
	DataType	An integer indicating the parameter type. The options are:		
		Value Description		
		1 String: A free-form data entry field.		
		2 Multiple Choice: Provides a list of acceptable values for the field. The multiple choice values are provided in the <i>Options</i> parameter.		
MetadataFields	<ul> <li>An object containing template-level metadata field settings. Template-level metadata field configurations can override global metadata field configurations in these possible ways: <ul> <li>Configuration on the metadata field of required, optional or hidden.</li> <li>The default value for the metadata field.</li> <li>A regular expression defined for the field (string fields only) against which entered data will be validated along with its associated message.</li> <li>For fields of data type multiple choice, the list of values that appear in multiple choice dropdowns.</li> </ul> </li> <li>Metadata field settings defined on a template apply to enrollments made with that template only. Template-level metadata field settings, if defined, take precedence over global-level metadata fields object contains the following parameters:</li> </ul>			
	Name	Description		
	Id	The Keyfactor Command reference ID of the template-specific metadata setting.		
	DefaultValue	A string containing the default value defined for the metadata field for the specific template.		

template-specific settings.

Metadatald

An integer indicating the global metadata field associated with the

Name	Description		
	Name	Description	
	Validation	which data enterenters informated specified regular specified in the 'a-za-za (keyexam This regular expectonsist of some lowercase letterescores, periods, "@keyexample"	ting the template-specific regular expression against ered in a string field will be validated. When a user tion in a metadata field that does not match the expression, he or she will see the warning message to the message field. For example:  10-9'_\.\-]*@  10
	Enrollment	-	indicates how metadata fields should be handled on R Enrollment pages. Possible values are:
		Value	Description
		0	Optional Users have the option to either enter a value or not enter a value in the field.
		1	Required Users are required to enter data in the field when populating metadata fields on the PFX and CSR Enrollment pages. The field is not required on the certificate details or Add Certificate page.
		2	Hidden The field is hidden and does not appear on the PFX and CSR Enrollment pages. This field still appears on the certificate details and the Add Certificate page.
	Message	ation in a meta	ning a message to present when a user enters informdata field that does not match the template-specific ion (Validation field).
	Options	appear in the fi	ning a comma separated list of values that should eld dropdown for multiple choice fields.  y supported for metadata fields with data type multiple

Name	Description		
	Name	Description	
		choice.	
AllowedEn- rollmentTypes	options causes the Management Po appear in dropde configured for each	ating the type of enrollment allowed for the certificate template. Setting these he template to appear in dropdowns in the corresponding section of the ortal. In the case of CSR Enrollment and PFX Enrollment, the templates only owns on the enrollment pages if they are available for enrollment from a CA also nrollment within Keyfactor Command. See Adding or Modifying a CA Record in ammand Reference Guide for more information. Possible values are:	
	Value	Description	
	0	None	
	1	PFX Enrollment	
	2	CSR Enrollment	
	3	CSR Enrollment & PFX Enrollment	
	4	CSR Generation	
	5	CSR Generation & PFX Enrollment	
	6	CSR Generation & CSR Enrollment	
	7	CSR Enrollment, PFX Enrollment & CSR Generation	
subject da template o regular ex		ning individual template-level regular expressions against which to validate the gular expressions defined on a template apply to enrollments made with that remplate-level regular expressions, if defined, take precedence over system-wide ons. For more information about system-wide regular expressions, see	

Name	Description		
	Name	Description	
	indicated subject p Keyfactor Comman method will be val Use the <i>GET /Tem</i> Parts on page 118	indicated subject par Keyfactor Command method will be valid: Use the <i>GET /Templo</i> Parts on page 1184)	ne regular expression against which data entered in the rt field (e.g. CN) in the enrollment pages of the Management Portal or using an API enrollment ated.  Intes/SubjectParts method (see GET Templates Subject to retrieve a list of all the supported subject parts.  Interest of the support
		Subject Part	Example
		CN (Common Name)	This regular expression specifies that the data entered in the field must consist of some number of characters in the first portion of the field made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly ".keyexample.com":  ^[a-zA-Z0-9' \.\-]*\.keyexample\.com\$  The default value for the Common Name regular expression is: .+  This requires entry of at least one character in the Common Name field in the enrollment pages.
		O (Organization)	This regular expression requires that the organization name entered in the field be one of "Key Example Inc."; "Key Example" or "Key Example Inc.":  ^(?:Key Example Inc Key Example Key Example, Inc\.)\$ The period in the final company name (Key Example, Inc.) needs to be escaped in the regular expression with a slash ("\") but the comma does not.
		OU (Organ- ization Unit)	This regular expression requires that the organizational unit entered in the field be one of these four departments:

Name Descript	Description			
Name	Description	Description		
	Subject Part	Example		
		^(?:IT HR Accounting E-Commerce)\$		
	L (City/Locality)	This regular expression requires that the city entered in the field be one of these five cities:  ^(?:Boston Chicago New York London Dallas)\$		
	ST (State/Province)	This regular expression requires that the state entered in the field be one of these eight states:  ^(?:Massachusetts Illinois New York Ontario Texas)\$		
	C (Country)	This regular expression requires that the country entered in the field be either US or CA:  ^(?:US CA)\$		
	E (Email)	This regular expression specifies that the data entered in the field must consist of some number of characters prior to the "@" made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly "@keyexample.com":  ^[a-zA-Z0-9'_ \.\-]*@keyexample\.com\$		
	DNS (Subject Alternative Name: DNS Name)	This regular expression specifies that the data entered in the field must consist of some number of characters in the first portion of the field made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly either ".keyexample1.com" or ".keyexample2.com":  ^[a-zA-Z0-9'_\.\-]*\. (?:keyexample1\.com keyexample2\.com)\$		
	IPv4 (Subject Alternative	This regular expression specifies that the data		

Name	Description	Description			
	Name	Description	Description		
		Subject Part	Example		
		Name: IPv4 Address)	entered in the field must be exactly "130.101." followed by anywhere between 1 and 3 numbers followed by exactly "." followed by anywhere between 1 and 3 numbers:  ^130\.101\.(?:[0-9]{1,3})\.(?:[0-9]{1,3})\.(?:[0-9]{1,3})\$  This regular expression specifies only that the IPv4 address is made up of 4 sets of between 1 and 3 numbers separated by periods:  ^(?:[0-9]{1,3}\.){3}[0-9]{1,3}\$		
	IPv6 (Subject Alternative Name: IPv6 Address)	This regular expression specifies that the data entered in the field must be made up of eight sets of between one and four numbers and/or uppercase letters separated by colons:  ^(?:[A-F0-9]{1,4}:){7}[A-F0-9] {1,4}\$			
	MAIL (Subject Alternative Name: Email)	This regular expression specifies that the data entered in the field must consist of some number of characters prior to the "@" made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly "@keyexample.com":  ^[a-zA-Z0-9'_ \.\-]*@keyexample\.com\$			
		UPN (Subject Alternative Name: User Prin- cipal Name)	This regular expression specifies that the data entered in the field must consist of some number of characters prior to the "@" made up only of lowercase letters, uppercase letters, numbers, apostrophes, underscores, periods, and/or hyphens followed by exactly "@keyexample.com":  ^[a-zA-Z0-9'_ \.\-]*@keyexample\.com\$		
	Error		e error message displayed to the user when the subject e CSR or entered for a PFX enrollment does not match		

Name	Description			
	Name	Description		
		the given regular expression. Note that the error message already includes a leading string with the subject part (e.g. "Common Name:" or "Invalid CN provided:" depending on the interface used). Your custom message follows this.		
TemplateDefaults	defined on a tem defaults, if define about system-wid	ning individual template-level template default settings. Template defaults plate apply to enrollments made with that template only. Template-level ed, take precedence over system-wide template defaults. For more information de template defaults, see <a href="Million-EET Templates Settings">GET Templates Settings on page 1165</a> . The template ntains the following parameters:		
	Value	Description		
	SubjectPart	A string indicating the portion of the subject the default applies to (e.g. L for City/Locality).  Use the GET /Templates/SubjectParts method (see GET Templates  Subject Parts on page 1184) to retrieve a list of all the supported subject parts.		
	Value	A string containing the value to assign as the default for that subject part (e.g. Chicago).		
TemplatePolicy	defined on a tem policies, if define about system-wid	ning the individual template-level template policy settings. Template policies plate apply to enrollments made with that template only. Template-level d, take precedence over system-wide template policies. For more information de template policies, see <a href="METTEMPLATES">GET Templates Settings on page 1165</a> . The template tains the following parameters:		
	Value	Description		
	TempalteId	The Keyfactor Command reference ID of the certificate template the policy is associated with.		
	RSAValidKeySiz	An object containing a comma-delimited list of integers defining the valid RSA key sizes supported for all templates used for enrollment. The supported values are:  • 2048 • 4096		
	ECCValidCurves	An object containing a list of strings defining the valid elliptic curve		

Name	Description		
	Value	Description	
		algorithms for ECC templates. These may be specified using the well-known OIDs for ECC algorithms or by friendly name. Well-known OIDs include:  • 1.2.840.10045.3.1.7 = P-256/prime256v1/secp256r1  • 1.3.132.0.34 = P-384/secp384r1  • 1.3.132.0.35 = P-521/secp521r1  When specifying by friendly name, do not include a slash (use "P-256", not "P-256/prime256v1/secp256r1").	
	AllowKeyReuse	A Boolean that indicates whether private key reuse is allowed (true) or not (false). This option applies to certificate renewals. By default, this is set to <i>true</i> at a system-wide level.	
	AllowWildcards	A Boolean that indicates whether wildcards are allowed (true) or not (false). By default, this is set to <i>true</i> at a system-wide level.	
	RFCEnforcement	A Boolean that indicates whether RFC 2818 compliance enforcement is enabled (true) or not (false). When this option is set to <i>true</i> , certificate enrollments made through Keyfactor Command for this template must include at least one DNS SAN. In the Keyfactor Command Management Portal, this causes the CN entered in PFX enrollment to automatically be replicated as a SAN, which the user can either change or accept. For CSR enrollment, if the CSR does not have a SAN that matches the CN, one will automatically be added to the certificate if this is set. By default, this is set to <i>false</i> at a system-wide level.	
	AllowEd448	A Boolean that indicates whether Ed448 key type is allowed (true) or not (false).	
	AllowEd25519	A Boolean that indicates whether Ed25519 key type is allowed (true) or not (false).	
UseAl- lowedRequesters	(true) or not (false). The R Command security roles t in Keyfactor Command us Microsoft templates that Keyfactor Command cann which users can enroll for similar to setting request	whether the Restrict Allowed Requesters option should be enabled Restrict Allowed Requesters option is used to select Keyfactor that a user must belong to in order to successfully enroll for certificates sing this template. This is typically used for EJBCA templates and are not in the local Active Directory forest, since in these cases, not make use of the access control model of the CA itself to determine a certificates; this setting replaces that functionality. This setting is certificates for the selected security roles at the template level on a to granting permissions at the template level, you need enable the	

Name	Description			
	Restrict Allowed Requesters option to grant permissions at the CA level. See <i>Adding or Modifying a CA Record</i> in the <i>Keyfactor Command Reference Guide</i> for more information.			
AllowedRequesters	An object containing the list of Keyfactor Command security roles—as strings—that have been granted enroll permission on the template.			
DisplayName	name is configu	A string indicating the Keyfactor Command display name of the template. If a template friendly name is configured, this is used as the display name. If not, the template name is used. The display name appears in the dropdowns for PFX enrollment, CSR enrollment, and CSR generation. The display name is a generated field and is not directly configurable.		
RequiresApproval	A Boolean indicating whether the template has been configured with the Microsoft <i>CA certificate manager approval</i> option enabled ( <i>true</i> ) or not ( <i>false</i> ).			
	Important: Any templates that are configured on the Microsoft CA Issuance Requirements tab for CA certificate manager approval cannot be used for enrollment and associated alerting in Keyfactor Command without configuring private key retention. Any of the enabled private key retention settings (settings other than none as described for KeyRetention) will allow a template requiring manager approval to work with Keyfactor Command PFX and CSR enrollment.    Corp Web Server - RA Properties			
KeyUsage	An integer indicating the total key usage of the certificate. Key usage is stored in Active Directory as a single value made of a combination of values. The values that make up the key usage value include:			
	Value	Description		
	0	None	No key usage parameters.	
			The key can be used for encryption only.	
			The key can be used to sign a certificate revocation list (CRL).	

Name	Description			
	Value	Function	Description	
	4	Key Certificate Signing	The key can be used to sign certificates.	
	8	Key Agreement	The key can be used to determine key agreement, such as a key created using the Diffie-Hellman key agreement algorithm.	
	16	Data Encipherment	The key can be used for data encryption.	
	32	Key Encipherment	The key can be used for key encryption.	
	64	Nonrepudiation	The key can be used for authentication.	
	128	Digital Signature	The key can be used as a digital signature.	
	32768 Decipherment Only		The key can be used for decryption only.	
	For example, a value of 160 would represent a key usage of digital signature with key encip ment. A value of 224 would add nonrepudiation to those.			
ExtendedKeyUsages			usage information for the template. This field is popule. The extended key usage object contains the following	
	Name	Description		
	ld An integer indic		ating the ID of the extended key usage in Active	
	Oid	A string contain	A string containing the object ID of the extended key usage.	
	DisplayName		A string specifying the display name of the extended key usage (e.g. Server Authentication).	
Curve	A string indicating the OID of the elliptic curve algorithm configured for the template, for ECC templates. Well-known OIDs include:  • 1.2.840.10045.3.1.7 = P-256/prime256v1/secp256r1  • 1.3.132.0.34 = P-384/secp384r1  • 1.3.132.0.35 = P-521/secp521r1		le:	

#### 2.2.29.7 POST Templates/Import

The POST /Templates/Import method is used to import templates from a specified configuration tenant into Keyfactor Command. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: PkiManagement: *Modify* 

Table 558: POST Templates/Import Input Parameters

Name	Description
ConfigurationTenant	A string indicating the name of the configuration tenant from which to import.

#### 2.2.30 Workflow Certificates

The endpoints in Keyfactor Command that are found under /Workflow/Certificates refer to the process through which certificate requests that are require manager approval at the CA level before issuance are approved or denied. These endpoints provide the ability to obtain a list of pending certificate enrollment requests, and approve or deny current requests. Endpoints are also included to view denied and external validation requests.



Note: Certificate requests that require approval at the Keyfactor Command workflow level (see <u>Workflow Definitions</u> in the *Keyfactor Command Reference Guide*) are not managed with these endpoints. Instead, refer to the Workflow Definitions and Workflow Instances endpoints (see <u>Workflow Definitions on page 1234</u> and Workflow Instances on page 1325).

Table 559: Workflow Certificates Endpoints

Endpoint	Method	Description	Link
/Certificates/{id}	GET	Retrieve certificate request information for a single request.	GET Workflow Certificates  ID on the next page
/Certificates/Denied	GET	Retrieve a list of denied certificate request(s).	GET Workflow Certificates Denied on page 1225
/Certificates/Pending	GET	Retrieve a list of outstanding pending certificate request(s).	GET Workflow Certificates Pending on page 1227
/Certificates/ExternalValidation	GET	Retrieve a list of certificate request(s) requiring external validation.	GET Workflow Certificates External Validation on page 1229
/Certificates/Approve	POST	Approve a list of pending certificate request(s).	POST Workflow Certificates Approve on page 1233

Endpoint	Method	Description	Link
/Certificates/Deny	POST	Deny a list of pending certificate request(s).	POST Workflow Certificates  Deny on page 1231

#### 2.2.30.1 GET Workflow Certificates ID

The Workflow GET /Certificates/{id} method is used to return details for a certificate enrollment request stored within Keyfactor Command that requires manager approval at the CA level. This method returns HTTP 200 OK on a success with the specified certificate request. This method will return certificate requests with any state (e.g. Pending, Denied, External Validation).



**Note:** Certificate requests that require approval at the Keyfactor Command workflow level (see *Workflow Definitions* in the *Keyfactor Command Reference Guide*) are not managed with this endpoint. Instead, refer to the Workflow Definitions and Workflow Instances endpoints (see <a href="Workflow Definitions on page 1234">Workflow Definitions on page 1234</a> and Workflow Instances on page 1325).



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: WorkflowManagement: *Read* 

Table 560: GET Workflow Certificates {id} Input Parameters

Name	In	Description
id	Path	Required. An integer indicating the ID of the certificate request to retrieve.  Use the GET /Workflow/Certificates/Pending method (see GET Workflow Certificates Pending on page 1227) to retrieve a list of all the certificate requests to determine the certificate request ID.

Table 561: GET Workflow Certificates {id} Input Parameters

Name	Description		
DenialComment	A string containing the user-provided comment entered when the certificate request was denied.		
KeyLength	An integer indicating the	ne key length of the certificate request.	
SANs	An object containing a comma delimited list of strings listing the subject alternative name elements of the certificate request.		
CertStores	An object containing the certificate store locations to which the certificate resulting from the request will be distributed once approved. Certificate store location data includes:		
	Name	Description	
	EntryName	A string indicating the alias of the certificate in the certificate store. This value will be blank for store types that use information from the issued certificate (e.g. the thumbprint) as the alias until the request is approved and a certificate issued.	
	ClientMachine	A string indicating the machine on which the certificate store is located.	
	StorePath	A string indicating the path on the machine where the certificate store is located. The format of this will vary depending on the type of store.	
Curve	A string indicating the OID of the elliptic curve algorithm configured used for the certificate request, for ECC certificate requests. Well-known OIDs include:  • 1.2.840.10045.3.1.7 = P-256/prime256v1/secp256r1  • 1.3.132.0.34 = P-384/secp384r1  • 1.3.132.0.35 = P-521/secp521r1		
Id	An integer indicating the reference ID in Keyfactor Command for the certificate request as stored in the Keyfactor Command database. This is not the same as the request ID issued by the CA. This maps to the KeyfactorRequestId parameter for pending certificate request approve and deny actions.		
		erence ID for the certificate request in Keyfactor Command does not tch the reference ID for the issued certificate in Keyfactor Command.	
CARequestId	An integer indicating the	he row index of the certificate request in the certificate authority.	

Name	Description	
CommonName	A string indicating the common name of the requested certificate.	
DistinguishedName	A string indicating the distinguished name of the requested certificate.	
SubmissionDate	The date and time at which the certificate request was received, as an ISO-8601 formatted UTC timestamp.	
CertificateAuthority	A string indicating the name of the certificate authority from which the certificate was requested in hostname\logical name format. For example:  corpca01.keyexample.com\\CorpIssuingCA1	
Template	A string indicating the name of the template used for the certificate request.	
Requester	A string containing the name of the identity that requested the certificate.	
State	An integer indicating the request state of the certificate. The possible values are:  • Unknown (0)  • Active (1)  • Revoked (2)  • Denied (3)  • Failed (4)  • Pending (5)  • Certificate Authority (6)  • Parent Certificate Authority (7)  • External Validation (8)	
StateString	A string indicating the request state of the certificate (e.g. Pending).	
Metadata	An array containing the metadata fields populated for the certificate request.	

#### 2.2.30.2 GET Workflow Certificates Denied

The GET /Workflow/Certificates/Denied method is used to return a list of denied certificate enrollment requests stored within Keyfactor Command for requests that required manager approval at the CA level. Results can be limited to selected requests using filtering, and URL parameters can be used to specify paging and the level of information detail. This method returns HTTP 200 OK on a success with the specified denied certificate requests.



**Note:** Certificate requests that require approval at the Keyfactor Command workflow level (see *Workflow Definitions* in the *Keyfactor Command Reference Guide*) are not managed with this endpoint. Instead, refer to the Workflow Definitions and Workflow Instances endpoints (see <a href="Workflow Definitions on page 1234">Workflow Instances on page 1234</a>).



Table 562: GET Workflow Certificates Denied Input Parameters

Name	In	Description	
queryString	Query	A string containing a query to limit the results (e.g. field1 -eq value1 AND field2 -gt value2). The default is to return all records. Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns for the same feature. For querying guidelines, refer to the Keyfactor Command Reference Guide: Certificate Search Page. The query fields supported for this endpoint are:  • CAHostname  • CALogical  • CommonName  • Requester  • RequestType (3 Denied, 5-Pending, 8-External Validation)  This method only returns records of type (State) 3.  • SubmissionDate  • Template  Tip: For example, for recent denied requests from requester key_service: SubmissionDate -ge "2022-09-01T00:00:00Z" AND Requester -eq "KEYEXAMPLE\key_service"	
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.	
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.	
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>CommonName</i> .	
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.	

Table 563: GET Workflow Certificates Denied Response Data

Name	Description
Id	An integer indicating the reference ID in Keyfactor Command for the certificate request as stored in the Keyfactor Command database. This is not the same as the request ID issued by the CA. This maps to the KeyfactorRequestId parameter for pending certificate request approve and deny actions.
CARequestId	An integer indicating the row index of the certificate request in the certificate authority.
CommonName	A string indicating the common name of the requested certificate.
DistinguishedName	A string indicating the distinguished name of the requested certificate.
SubmissionDate	The date and time at which the certificate request was received, as an ISO-8601 formatted UTC timestamp.
CertificateAuthority	A string indicating the name of the certificate authority from which the certificate was requested in hostname\logical name format. For example: corpca01.keyexample.com\\CorpIssuingCA1
Template	A string indicating the name of the template used for the certificate request.
Requester	A string containing the name of the identity that requested the certificate.
State	An integer indicating the request state of the certificate.
	Note: This method returns only requests with state 3 (denied).
StateString	A string indicating the request state of the certificate (e.g. Pending).
	Note: This method returns only requests with a Denied state.
Metadata	An array containing the metadata fields populated for the certificate request.

# 2.2.30.3 GET Workflow Certificates Pending

The GET /Workflow/Certificates/Pending method is used to return a list of pending certificate enrollment requests stored within Keyfactor Command for requests that require manager approval at the CA level. Results can be limited to selected requests using filtering, and URL parameters can be used to specify paging and the level of information detail. This method returns HTTP 200 OK on a success with the specified pending certificate requests.



**Note:** Certificate requests that require approval at the Keyfactor Command workflow level (see *Workflow Definitions* in the *Keyfactor Command Reference Guide*) are not managed with this endpoint. Instead, refer to the Workflow Definitions and Workflow Instances endpoints (see <a href="Workflow Definitions on page 1234">Workflow Instances on page 1234</a>).



Table 564: GET Workflow Certificates Pending Input Parameters

Name	In	Description	
queryString	Query	A string containing a query to limit the results (e.g. field1 -eq value1 AND field2 -gt value2). The default is to return all records. Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns for the same feature. For querying guidelines, refer to the Keyfactor Command Reference Guide: Certificate Search Page. The query fields supported for this endpoint are:  • CAHostname  • CALogical  • CommonName  • Requester  • RequestType (3 Denied, 5-Pending, 8-External Validation)  This method only returns records of type (State) 5.  • SubmissionDate  • Template  Tip: For example, for recent pending requests from requester key_service: SubmissionDate -ge "2022-09-01T00:00:00Z" AND Requester -eq "KEYEXAMPLE\key_service"	
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.	
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.	
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>CommonName</i> .	
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.	

Table 565: GET Workflow Certificates Pending Response Data

Name	Description
Id	An integer indicating the reference ID in Keyfactor Command for the certificate request as stored in the Keyfactor Command database. This is not the same as the request ID issued by the CA. This maps to the KeyfactorRequestId parameter for pending certificate request approve and deny actions.
CARequestId	An integer indicating the row index of the certificate request in the certificate authority.
CommonName	A string indicating the common name of the requested certificate.
DistinguishedName	A string indicating the distinguished name of the requested certificate.
SubmissionDate	The date and time at which the certificate request was received, as an ISO-8601 formatted UTC timestamp.
CertificateAuthority	A string indicating the name of the certificate authority from which the certificate was requested in hostname\logical name format. For example: corpca01.keyexample.com\\CorpIssuingCA1
Template	A string indicating the name of the template used for the certificate request.
Requester	A string containing the name of the identity that requested the certificate.
State	An integer indicating the request state of the certificate.
	Note: This method returns only requests with state 5 (pending).
StateString	A string indicating the request state of the certificate (e.g. Pending).
	Note: This method returns only requests with a Pending state.
Metadata	An array containing the metadata fields populated for the certificate request.

#### 2.2.30.4 GET Workflow Certificates External Validation

The GET /Workflow/Certificates/ExternalValidation method is used to return a list of certificate enrollment requests requiring external validation (at the public CA level) stored within Keyfactor Command. Results can be limited to selected requests using filtering, and URL parameters can be used to specify paging and the level of information detail. This method returns HTTP 200 OK on a success with the specified certificate requests requiring external validation.



**Note:** Certificate requests that require approval at the Keyfactor Command workflow level (see *Workflow Definitions* in the *Keyfactor Command Reference Guide*) are not managed with this endpoint. Instead, refer

to the Workflow Definitions and Workflow Instances endpoints (see  $\underline{\text{Workflow Definitions on page 1234}}$  and Workflow Instances on page 1325).



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: WorkflowManagement: *Read* 

Table 566: GET Workflow Certificates External Validation Input Parameters

Name	In	Description
queryString	Query	A string containing a query to limit the results (e.g. field1 -eq value1 AND field2 -gt value2). The default is to return all records. Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns for the same feature. For querying guidelines, refer to the Keyfactor Command Reference Guide: Certificate Search Page. The query fields supported for this endpoint are:  • CAHostname  • CALogical  • CommonName  • Requester  • RequestType (3 Denied, 5-Pending, 8-External Validation)  This method only returns records of type (State) 8.  • SubmissionDate  • Template  Tip: For example, for recent external validation requests from requester key_service:  SubmissionDate -ge "2022-09-01T00:00:002" AND Requester -eq  "KEYEXAMPLE\key_service"
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>CommonName</i> .
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.

Table 567: GET Workflow Certificates External Validation Response Data

Name	Description
Id	An integer indicating the reference ID in Keyfactor Command for the certificate request as stored in the Keyfactor Command database. This is not the same as the request ID issued by the CA. This maps to the KeyfactorRequestId parameter for pending certificate request approve and deny actions.
CARequestId	An integer indicating the row index of the certificate request in the certificate authority.
CommonName	A string indicating the common name of the requested certificate.
DistinguishedName	A string indicating the distinguished name of the requested certificate.
SubmissionDate	The date and time at which the certificate request was received, as an ISO-8601 formatted UTC timestamp.
CertificateAuthority	A string indicating the name of the certificate authority from which the certificate was requested in hostname\logical name format. For example: corpca01.keyexample.com\\CorpIssuingCA1
Template	A string indicating the name of the template used for the certificate request.
Requester	A string containing the name of the identity that requested the certificate.
State	An integer indicating the request state of the certificate.
	Note: This method returns only requests with state 8 (external validation).
StateString	A string indicating the request state of the certificate (e.g. Pending).
	Note: This method returns only requests with an External Validation state.
Metadata	An array containing the metadata fields populated for the certificate request.

## 2.2.30.5 POST Workflow Certificates Deny

The POST /Workflow/Certificates/Deny method will attempt to deny the provided pending certificate enrollment request(s) that require manager approval at the CA level. The certificate request IDs should be supplied in the request body as a JSON array of integers. This method returns HTTP 200 OK on a success with details about successful, failed and denied denial requests.



**Note:** Certificate requests that require approval at the Keyfactor Command workflow level (see *Workflow Definitions* in the *Keyfactor Command Reference Guide*) are not managed with this endpoint. Instead, refer to the Workflow Definitions and Workflow Instances endpoints (see <a href="Workflow Definitions on page 1234">Workflow Definitions on page 1234</a> and Workflow Instances on page 1325).



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: WorkflowManagement: *Participate* 

Table 568: POST Workflow Certificates Deny Input Parameters

Name	In	Description
CertificateRequestIds	Body	Required. An array of Keyfactor Command certificate request IDs for certificate requests that should be denied in the form:  [23,45,12]  Use the GET /Workflow/Certificates/Pending method (see GET Workflow Certificates Pending on page 1227) to retrieve a list of all the pending certificate requests to determine the certificate request's IDs.
Comment	Body	A string providing a comment regarding the denial. This comment can be delivered to the requester or other interested party using a denied request alert.

Table 569: POST Workflow Certificates Deny Response Data

Name	Description			
Successes	An array of the successful denial response details. Response details contain the following information:			
	Name	Description		
	CAHost	Host name of the certificate authority to which the certificate enrollment request was submitted.		
	CALogicalName	Logical name of the certificate authority to which the certificate enrollment request was submitted.		
	CARequestId	The row index of the certificate request in the certificate authority.		
	KeyfactorRequestId	An integer indicating the Keyfactor Command reference ID for the requested certificate as stored in the Keyfactor Command database. This is not the same as the request ID issued by the CA. This maps to the Id response parameter for the GET /Workflow/Certificate/Pending method.		
	Comment	A comment about the denial. For example, for a deny that succeeds, the comment will be "Successful". Denies that fail or are denies will have alternate comments (see below).		
Failures	An array of the failed approval response details containing the information noted above for successes. Failures of this type are generally exceptions.			
Denials	An array of the denial requests that were denied containing the information noted above for successes. Denials are usually the result of insufficient user permissions required to perform the deny.			

### 2.2.30.6 POST Workflow Certificates Approve

The POST /Workflow/Certificates/Approve method will attempt to approve the provided pending certificate enrollment request(s) that require manager approval at the CA level. The certificate request IDs should be supplied in the request body as a JSON array of integers. This method returns HTTP 200 OK on a success with details about successful, failed and denied approval requests.



**Note:** Certificate requests that require approval at the Keyfactor Command workflow level (see *Workflow Definitions* in the *Keyfactor Command Reference Guide*) are not managed with this endpoint. Instead, refer to the Workflow Definitions and Workflow Instances endpoints (see <u>Workflow Definitions on the next page</u> and Workflow Instances on page 1325).



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: WorkflowManagement: *Participate* 

Table 570: POST Workflow Certificates Approve Input Parameters

Name	In	Description
requestIds	Body	Required. An array of Keyfactor Command certificate request IDs for certificate requests that should be approved in the form (without parameter name):  [23,45,12]  Use the GET /Workflow/Certificates/Pending method (see GET Workflow Certificates  Pending on page 1227) to retrieve a list of all the certificate requests to determine the certificate request's IDs.

Table 571: POST Workflow Certificates Approve Response Data

Name	Description			
Successes	An array of the successful approval response details. Response details contain the following information:			
	Name	Description		
	CAHost	Host name of the certificate authority to which the certificate enrollment request was submitted.		
	CALogicalName	Logical name of the certificate authority to which the certificate enrollment request was submitted.		
	CARequestId	The row index of the certificate request in the certificate authority.		
	KeyfactorRequestId	An integer indicating the Keyfactor Command reference ID for the requested certificate as stored in the Keyfactor Command database. This is not the same as the request ID issued by the CA. This maps to the Id response parameter for the GET /Workflow/Certificate/Pending method.		
	Comment	A reason or description about why the request denials succeeded, failed or were denied.		
Failures	An array of the failed approval response details containing the information noted above for successes. Failures of this type are generally exceptions.			
Denials	An array of the approval requests that were denied containing the information noted above for successes. Denials are usually the result of insufficient user permissions required to perform the approval.			

# 2.2.31 Workflow Definitions

The Workflow Definitions component of the Keyfactor API includes methods necessary to programmatically create, edit, retrieve, and test workflow definitions. There are two types of workflow definition:

#### Global

The global workflow definitions are built into the product and cannot be deleted, though they can be modified to add workflow steps, if desired. Global workflow definitions do not have a specific associated *key*—in the case of the currently available workflows, this is a *certificate template*—and apply to all requests of the workflow's type (e.g. enrollment) that are not otherwise handled by a custom workflow specifying a key.

#### Custom

Custom workflow definitions are any additional workflow definitions you define beyond the built-in ones. Custom workflows are associated with a specific *key* (certificate template) and each workflow only applies to requests made using that key.

All enrollment, certificate renewal, and revocation requests go through workflow even if you haven't created any workflow steps or added any custom workflow definitions. In the absence of customization, the global workflow definitions are used.

For more information about workflow, see the <u>Workflow Definitions</u> section in the *Keyfactor Command Reference Guide*.

Table 572: Workflow Definitions Endpoints

Endpoint	Method	Description	Link
/Steps/{extensionName}	GET	Returns information about the structure of the workflow definition step with the specified name.	GET Workflow Definitions Steps Extension Name on the next page
/{definitionId}	DELETE	Deletes the workflow definition with the specified GUID.	DELETE Workflow Definitions Definition ID on page 1237
/{definitionId}	GET	Returns details of the workflow definition, including steps, for the workflow with the specified GUID.	GET Workflow Definitions Definition ID on page 1238
/{definitionId}	PUT	Updates the name and description of the workflow definition with the specified GUID.	PUT Workflow Definitions Definition ID on page 1253
/	GET	Returns a list of workflow definitions, without steps.	GET Workflow Definitions on page 1269
/	POST	Creates a new workflow definition, without steps.	POST Workflow Definitions on page 1271
/Steps	GET	Returns information about the structure of the workflow definitions.	GET Workflow Definitions Steps on page 1287
/Types	GET	Returns a list of the defined workflow definition types.	GET Workflow Definitions Types on page 1289

Endpoint	Method	Description	Link
/{definitionId}/Steps	PUT	Updates the workflow definition with the specified GUID to add new steps or modify existing steps.	PUT Workflow Definitions Definition ID Steps on page 1291
/{definitionId}/Publish	POST	Publishes the workflow definition with the specified GUID to activate it for use.	POST Workflow Definitions Definition ID Publish on page 1309

## 2.2.31.1 GET Workflow Definitions Steps Extension Name

The GET /Workflow/Definitions/Steps/{extensionName} method is used to retrieve the workflow definition step structure for the step with the specified extensionName. Its primary use case is to populate the UI dialog in which step information is configured. When you are developing a custom workflow step, it can be used to confirm that the workflow step will display correctly in the UI. This method returns HTTP 200 OK on a success with information about the structure of the workflow definition step.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: WorkflowDefinitions: *Read* 

Table 573: GET Workflow Definitions Steps {extensionName} Input Parameters

Name	In	Description
extensionName	Path	Required. A string indicating the <i>extensionName</i> of the workflow definition step to retrieve.  Use the <i>GET /Workflow/Definitions/Steps</i> method (see <u>GET Workflow Definitions</u> <u>Steps on page 1287</u> ) to retrieve a list of all the workflow definition steps to determine the extensionName.

Table 574: GET Workflow Definitions Steps {extensionName} Response Data

Name	Description
DisplayName	A string indicating the display name of the workflow definition step.
ExtensionName	A string indicating the extension name of the workflow definition step. The built-in extension names are:  • Email—Send an email message. This is a separate email message from those typically sent as part of a *RequireApproval* step.*  • EnrollStep—Enroll for a certificate through Keyfactor Command.  • NOOPStep—An entry or exit step in which no operation occurs. Steps of this type indicate the start and end of the workflow.  • PowerShell—Run a PowerShell script. The script contents are embedded within the step. It does not call out to an external file.  • RequireApproval—Require approval for a workflow step before the step can be completed. This step includes logic to gather the correct number of approvals from the users with the correct security roles and to send an email message indicating whether the step was approved or denied. This step does not include logic to send an email initiating the approval process. Use an *Email* type for this.  • Important: Workflows are not supported with CA delegation when they contain steps that require approval. For more information, see the CA configuration *Authorization Methods Tab* in the *Keyfactor Command Reference Guide.*  • RestRequest—Run a REST request. The REST request contents are embedded within the step. It does not call out to an external file.  • RevokeStep—Revoke a certificate through Keyfactor Command.
Outputs	
Outputs	An object containing the outputs for the workflow definition step. For the built- in steps, the only output is an indicator for the next step in the workflow.
ConfigurationParametersDefinition	An object containing the configuration parameters for the workflow definition step. These will vary depending on the step.
SignalsDefinition	An object containing the signals defined for the workflow definition step. These will vary depending on the step.

## 2.2.31.2 DELETE Workflow Definitions Definition ID

The DELETE /Workflow/Definitions/{definitionid} method is used to delete the workflow definition with the specified GUID. This endpoint returns 204 with no content upon success.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: WorkflowDefinitions: *Modify* 



**Note:** The built-in global workflow definitions (*Global Revocation Workflow* and *Global Enrollment Workflow*) cannot be deleted. A workflow definition cannot be deleted if there is an active or suspended workflow instance for the workflow definition.

Table 575: DELETE Workflow Definitions {definitionid} Input Parameters

Name	In	Description
definitionId	Path	<b>Required</b> . A string indicating the Keyfactor Command reference GUID of the workflow definition to delete.
		Use the $GET$ /Workflow/Definitions method (see $\underline{GET}$ Workflow Definitions on page 1269) to retrieve a list of all the workflow definitions to determine the GUID.

#### 2.2.31.3 GET Workflow Definitions Definition ID

The GET /Workflow/Definitions/{definitionid} method is used to retrieve the workflow definition with the specified GUID. This method returns HTTP 200 OK on a success with details about the specified workflow definition.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: WorkflowDefinitions: *Read* 

Table 576: GET Workflow Definitions {definitionid} Input Parameters

Name	In	Description
definitionId	Path	Required. A string indicating the Keyfactor Command reference GUID of the workflow definition to retrieve.  Use the GET /Workflow/Definitions method (see GET Workflow Definitions on page 1269) to retrieve a list of all the workflow definitions to determine the GUID.
definitionVersion	Query	An integer indicating which version of the workflow definition to return. The default is to return the most recent version (which may not necessarily be the published version).
exportable	Query	A Boolean indicating whether any security Rolelds (see Security Roles on page 893) in the workflow definition should be removed from the response (true) or not (false). A value of <i>true</i> allows for the workflow definition to be exported without role-specific data. The default is <i>false</i> .

Table 577: GET Workflow Definitions {definitionsid} Response Data

Name	Description			
Id	A string indicating	the Keyfactor Command reference GUID of the workflow definition.		
DisplayNa- me	A string indicating	the display name defined for the workflow definition.		
Descrip- tion	A string indicating the description for the workflow definition.			
Key	field will vary depe	the reference key for the workflow definition. The type of information contained in this nding on the <i>WorkflowType</i> . If the <i>WorkflowType</i> is <i>Enrollment</i> or <i>Revocation</i> , this field yfactor Command reference ID for the certificate template.		
KeyDis- playName	A string indicating	the friendly name defined in Keyfactor Command for the certificate template.		
IsPub- lished		ng whether the workflow definition has been published (true) or not (false). A workflow published to activate it. For a newly created workflow, this will be <i>false</i> .		
Work- flowType	A string indicating the type of workflow definition. The currently supported types are:  • Enrollment  • Revocation			
Steps	An array of objects indicating the steps in the workflow definition. The contents of each step will vary depending on the type of workflow and the type of step. For a newly created workflow, there will be no data in this value. Possible steps include:			
	Name	Description		
	Id	A string indicating the Keyfactor Command reference GUID of the workflow definition step.		
	DisplayName	A string indicating the display name for the step.		
	UniqueName A string indicating the unique name for the step. This value must be unique among the steps in the particular workflow definition. It is intended to be used as a user-friendly reference ID.			
	Exten- sionName	A string indicating the type of step. The currently supported types are:  • Email		

Name	Description				
	Name	Description			
		Send an email message. This is a separate email message from those typically sent as part of a <i>Require Approval</i> step. You might send an email message as part of an enrollment request to notify approvers that a new request needs approval. The email messages can be customized to provide detailed information about, for example, the certificate request.  • PowerShell  Run PowerShell commands within the confines of the workflow to populate variables with information to pass back to the workflow. The PowerShell script contents are embedded within the step. This step does not call out to an external file. This provides a high level of security by greatly limiting the number of standard PowerShell cmdlets that can be executed by the workflow step. A small number of PowerShell cmdlets have been white listed to allow them to be included in workflow steps of this type, including:  • Where-Object  • ForEach-Object  • Get-Command  • CustomPowerShell  Run a PowerShell script. The script contents are in a file placed in the ExtensionLibrary\Workflow directory or a subdirectory of it on the Keyfactor Command server under the install directory for Keyfactor Command. By default, this is:  C:\Program Files\Keyfactor\Keyfactor Platform\ExtensionLibrary\Workflow			
		The file must have an extension of .ps1. A sample PowerShell script is provided in the Workflow directory (CustomPowershellExample.ps1).			
		RequireApproval  Require approval for a workflow step before the step can be completed. The			
		require approval step applies to certificate enrollments, renewals, and revocations and can require approval from just one approver or multiple approvers. The workflow will be suspended at this point until the correct number of approvals from users with the correct security roles is received or until one deny is received before continuing to the next step. As part of this step, an email message is sent indicating whether the step was approved or denied—typically to the requester. This step does not include logic to send an email initiating the approval process (letting users know something needs approval). Use an <i>Email</i> type step for this.			
		Important: Workflows are not supported with CA delegation when they contain steps that require approval. For more information, see			

Name	Description	
	Name	Description
		the CA configuration Authorization Methods Tab in the Keyfactor Command Reference Guide.
		Tip: The workflow builder does not include a step to send a notification to the requester of a certificate once the certificate is issued by the CA (as opposed to approved in Keyfactor Command). Use the issued alerts for this (see Issued Request Alert Operations in the Keyfactor Command Reference Guide).
		RESTRequest
		Run a REST (API) request. The REST request contents are embedded within the step. It does not call out to an external file.
		• EnrollmentAgent
		On an enrollment (either CSR or PFX), create a resigned CSR to prepare an updated enrollment request for delivery to a Microsoft CA after a previous step in the workflow has been used to update either the SANs in the initial request, subject (DN) in the initial request or both. This step must be placed later in the workflow than the step(s) to modify the SANs and/or subject. The SANs and subject may be modified with either of the PowerShell step types or a custom step type. The step creates a new CSR using the same public key as the original CSR using the updated SAN and/or subject values. It signs the new CSR with the certificate provided in the step's configuration.
		For this type of step you will need an enrollment agent certificate available as a PKCS#12 (.PFX) file with included private key to import into Keyfactor Command. This can be a user certificate or a computer certificate (e.g. generated from a copy of the "Enrollment Agent" template or the "Enrollment Agent (Computer)" template) and must have a Certificate Request Agent EKU. Note that the built-in "Enrollment Agent" and "Enrollment Agent (Computer)" templates do not allow private keys to be exported by default. You will need a template that allows private key export or will need to manually override private key export to create a certificate with an exportable private key in order to create a PKCS#12 (.PFX) file.
		Important: This step applies to Microsoft CAs only. If this step is added to workflow for requests directed to an EJBCA CA, it will fail on enrollment. Note that EJBCA supports submission of updated SAN or subject details as part of standard functionality.
		• EnrollStep

Name	Description		
	Name	Description	
		Enroll for a certificate through Keyfactor Command. The enroll step of always fall as the last step in the workflow, immediately following the EndNOOP step.  • NOOPStep  An entry or exit step in which no operation occurs. Steps of this type the start and end of the workflow.  • RevokeStep  Revoke a certificate through Keyfactor Command. The revoke step of always fall as the last step in the workflow, immediately following the EndNOOP step.  Tip: For steps that send email messages, the SMTP settings and see information come from the standard Keyfactor Command SMTP configuration (see SMTP on page 1081) and are not configurationally in the workflow steps.	
	Enabled	A Boolean indicating whe	ther the step is enabled to run (true) or not (false).
	Config- urationPara- meters	An array containing the co	onfiguration parameters for the workflow definition step.  3 on the type of workflow and the type of step (see <i>Exten</i> -
		Note: There are NOOPStep, or Rev	no ConfigurationParameters for steps of type EnrollStep, vokeStep.
		Possible CustomPowerSh	nell parameters include:
		Value	Description
		ScriptParameters	An array of key/value pair strings defining any parameters to be used in the PowerShell script.
		ScriptName	The path and filename for the script to execute. The script needs to be in the ExtensionLibrary\Workflow directory or a subdirectory of it on the Keyfactor Command server under the install directory. By default, this is:  C:\Program Files\Keyfactor\Keyfactor

Name	Description				
	Name	Description	Description		
		Value	Description		
			Platform\ExtensionLibrary\Workflow The file must have an extension of .ps1. A sample PowerShell script is provided in the Workflow directory (CustomPowershellExample.ps1).		
		meter replace metace comm	Tokens (a.k.a. substitutable special text) may be used in the script parar value field. Tokens use a variable in the workflow definition that is ced by data from the certificate request, certificate, or certificate data at processing time. For example, you can take the revocation nent entered when the revocation request is approved—\$(cmnt)—and additional data to it using PowerShell.		
		Possible <b>Ema</b>	Possible <b>Email</b> parameters include:		
		Value	Description		
		Subject	A string indicating the subject line for the email message that will be delivered when the workflow definition step is executed.		
		Message	A string indicating the email message that will be delivered when the workflow definition step is executed. The email message is made up of regular text and tokens. If desired, you can format the message body using HTML. For example, for an enrollment pending request notification:		
			"Hello,\n\nA certificate using the \$(template) template was requested by \$(requester:displayname) from \$(CA) on \$(subdate). The certificate details include:\n\n\n Certificate Details Hello,\n\n\n CA) on \$(subdate). The certificate details include:\n\n\n Certificate Details Hello,\n CA) on \$(subdate). The certificate details include:\n\n Certificate Details Hello,\n CA) on \$(subdate). The certificate details include:\n\n CETIFICATION (STEP) (STEP		
			\$(request:dn)\$(metadata:Ap-pOwnerLast Name: \$(metadata:Ap-pOwnerLastName)\$(sans)\$(sans)\$(metadata:Ap-pOwnerEmail Address: \$(metadata:Ap-pOwnerEmail Address: \$(metadata:Ap-pOwn-		
			erEmailAddress)\n Business		

Name	Description	Description		
	Name	Description		
		Value	Description	
			Critical: \$(metadata:BusinessCritical)\n\nPlease review this request and issue the certificate as appropriate by going here:\n\n\$(reviewlink)\n\nThanks!\n\nYour Certificate Management Tool\n"  See Table 1: Tokens for Workflow Definitions in the Keyfactor Command Reference Guide for a complete list of available tokens.	
		Recip- ients	An array of strings containing the recipients for the workflow definition email. Each email message can have multiple recipients. You can use specific email addresses and/or use tokens to replace an email address variable with actual email addresses at processing time. Available email tokens include:	
			\$(requester:mail)     The certificate requester, based on a lookup in Active     Directory of the email address associated with the     requester on the certificate.	
			<ul> <li>Your custom email-based metadata field, which would be specified similarly to \$(metadata:AppOwnerEmailAddress).</li> </ul>	
		messa defini certifi quest messa	Tokens (a.k.a. substitutable special text) may be used in the subject line, age and email recipient fields. Tokens use a variable in the workflow ition that is replaced by data from the certificate request, certificate, or icate metadata at processing time. For example, you can select \$(reser) in the workflow definition for an enrollment request and the email age will contain the specific certificate requester name instead of the ole \$(requester).	
		Possible <b>Pow</b>	verShell parameters include:	
		Value	Description	
		ScriptParam	An array of key/value pair strings defining any parameters to be used in the PowerShell script. The key is the name of a custom parameter defined by you and the value is the initial value that should be set for that parameter before the PowerShell is executed, if any.	

Name	Description					
	Name	Description				
		Value	Description			
			Tokens are supported in the value.			
		ScriptContent	A string containing the PowerShell commands to execute. This should be the actual contents of the PowerShell script (the PowerShell commands and supporting components), not a path and filename to an external file.			
		Tip: Tokens (a.k.a. substitutable special text) may be used in the script parameter value field. Tokens use a variable in the workflow definition that is replaced by data from the certificate request, certificate, or certificate metadata at processing time. For example, you can take the revocation comment entered when the revocation request is approved—\$(cmnt)—and append additional data to it using PowerShell.				
		Possible RequireApproval parameters include:				
		Value	Description			
		MinimumApprovals	In integer indicating the minimum number of users who must approve the request to allow the request to complete.			
		DenialEmailSubject	A string indicating the subject line for the email message that will be delivered if the request is denied.			
		DenialEmailMessage	A string indicating the email message that will be delivered if the request is denied. The email message is made up of regular text and tokens. If desired, you can format the message body using HTML.  See <i>Table: Tokens for Workflow Definitions</i> in the <i>Keyfactor Command Reference Guide</i> for a complete list of available tokens.			

Name	Description					
	Name	Description				
		Value	Description			
		DenialEmailRecipients	An array of strings containing the recipients for the denial email. Each email message can have multiple recipients. You can use specific email addresses and/or use tokens to replace an email address variable with actual email addresses at processing time. Available email tokens include:  • \$(requester:mail)  The certificate requester, based on a lookup in Active Directory of the email address associated with the requester on the certificate.  • Your custom email-based metadata field, which would be specified similarly to \$(metadata:AppOwnerEmailAddress).			
		ApprovalEmailSubject	A string indicating the subject line for the email message that will be delivered if the request is approved.			
		ApprovalEmailMessage	A string indicating the email message that will be delivered if the request is approved. The email message is made up of regular text and tokens. If desired, you can format the message body using HTML.  See <i>Table: Tokens for Workflow Definitions</i> in the <i>Keyfactor Command Reference Guide</i> for a complete list of available tokens.			
		ApprovalEmailRecipients	An array of strings containing the recipients for the approval email. Each email message can have multiple recipients. You can use specific email addresses and/or use tokens to replace an email address variable with actual email addresses at processing time. Available email tokens include:  • \$(requester:mail)  The certificate requester, based on a			

Name	Description				
	Name	Description	Description		
		Value	Description		
			lookup in Active Directory of the email address associated with the requester on the certificate.  • Your custom email-based metadata field, which would be specified similarly to \$(metadata:AppOwnerEmailAddress).		
		messag definition certifica quester messag	kens (a.k.a. substitutable special text) may be used in the subject line, e and email recipient fields. Tokens use a variable in the workflow on that is replaced by data from the certificate request, certificate, or ate metadata at processing time. For example, you can select \$(re-t) in the workflow definition for an enrollment request and the email e will contain the specific certificate requester name instead of the e \$(requester).		
		Possible <b>RestRe</b>	equest parameters include:		
		Value	Description		
		Headers	An array of key/value pair strings containing the header information for the request. The key is the name of the specific request header (for Keyfactor API request headers, see <a href="Table 1: Common Request Headers">Table 1: Common Request Headers</a> and the specific documentation for each endpoint) and the value is the value that should be set for that header. For a Keyfactor API request, this might look like:		
			<pre>"Headers": {     "x-keyfactor-requested-with": [</pre>		

Name	Description		
	Name	Description	
		Value	Description
			Tip: For a Keyfactor API request, version 1 is assumed if no version is specified. Content type and authorization headers do not need to be specified, since those are addressed elsewhere in the configuration.
		DataBuck- etProperty	A string containing the variable that the response from the request will be returned in, if any. You can then reference this parameter from subsequent steps in the workflow.
			Tip: The response is stored as a serialized JObject. To make use of only a portion of the response data in your subsequent step, use JSON path syntax. For example, say you returned the data from a GET /Agents request in a variable called MyResponse and you wanted to reference the ClientMachine name for the orchestrator in a subsequent email message. To limit the data to the first result and only the ClientMachine name, in the email message you would enter the following:  \$(MyResponse.[0].ClientMachine)
		Verb	A string indicating the HTTP verb for the type of request to perform. Supported values are:  DELETE GET HEAD OPTIONS POST PUT TRACE
		UseBasicAu- th	A Boolean indicating whether Basic authentication should be used for the request (True) or not (False).  If <i>UseBasicAuth</i> is <i>False</i> , Windows authentication in the context of the Keyfactor Command application pool user will be used (see <i>Create Active Directory Service Accounts for Keyfactor</i>

Name	Description				
	Name	Description	Description		
		Value	Description		
			Command in the K	eyfactor Command Server Installation Guide).	
		BasicUser- name	An array indicating tication if <i>UseBasic</i>	the username information to use for authen- Auth is True.	
			<ul> <li>Store the creatable.</li> <li>A Keyfactor sword that is Keyfactor Co</li> <li>Load the creatable See PAM Pro</li> </ul>	Is to store credential information are: Edential information in the Keyfactor secrets  Secret is a user-defined username or pass- encrypted and stored securely in the emmand database.  Idential information from a PAM provider. Eviders and Privileged Access Management Exeyfactor Command Reference Guide for ation.	
			Value	Description	
			SecretValue	A string containing the username defined for basic authentication (in DOMAIN\\username format).	
			Parameters	An array indicating the parameters to supply for PAM authentication. These will vary depending on the PAM provider.	
			Provider	A string indicating the ID of the PAM provider.  Use the GET /PamProviders method (see GET PAM Providers on page 724) to retrieve a list of all the PAM providers to determine the ID.	
			For example, the u	sername stored as a Keyfactor secret will look	

Name	Description		
	Name	Description	
		Value	Description
			<pre>{     "SecretValue": "KEYEXAMPLE\svc_MyServiceName" }</pre>
			The username stored as a CyberArk PAM secret will look like (where the Provider value—1 in this example—is the Id value from GET PAM Providers on page 724 and the Folder and Object reference the folder name and object name in the CyberArk safe):
			<pre>{     "Provider": "1",     "Parameters":{         "Folder":"MyFolderName",         "Object":"MyWorkflowUsername"     } }</pre>
			The username stored as a Delinea PAM secret will look like (where the Provider value—1 in this example—is the Id value from GET PAM Providers on page 724 and the SecretId is the ID if the secret created in the Delinea secret server for this purpose):
			<pre>{     "Provider": "1",     "Parameters":{         "SecretId":"MyUsernameId"     } }</pre>
			Due to its sensitive nature, this value is not returned in responses.
		BasicPass- word	An array indicating the password information to use for authentication if <i>UseBasicAuth</i> is <i>True</i> . The syntax is the same as for <i>BasicUsername</i> .  Due to its sensitive nature, this value is not returned in

Name	Description				
	Name	Description	Description		
		Value	Description		
			responses.		
		URL	A string containing the URL for the request, including tokens, if desired. For a Keyfactor API request, this might look like:  https://keyfactor.keyexample.com/KeyfactorAP I/Certificates?pq.queryString=CN%20- contains%20%22appsrvr14%22%20AND%20CertStore Path%20-ne%20NULL Or, with tokens: https://keyfactor.keyexample.com/KeyfactorAP I/Certificates/\$(certid)		
			Note: To prevent REST requests from being made to inappropriate locations by malicious users, configure a system environment variable of KEYFACTOR_BLOCKED_OUTBOUND_IPS on your Keyfactor Command server pointing to the IP address or range of addresses in CIDR format that you wish to block. Both IPv4 and IPv6 addresses are supported. More than one address or range may be specified in a comma-delimited list. For example:  192.168.12.0/24,192.168.14.22/24 When a REST request is made where the URL is either configured to a blocked IP address or resolves via DNS to a blocked IP address, the REST request will fail.		
		ContentTyp- e	A string indicating the content type for the request. Supported values are:  • application/json		
		RequestCon- tent	A string containing the body of the REST request, if needed. For a Keyfactor API request, this will vary depending on the request and might look like (for a PUT /Certificates/Metadata request):		
			{     "Id": "\$(certid)",		

# Description Name Name Description Value Description "Metadata":{ "RevocationComment": "\$(cmnt)" Note: This example assumes you have a metadata field called RevocationComment. Tip: Tokens (a.k.a. substitutable special text) may be used in the URL and request content fields. Tokens use a variable in the workflow definition that is replaced by data from the certificate request, certificate, or certificate metadata at processing time. For example, you can take the revocation comment entered when the revocation request is approved—\$(cmnt)—and insert it into a custom metadata field in the certificate by doing a PUT /Certificates/Metadata request for the \$(id). Signals An array of objects containing data used at the point in the workflow step where the workflow needs to continue based on user input. These will vary depending on the type of workflow and the type of step (see ExtensionName). Possible RequireApproval values are: Value **Description** RoleIds An array of integers indicating the security roles whose members are allowed to approve the request. SignalName A string indicating the name of the signal. This value will vary depending on the workflow step. For the built-in Require Approval step, the SignalName is "ApprovalStatus". Important: If all the security roles configured for a workflow step are deleted from Keyfactor Command, no users will be able to submit signals for workflow instances initiated with that workflow definition. To remedy this, update the workflow definition with one or more current security roles, republish it, and then restart any outstanding workflow instances.


Name	Description			
	Name	Description		
	Conditions	An object containing conditions indicating whether the step should run (true) or not (false). Conditions may either have a static value of True or False or a token that will have a value of True or False at the time the step is run. More than one condition may be added. If multiple conditions are used in the same step, all conditions must have a value of True at the time the step is evaluated to be run in order for the step to run. If any single condition evaluates to False, the step will not run. Condition values are:		
		Value	Description	
		Id	A string indicating the Keyfactor Command reference ID of the condition.	
		Value	A string indicating the value of the condition. This should be one of "true", "false", or a token that will be set to either "true" or "false" in an earlier step in the workflow (see Workflow Definition Operations: Adding or Modifying a Workflow Definition in the Keyfactor Command Reference Guide for an example).	
	Outputs	An array indicating the next step in the workflow. Possible values are:		
		Value	Description	
		continue	A string indicating the <i>UniqueName</i> of the next workflow step in the chain. This value will be null for the final step in the chain.	
DraftVer- sion	_	eger indicating the version number of the workflow definition. If this version number does not match blishedVersion, changes have been made to the workflow definition that have not yet been published.		
Published- Version	An integer indicating the currently published version number of the workflow definition. For a newly created workflow, this value will be null.			

#### 2.2.31.4 PUT Workflow Definitions Definition ID

The PUT /Workflow/Definitions/{definitionid} method is used to update the name and description for the workflow definition with the specified GUID. This method returns HTTP 200 OK on a success with details about the updated workflow definition.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: WorkflowDefinitions: *Modify* 



- Note: If you edit an existing *published* workflow definition, a new version of the workflow definition will be created. If you edit an existing workflow definition which has *never been published*, the existing configuration will be overwritten with the changes you've made—a new version will not be created.
- Warning: Any previously populated fields that are not submitted with their full existing data using this method will be cleared of their existing data. When using this method, you should first do a GET to retrieve all the values for the record you want to update, enter corrected data into the field(s) you want to update, and then submit all the fields using PUT, including the fields that contain values but which you are not changing.

Table 578: PUT Workflow Definitions {definitionid} Input Parameters

Name	In	Description	
definitionId	Path	<b>Required</b> . A string indicating the Keyfactor Command reference GUID of the workflow definition.	
DisplayName	Body	Required. A string indicating the display name defined for the workflow definition.	
Description	Body	A string indicating the description for the workflow definition.	

Table 579: PUT Workflow Definitions {definitionid} Response Body

Name	Description			
Id	A string indicating	the Keyfactor Command reference GUID of the workflow definition.		
DisplayNa- me	A string indicating the display name defined for the workflow definition.			
Descrip- tion	A string indicating	A string indicating the description for the workflow definition.		
Key	field will vary depe	the reference key for the workflow definition. The type of information contained in this nding on the <i>WorkflowType</i> . If the <i>WorkflowType</i> is <i>Enrollment</i> or <i>Revocation</i> , this field yfactor Command reference ID for the certificate template.		
KeyDis- playName	A string indicating	the friendly name defined in Keyfactor Command for the certificate template.		
IsPub- lished		ng whether the workflow definition has been published (true) or not (false). A workflow published to activate it. For a newly created workflow, this will be <i>false</i> .		
Work- flowType	A string indicating the type of workflow definition. The currently supported types are:  • Enrollment • Revocation			
Steps	An array of objects indicating the steps in the workflow definition. The contents of each step will vary depending on the type of workflow and the type of step. For a newly created workflow, there will be no data in this value. Possible steps include:			
	Name	Description		
	Id	A string indicating the Keyfactor Command reference GUID of the workflow definition step.		
	DisplayName	A string indicating the display name for the step.		
	UniqueName A string indicating the unique name for the step. This value must be unique among the steps in the particular workflow definition. It is intended to be used as a user-friendly reference ID.			
	Exten- sionName	A string indicating the type of step. The currently supported types are:  • Email		

Name	Description			
	Name	Description		
		Send an email message. This is a separate email message from those typically sent as part of a <i>Require Approval</i> step. You might send an email message as part of an enrollment request to notify approvers that a new request needs approval. The email messages can be customized to provide detailed information about, for example, the certificate request.  • PowerShell  Run PowerShell commands within the confines of the workflow to populate variables with information to pass back to the workflow. The PowerShell script contents are embedded within the step. This step does not call out to an external file. This provides a high level of security by greatly limiting the number of standard PowerShell cmdlets that can be executed by the workflow step. A small number of PowerShell cmdlets have been white listed to allow them to be included in workflow steps of this type, including:  • Where-Object  • ForEach-Object  • Get-Command  • CustomPowerShell  Run a PowerShell script. The script contents are in a file placed in the ExtensionLibrary\Workflow directory or a subdirectory of it on the Keyfactor Command server under the install directory for Keyfactor Command. By default, this is:  C:\Program Files\Keyfactor\Keyfactor Platform\ExtensionLibrary\Workflow		
		The file must have an extension of .ps1. A sample PowerShell script is provided in the Workflow directory (CustomPowershellExample.ps1).		
		RequireApproval  Require approval for a workflow step before the step can be completed. The		
		require approval step applies to certificate enrollments, renewals, and revocations and can require approval from just one approver or multiple approvers. The workflow will be suspended at this point until the correct number of approvals from users with the correct security roles is received or until one deny is received before continuing to the next step. As part of this step, an email message is sent indicating whether the step was approved or denied—typically to the requester. This step does not include logic to send an email initiating the approval process (letting users know something needs approval). Use an <i>Email</i> type step for this.		
		Important: Workflows are not supported with CA delegation when they contain steps that require approval. For more information, see		

### **Description** Name Name Description the CA configuration Authorization Methods Tab in the Keyfactor Command Reference Guide. Tip: The workflow builder does not include a step to send a notification to the requester of a certificate once the certificate is issued by the CA (as opposed to approved in Keyfactor Command). Use the issued alerts for this (see Issued Request Alert Operations in the Keyfactor Command Reference Guide). RESTRequest Run a REST (API) request. The REST request contents are embedded within the step. It does not call out to an external file. EnrollmentAgent On an enrollment (either CSR or PFX), create a resigned CSR to prepare an updated enrollment request for delivery to a Microsoft CA after a previous step in the workflow has been used to update either the SANs in the initial request, subject (DN) in the initial request or both. This step must be placed later in the workflow than the step(s) to modify the SANs and/or subject. The SANs and subject may be modified with either of the PowerShell step types or a custom step type. The step creates a new CSR using the same public key as the original CSR using the updated SAN and/or subject values. It signs the new CSR with the certificate provided in the step's configuration. For this type of step you will need an enrollment agent certificate available as a PKCS#12 (.PFX) file with included private key to import into Keyfactor Command. This can be a user certificate or a computer certificate (e.g. generated from a copy of the "Enrollment Agent" template or the "Enrollment Agent (Computer)" template) and must have a Certificate Request Agent EKU. Note that the built-in "Enrollment Agent" and "Enrollment Agent (Computer)" templates do not allow private keys to be exported by default. You will need a template that allows private key export or will need to manually override private key export to create a certificate with an exportable private key in order to create a PKCS#12 (.PFX) file. **Important:** This step applies to Microsoft CAs only. If this step is added to workflow for requests directed to an EJBCA CA, it will fail on enrollment. Note that EJBCA supports submission of updated SAN or subject details as part of standard functionality. EnrollStep

Name	Description			
	Name	Description		
		Enroll for a certificate through Keyfactor Command. The enroll step must always fall as the last step in the workflow, immediately following the EndNOOP step.  • NOOPStep  An entry or exit step in which no operation occurs. Steps of this type indicate the start and end of the workflow.  • RevokeStep  Revoke a certificate through Keyfactor Command. The revoke step must always fall as the last step in the workflow, immediately following the EndNOOP step.  Tip: For steps that send email messages, the SMTP settings and sender information come from the standard Keyfactor Command SMTP configuration (see SMTP on page 1081) and are not configured individually in the workflow steps.		
	Enabled	A Boolean indicating whether the step is enabled to run (true) or not (false).		
	Config- urationPara- meters	An array containing the configuration parameters for the workflow definition step. These will vary depending on the type of workflow and the type of step (see <i>ExtensionName</i> ).		
		Note: There are no ConfigurationParameters for steps of type EnrollStep, NOOPStep, or RevokeStep.		
		Possible CustomPowerS	hell parameters include:	
		Value	Description	
		ScriptParameters	An array of key/value pair strings defining any parameters to be used in the PowerShell script.	
		ScriptName	The path and filename for the script to execute. The script needs to be in the ExtensionLibrary\Workflow directory or a subdirectory of it on the Keyfactor Command server under the install directory. By default, this is:  C:\Program Files\Keyfactor\Keyfactor	

Name	Description				
	Name	Description	Description		
		Value	Description		
			Platform\ExtensionLibrary\Workflow The file must have an extension of .ps1. A sample PowerShell script is provided in the Workflow directory (CustomPowershellExample.ps1).		
		meter replace metace comm	Tokens (a.k.a. substitutable special text) may be used in the script parar value field. Tokens use a variable in the workflow definition that is ced by data from the certificate request, certificate, or certificate data at processing time. For example, you can take the revocation nent entered when the revocation request is approved—\$(cmnt)—and additional data to it using PowerShell.		
		Possible <b>Ema</b>	Possible <b>Email</b> parameters include:		
		Value	Description		
		Subject	A string indicating the subject line for the email message that will be delivered when the workflow definition step is executed.		
		Message	A string indicating the email message that will be delivered when the workflow definition step is executed. The email message is made up of regular text and tokens. If desired, you can format the message body using HTML. For example, for an enrollment pending request notification:		
			"Hello,\n\nA certificate using the \$(template) template was requested by \$(requester:displayname) from \$(CA) on \$(subdate). The certificate details include:\n\n\n Certificate Details Hello,\n\n\n CA) on \$(subdate). The certificate details include:\n\n\n Certificate Details Hello,\n CA) on \$(subdate). The certificate details include:\n\n Certificate Details Hello,\n CA) on \$(subdate). The certificate details include:\n\n CETIFICATION (STEP) (STEP		
			\$(request:dn)\$(metadata:Ap-pOwnerLast Name: \$(metadata:Ap-pOwnerLastName)\$(sans)\$(sans)\$(metadata:Ap-pOwnerEmail Address: \$(metadata:Ap-pOwnerEmail Address: \$(metadata:Ap-pOwn-		
			erEmailAddress)\n Business		

Name	Description				
	Name	Description			
		Value	Description		
			Critical: \$(metadata:BusinessCritical) \n\nPlease review this request and issue the certificate as appropriate by going here:\n\n\$(reviewlink)\n\nThanks!\n\nYour Certificate Management Tool\n"  See Table 1: Tokens for Workflow Definitions in the Keyfactor Command Reference Guide for a complete list of available tokens.		
		Recip- ients	An array of strings containing the recipients for the workflow definition email. Each email message can have multiple recipients. You can use specific email addresses and/or use tokens to replace an email address variable with actual email addresses at processing time. Available email tokens include:		
			\$(requester:mail)     The certificate requester, based on a lookup in Active     Directory of the email address associated with the     requester on the certificate.		
			<ul> <li>Your custom email-based metadata field, which would be specified similarly to \$(metadata:AppOwnerEmailAddress).</li> </ul>		
		messa defini certifi questo messa	Tokens (a.k.a. substitutable special text) may be used in the subject line, age and email recipient fields. Tokens use a variable in the workflow ition that is replaced by data from the certificate request, certificate, or icate metadata at processing time. For example, you can select \$(recer) in the workflow definition for an enrollment request and the email age will contain the specific certificate requester name instead of the ole \$(requester).		
		Possible PowerShell parameters include:			
		Value	Description		
		ScriptParam	An array of key/value pair strings defining any parameters to be used in the PowerShell script. The key is the name of a custom parameter defined by you and the value is the initial value that should be set for that parameter before the PowerShell is executed, if any.		

Name	Description						
	Name	Description	Description				
		Value	Description				
			Tokens are supported in the <i>value</i> .				
		ScriptContent	A string containing the PowerShell commands to execute. This should be the actual contents of the PowerShell script (the PowerShell commands and supporting components), not a path and filename to an external file.				
		Tip: Tokens (a.k.a. substitutable special text) may be used in the script parameter value field. Tokens use a variable in the workflow definition that is replaced by data from the certificate request, certificate, or certificate metadata at processing time. For example, you can take the revocation comment entered when the revocation request is approved—\$(cmnt)—and append additional data to it using PowerShell.					
		Possible <b>RequireApproval</b>	Possible RequireApproval parameters include:				
		Value	Description				
		MinimumApprovals	In integer indicating the minimum number of users who must approve the request to allow the request to complete.				
		DenialEmailSubject	A string indicating the subject line for the email message that will be delivered if the request is denied.				
		DenialEmailMessage	A string indicating the email message that will be delivered if the request is denied. The email message is made up of regular text and tokens. If desired, you can format the message body using HTML.  See Table: Tokens for Workflow Definitions in the Keyfactor Command Reference Guide for a complete list of available tokens.				

Name	Description						
	Name	Description	Description				
		Value	Description				
		DenialEmailRecipients	An array of strings containing the recipients for the denial email. Each email message can have multiple recipients. You can use specific email addresses and/or use tokens to replace an email address variable with actual email addresses at processing time. Available email tokens include:  • \$(requester:mail)  The certificate requester, based on a lookup in Active Directory of the email address associated with the requester on the certificate.  • Your custom email-based metadata field, which would be specified similarly to \$(metadata:AppOwnerEmailAddress).				
		ApprovalEmailSubject	A string indicating the subject line for the email message that will be delivered if the request is approved.				
		ApprovalEmailMessage	A string indicating the email message that will be delivered if the request is approved. The email message is made up of regular text and tokens. If desired, you can format the message body using HTML.  See <i>Table: Tokens for Workflow Definitions</i> in the <i>Keyfactor Command Reference Guide</i> for a complete list of available tokens.				
		ApprovalEmailRecipients	An array of strings containing the recipients for the approval email. Each email message can have multiple recipients. You can use specific email addresses and/or use tokens to replace an email address variable with actual email addresses at processing time. Available email tokens include:  • \$(requester:mail)  The certificate requester, based on a				

## **Description** Name Name Description Value Description lookup in Active Directory of the email address associated with the requester on the certificate. · Your custom email-based metadata field, which would be specified similarly to \$(metadata:AppOwnerEmailAddress). Tip: Tokens (a.k.a. substitutable special text) may be used in the subject line, message and email recipient fields. Tokens use a variable in the workflow definition that is replaced by data from the certificate request, certificate, or certificate metadata at processing time. For example, you can select \$(requester) in the workflow definition for an enrollment request and the email message will contain the specific certificate requester name instead of the variable \$(requester). Possible RestRequest parameters include: Value Description Headers An array of key/value pair strings containing the header information for the request. The key is the name of the specific request header (for Keyfactor API request headers, see Table 1: Common Request Headers and the specific documentation for each endpoint) and the value is the value that should be set for that header. For a Keyfactor API request, this might look like: "Headers": { "x-keyfactor-requested-with": [ "APIClient" "x-keyfactor-api-version": [ "2"

Name	Description		
	Name	Description	
		Value	Description
			Tip: For a Keyfactor API request, version 1 is assumed if no version is specified. Content type and authorization headers do not need to be specified, since those are addressed elsewhere in the configuration.
		DataBuck- etProperty	A string containing the variable that the response from the request will be returned in, if any. You can then reference this parameter from subsequent steps in the workflow.
			Tip: The response is stored as a serialized JObject. To make use of only a portion of the response data in your subsequent step, use JSON path syntax. For example, say you returned the data from a GET /Agents request in a variable called MyResponse and you wanted to reference the ClientMachine name for the orchestrator in a subsequent email message. To limit the data to the first result and only the ClientMachine name, in the email message you would enter the following:  \$(MyResponse.[0].ClientMachine)
		Verb	A string indicating the HTTP verb for the type of request to perform. Supported values are:  DELETE GET HEAD OPTIONS POST PUT TRACE
		UseBasicAu- th	A Boolean indicating whether Basic authentication should be used for the request (True) or not (False).  If <i>UseBasicAuth</i> is <i>False</i> , Windows authentication in the context of the Keyfactor Command application pool user will be used (see <i>Create Active Directory Service Accounts for Keyfactor</i>

Name	Description				
	Name	Description			
		Value	Description		
			Command in the Ke	ryfactor Command Server Installation Guide).	
		BasicUser- name	An array indicating tication if <i>UseBasica</i>	the username information to use for authen- Auth is True.	
			<ul> <li>Store the cree table.</li> <li>A Keyfactor so word that is exercised to Core.</li> <li>Load the cree See PAM Processing</li> </ul>	dential information in the Keyfactor secrets  ecret is a user-defined username or passencrypted and stored securely in the mmand database.  dential information from a PAM provider.  viders and Privileged Access Management  Keyfactor Command Reference Guide for ation.	
			Value	Description	
			SecretValue	A string containing the username defined for basic authentication (in DOMAIN\\username format).	
			Parameters	An array indicating the parameters to supply for PAM authentication. These will vary depending on the PAM provider.	
			Provider	A string indicating the ID of the PAM provider.  Use the GET /PamProviders method (see GET PAM Providers on page 724) to retrieve a list of all the PAM providers to determine the ID.	
			For example, the us like:	sername stored as a Keyfactor secret will look	

Name	Description		
	Name	Description	
		Value	Description
			<pre>{     "SecretValue": "KEYEXAMPLE\svc_MyServiceName" }</pre>
			The username stored as a CyberArk PAM secret will look like (where the Provider value—1 in this example—is the Id value from GET PAM Providers on page 724 and the Folder and Object reference the folder name and object name in the CyberArk safe):
			<pre>{     "Provider": "1",     "Parameters":{         "Folder":"MyFolderName",         "Object":"MyWorkflowUsername"     } }</pre>
			The username stored as a Delinea PAM secret will look like (where the Provider value—1 in this example—is the Id value from GET PAM Providers on page 724 and the SecretId is the ID if the secret created in the Delinea secret server for this purpose):
			<pre>{     "Provider": "1",     "Parameters":{         "SecretId":"MyUsernameId"     } }</pre>
			Due to its sensitive nature, this value is not returned in responses.
		BasicPass- word	An array indicating the password information to use for authentication if <i>UseBasicAuth</i> is <i>True</i> . The syntax is the same as for <i>BasicUsername</i> .  Due to its sensitive nature, this value is not returned in

Name	Description				
	Name	Description	Description		
		Value	Description		
			responses.		
		URL	A string containing the URL for the request, including tokens, if desired. For a Keyfactor API request, this might look like:  https://keyfactor.keyexample.com/KeyfactorAP I/Certificates?pq.queryString=CN%20- contains%20%22appsrvr14%22%20AND%20CertStore Path%20-ne%20NULL Or, with tokens: https://keyfactor.keyexample.com/KeyfactorAP I/Certificates/\$(certid)		
			Note: To prevent REST requests from being made to inappropriate locations by malicious users, configure a system environment variable of KEYFACTOR_BLOCKED_OUTBOUND_IPS on your Keyfactor Command server pointing to the IP address or range of addresses in CIDR format that you wish to block. Both IPv4 and IPv6 addresses are supported. More than one address or range may be specified in a comma-delimited list. For example:  192.168.12.0/24,192.168.14.22/24 When a REST request is made where the URL is either configured to a blocked IP address or resolves via DNS to a blocked IP address, the REST request will fail.		
		ContentTyp- e	A string indicating the content type for the request. Supported values are:  • application/json		
		RequestCon- tent	A string containing the body of the REST request, if needed. For a Keyfactor API request, this will vary depending on the request and might look like (for a PUT /Certificates/Metadata request):		
			{     "Id": "\$(certid)",		

# Description Name Name Description Value Description "Metadata":{ "RevocationComment": "\$(cmnt)" Note: This example assumes you have a metadata field called RevocationComment. Tip: Tokens (a.k.a. substitutable special text) may be used in the URL and request content fields. Tokens use a variable in the workflow definition that is replaced by data from the certificate request, certificate, or certificate metadata at processing time. For example, you can take the revocation comment entered when the revocation request is approved—\$(cmnt)—and insert it into a custom metadata field in the certificate by doing a PUT /Certificates/Metadata request for the \$(id). Signals An array of objects containing data used at the point in the workflow step where the workflow needs to continue based on user input. These will vary depending on the type of workflow and the type of step (see ExtensionName). Possible RequireApproval values are: Value **Description** RoleIds An array of integers indicating the security roles whose members are allowed to approve the request. SignalName A string indicating the name of the signal. This value will vary depending on the workflow step. For the built-in Require Approval step, the SignalName is "ApprovalStatus". Important: If all the security roles configured for a workflow step are deleted from Keyfactor Command, no users will be able to submit signals for workflow instances initiated with that workflow definition. To remedy this, update the workflow definition with one or more current security roles, republish it, and then restart any outstanding workflow instances.

Name	Description			
	Name	Description		
	Conditions	An object containing conditions indicating whether the step should run (true) or not (false). Conditions may either have a static value of True or False or a token that will have a value of True or False at the time the step is run. More than one condition may be added. If multiple conditions are used in the same step, all conditions must have a value of True at the time the step is evaluated to be run in order for the step to run. If any single condition evaluates to False, the step will not run. Condition values are:		
		Value	Description	
		Id	A string indicating the Keyfactor Command reference ID of the condition.	
		Value	A string indicating the value of the condition. This should be one of "true", "false", or a token that will be set to either "true" or "false" in an earlier step in the workflow (see Workflow Definition Operations: Adding or Modifying a Workflow Definition in the Keyfactor Command Reference Guide for an example).	
	Outputs	An array indicating the next step in the workflow. Possible values are:		
		Value	Description	
		continue	A string indicating the <i>UniqueName</i> of the next workflow step in the chain. This value will be null for the final step in the chain.	
DraftVer- sion	An integer indicating the version number of the workflow definition. If this version number does not match the <i>PublishedVersion</i> , changes have been made to the workflow definition that have not yet been published.			
Published- Version	An integer indicating the currently published version number of the workflow definition. For a newly created workflow, this value will be null.			

#### 2.2.31.5 GET Workflow Definitions

The GET /Workflow/Definitions method is used to retrieve the list of workflow definitions. This method returns HTTP 200 OK on a success with high level information about the workflow definitions. Use the GET /Workflow/Definitions/{definitionid} method (see GET Workflow Definitions Definition ID on page 1238) to return details including the workflow steps.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: WorkflowDefinitions: *Read* 

Table 580: GET Workflow Definitions Input Parameters

Name	In	Description
queryString	Query	A string containing a query to limit the results (e.g. field1 -eq value1 AND field2 -gt value2). The default is to return all records. Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns for the same feature. For querying guidelines, refer to the Keyfactor Command Reference Guide: Using the Workflow Definitions Search Feature. The query fields supported for this endpoint are:  • DisplayName  • Id  • IsPublished (true or false)  • WorkflowType (Enrollment or Revocation)
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>DisplayName</i> .
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.

Table 581: GET Workflow Definitions Response Data

Name	Description
Id	A string indicating the Keyfactor Command reference GUID of the workflow definition.
DisplayName	A string indicating the display name defined for the workflow definition.
Key	A string indicating the reference key for the workflow definition. The type of information contained in this field will vary depending on the <i>WorkflowType</i> . If the <i>WorkflowType</i> is <i>Enrollment</i> or <i>Revocation</i> , this field will contain the Keyfactor Command reference ID for the certificate template.
KeyDisplayName	A string indicating the friendly name defined in Keyfactor Command for the certificate template.
WorkflowType	A string indicating the type of workflow definition. The currently supported types are:  • Enrollment • Revocation
DraftVersion	An integer indicating the version number of the workflow definition. If this version number does not match the <i>PublishedVersion</i> , changes have been made to the workflow definition that have not yet been published.
PublishedVersion	An integer indicating the currently published version number of the workflow definition.

#### 2.2.31.6 POST Workflow Definitions

The POST /Workflow/Definitions method is used to create a new workflow definition without any steps. To add steps to the workflow, use the PUT /Workflow/Definitions/{definitionId}/Steps method (see <u>PUT Workflow Definitions Definition ID Steps on page 1291</u>). This method returns HTTP 200 OK on a success with details about the workflow definition.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: WorkflowDefinitions: *Modify* 



**Note:** Only one workflow definition can be created for each combination of **Workflow Type** and **Key** (**Template**). In other words, you cannot have two enrollment or revocation workflow definitions for the same template, though you can have one enrollment workflow definition and one revocation workflow definition for a given template.

Table 582: POST Workflow Definitions Input Parameters

Name	In	Description
DisplayName	Body	Required. A string indicating the display name defined for the workflow definition.
Description	Body	A string indicating the description for the workflow definition.
Key	Body	Required. A string indicating the reference key for the workflow definition. The type of information contained in this field will vary depending on the <i>WorkflowType</i> . If the <i>WorkflowType</i> is <i>Enrollment</i> or <i>Revocation</i> , this field will contain the Keyfactor Command reference ID for the certificate template.  Use the GET /Templates method (see GET Templates on page 1185) to retrieve a list or your certificate templates to determine the template ID.  This field cannot be modified on an edit.
KeyDisplayName	Body	A string indicating the friendly name defined in Keyfactor Command for the certificate template.
WorkflowType	Body	Required. A string indicating the type of workflow definition. The currently supported types are:  • Enrollment • Revocation This field cannot be modified on an edit.

Table 583: POST Workflow Definitions Response Body

Name	Description		
Id	A string indicating the Keyfactor Command reference GUID of the workflow definition.		
DisplayNa- me	A string indicating the display name defined for the workflow definition.		
Descrip- tion	A string indicating the description for the workflow definition.		
Key	A string indicating the reference key for the workflow definition. The type of information contained in this field will vary depending on the <i>WorkflowType</i> . If the <i>WorkflowType</i> is <i>Enrollment</i> or <i>Revocation</i> , this field will contain the Keyfactor Command reference ID for the certificate template.		
KeyDis- playName	A string indicating the friendly name defined in Keyfactor Command for the certificate template.		
IsPub- lished	A Boolean indicating whether the workflow definition has been published (true) or not (false). A workflow definition must be published to activate it. For a newly created workflow, this will be <i>false</i> .		
Work- flowType	A string indicating the type of workflow definition. The currently supported types are:  • Enrollment • Revocation		
Steps	An array of objects indicating the steps in the workflow definition. The contents of each step will vary depending on the type of workflow and the type of step. For a newly created workflow, there will be no data in this value. Possible steps include:		
	Name	Description	
	Id	A string indicating the Keyfactor Command reference GUID of the workflow definition step.	
	DisplayName	A string indicating the display name for the step.	
	UniqueName	A string indicating the unique name for the step. This value must be unique among the steps in the particular workflow definition. It is intended to be used as a user-friendly reference ID.	
	Exten- sionName	A string indicating the type of step. The currently supported types are:  • Email	

Name	Description		
	Name	Description	
		Send an email message. This is a separate email message from those typically sent as part of a <i>Require Approval</i> step. You might send an email message as part of an enrollment request to notify approvers that a new request needs approval. The email messages can be customized to provide detailed information about, for example, the certificate request.  • PowerShell  Run PowerShell commands within the confines of the workflow to populate variables with information to pass back to the workflow. The PowerShell script contents are embedded within the step. This step does not call out to an external file. This provides a high level of security by greatly limiting the number of standard PowerShell cmdlets that can be executed by the workflow step. A small number of PowerShell cmdlets have been white listed to allow them to be included in workflow steps of this type, including:  • Where-Object  • ForEach-Object  • Get-Command  • CustomPowerShell  Run a PowerShell script. The script contents are in a file placed in the ExtensionLibrary\Workflow directory or a subdirectory of it on the Keyfactor Command server under the install directory for Keyfactor Command. By default, this is:  C:\Program Files\Keyfactor\Keyfactor Platform\ExtensionLibrary\Workflow  The file must have an extension of .ps1. A sample PowerShell script is	
		provided in the Workflow directory (CustomPowershellExample.ps1).  • RequireApproval	
		Require approval for a workflow step before the step can be completed. The require approval step applies to certificate enrollments, renewals, and revocations and can require approval from just one approver or multiple approvers. The workflow will be suspended at this point until the correct number of approvals from users with the correct security roles is received or until one deny is received before continuing to the next step. As part of this step, an email message is sent indicating whether the step was approved or denied—typically to the requester. This step does not include logic to send an email initiating the approval process (letting users know something needs approval). Use an <i>Email</i> type step for this.	
		Important: Workflows are not supported with CA delegation when they contain steps that require approval. For more information, see	

Name	Description	
	Name	Description
		the CA configuration Authorization Methods Tab in the Keyfactor Command Reference Guide.
		Tip: The workflow builder does not include a step to send a notification to the requester of a certificate once the certificate is issued by the CA (as opposed to approved in Keyfactor Command). Use the issued alerts for this (see <i>Issued Request Alert Operations</i> in the <i>Keyfactor Command Reference Guide</i> ).
		RESTRequest
		Run a REST (API) request. The REST request contents are embedded within the step. It does not call out to an external file.
		EnrollmentAgent
		On an enrollment (either CSR or PFX), create a resigned CSR to prepare an updated enrollment request for delivery to a Microsoft CA after a previous step in the workflow has been used to update either the SANs in the initial request, subject (DN) in the initial request or both. This step must be placed later in the workflow than the step(s) to modify the SANs and/or subject. The SANs and subject may be modified with either of the PowerShell step types or a custom step type. The step creates a new CSR using the same public key as the original CSR using the updated SAN and/or subject values. It signs the new CSR with the certificate provided in the step's configuration.
		For this type of step you will need an enrollment agent certificate available as a PKCS#12 (.PFX) file with included private key to import into Keyfactor Command. This can be a user certificate or a computer certificate (e.g. generated from a copy of the "Enrollment Agent" template or the "Enrollment Agent (Computer)" template) and must have a Certificate Request Agent EKU. Note that the built-in "Enrollment Agent" and "Enrollment Agent (Computer)" templates do not allow private keys to be exported by default. You will need a template that allows private key export or will need to manually override private key export to create a certificate with an exportable private key in order to create a PKCS#12 (.PFX) file.
		Important: This step applies to Microsoft CAs only. If this step is added to workflow for requests directed to an EJBCA CA, it will fail on enrollment. Note that EJBCA supports submission of updated SAN or subject details as part of standard functionality.
		EnrollStep

Name	Description				
	Name	Description			
		Enroll for a certificate through Keyfactor Command. The enroll step always fall as the last step in the workflow, immediately following the EndNOOP step.  • NOOPStep  An entry or exit step in which no operation occurs. Steps of this type the start and end of the workflow.  • RevokeStep  Revoke a certificate through Keyfactor Command. The revoke step realways fall as the last step in the workflow, immediately following the EndNOOP step.  Tip: For steps that send email messages, the SMTP settings and see information come from the standard Keyfactor Command SMTP configuration (see SMTP on page 1081) and are not configuration.			
	Enabled	vidually in the workflow steps.  A Boolean indicating whether the step is enabled to run (true) or not (false).			
	Config- urationPara- meters	An array containing the configuration parameters for the workflow definition step.  These will vary depending on the type of workflow and the type of step (see ExtensionName).			
		Note: There are no ConfigurationParameters for steps of type Enrol NOOPStep, or RevokeStep.			
		Possible CustomPowerSh	nell parameters include:		
		Value	Description		
		ScriptParameters	An array of key/value pair strings defining any parameters to be used in the PowerShell script.		
		ScriptName	The path and filename for the script to execute. The script needs to be in the ExtensionLibrary\Workflow directory or a subdirectory of it on the Keyfactor Command server under the install directory. By default, this is:  C:\Program Files\Keyfactor\Keyfactor		

Name	Description				
	Name	Description	Description		
		Value	Description		
			Platform\ExtensionLibrary\Workflow The file must have an extension of .ps1. A sample PowerShell script is provided in the Workflow directory (CustomPowershellExample.ps1).		
		meter replace metace comm	Tokens (a.k.a. substitutable special text) may be used in the script parar value field. Tokens use a variable in the workflow definition that is ced by data from the certificate request, certificate, or certificate data at processing time. For example, you can take the revocation nent entered when the revocation request is approved—\$(cmnt)—and additional data to it using PowerShell.		
		Possible <b>Ema</b>	Possible <b>Email</b> parameters include:		
		Value	Description		
		Subject	A string indicating the subject line for the email message that will be delivered when the workflow definition step is executed.		
		Message	A string indicating the email message that will be delivered when the workflow definition step is executed. The email message is made up of regular text and tokens. If desired, you can format the message body using HTML. For example, for an enrollment pending request notification:		
			"Hello,\n\nA certificate using the \$(template) template was requested by \$(requester:displayname) from \$(CA) on \$(subdate). The certificate details include:\n\n\n Certificate Details Hello,\n\n\n CA) on \$(subdate). The certificate details include:\n\n\n Certificate Details Hello,\n CA) on \$(subdate). The certificate details include:\n\n Certificate Details Hello,\n CA) on \$(subdate). The certificate details include:\n\n CETIFICATION (STEP) (STEP		
			\$(request:dn)\$(metadata:Ap-pOwnerLast Name: \$(metadata:Ap-pOwnerLastName)\$(sans)\$(sans)\$(metadata:Ap-pOwnerEmail Address: \$(metadata:Ap-pOwnerEmail Address: \$(metadata:Ap-pOwn-		
			erEmailAddress)\n Business		

Name	Description	cription			
	Name	Description			
		Value	Description		
			Critical: \$(metadata:BusinessCritical)\n\nPlease review this request and issue the certificate as appropriate by going here:\n\n\$(reviewlink)\n\nThanks!\n\nYour Certificate Management Tool\n"  See Table 1: Tokens for Workflow Definitions in the Keyfactor Command Reference Guide for a complete list of available tokens.		
		Recip- ients	An array of strings containing the recipients for the workflow definition email. Each email message can have multiple recipients. You can use specific email addresses and/or use tokens to replace an email address variable with actual email addresses at processing time. Available email tokens include:		
			\$(requester:mail)     The certificate requester, based on a lookup in Active     Directory of the email address associated with the     requester on the certificate.		
			<ul> <li>Your custom email-based metadata field, which would be specified similarly to \$(metadata:AppOwnerEmailAddress).</li> </ul>		
		messa defini certifi quest messa	Tokens (a.k.a. substitutable special text) may be used in the subject line, age and email recipient fields. Tokens use a variable in the workflow ition that is replaced by data from the certificate request, certificate, or icate metadata at processing time. For example, you can select \$(rever) in the workflow definition for an enrollment request and the email age will contain the specific certificate requester name instead of the ole \$(requester).		
		Possible PowerShell parameters include:			
		Value	Description		
		ScriptParam	An array of key/value pair strings defining any parameters to be used in the PowerShell script. The key is the name of a custom parameter defined by you and the value is the initial value that should be set for that parameter before the PowerShell is executed, if any.		

Name	Description					
	Name	Description				
		Value	Description			
			Tokens are supported in the <i>value</i> .			
		ScriptContent	A string containing the PowerShell commands to execute. This should be the actual contents of the PowerShell script (the PowerShell commands and supporting components), not a path and filename to an external file.			
		Tip: Tokens (a.k.a. substitutable special text) may be used in the script parameter value field. Tokens use a variable in the workflow definition that is replaced by data from the certificate request, certificate, or certificate metadata at processing time. For example, you can take the revocation comment entered when the revocation request is approved—\$(cmnt)—and append additional data to it using PowerShell.				
		Possible <b>RequireApproval</b> parameters include:				
		Value	Description			
		MinimumApprovals	In integer indicating the minimum number of users who must approve the request to allow the request to complete.			
		DenialEmailSubject	A string indicating the subject line for the email message that will be delivered if the request is denied.			
		DenialEmailMessage	A string indicating the email message that will be delivered if the request is denied. The email message is made up of regular text and tokens. If desired, you can format the message body using HTML.  See Table: Tokens for Workflow Definitions in the Keyfactor Command Reference Guide for a complete list of available tokens.			

Name	Description						
	Name	Description	Description				
		Value	Description				
		DenialEmailRecipients	An array of strings containing the recipients for the denial email. Each email message can have multiple recipients. You can use specific email addresses and/or use tokens to replace an email address variable with actual email addresses at processing time. Available email tokens include:  • \$(requester:mail)  The certificate requester, based on a lookup in Active Directory of the email address associated with the requester on the certificate.  • Your custom email-based metadata field, which would be specified similarly to \$(metadata:AppOwnerEmailAddress).				
		ApprovalEmailSubject	A string indicating the subject line for the email message that will be delivered if the request is approved.				
		ApprovalEmailMessage	A string indicating the email message that will be delivered if the request is approved. The email message is made up of regular text and tokens. If desired, you can format the message body using HTML.  See <i>Table: Tokens for Workflow Definitions</i> in the <i>Keyfactor Command Reference Guide</i> for a complete list of available tokens.				
		ApprovalEmailRecipients	An array of strings containing the recipients for the approval email. Each email message can have multiple recipients. You can use specific email addresses and/or use tokens to replace an email address variable with actual email addresses at processing time. Available email tokens include:  • \$(requester:mail)  The certificate requester, based on a				

Name	Description			
	Name	Description		
		Value	Description	
			lookup in Active Directory of the email address associated with the requester on the certificate.  • Your custom email-based metadata field, which would be specified similarly to \$(metadata:AppOwnerEmailAddress).	
		message definitio certifica quester) message	kens (a.k.a. substitutable special text) may be used in the subject line, and email recipient fields. Tokens use a variable in the workflow on that is replaced by data from the certificate request, certificate, or the metadata at processing time. For example, you can select \$(re-1) in the workflow definition for an enrollment request and the email will contain the specific certificate requester name instead of the \$(requester).	
		Possible <b>RestRe</b>	equest parameters include:	
		Value	Description	
		Headers	An array of key/value pair strings containing the header information for the request. The key is the name of the specific request header (for Keyfactor API request headers, see <a href="Table 1: Common Request Headers">Table 1: Common Request Headers</a> and the specific documentation for each endpoint) and the value is the value that should be set for that header. For a Keyfactor API request, this might look like:	
			<pre>"Headers": {     "x-keyfactor-requested-with": [         "APIClient" ],     "x-keyfactor-api-version": [         "2" ] }</pre>	

Name	Description		
	Name	Description	
		Value	Description
			Tip: For a Keyfactor API request, version 1 is assumed if no version is specified. Content type and authorization headers do not need to be specified, since those are addressed elsewhere in the configuration.
		DataBuck- etProperty	A string containing the variable that the response from the request will be returned in, if any. You can then reference this parameter from subsequent steps in the workflow.
			Tip: The response is stored as a serialized JObject. To make use of only a portion of the response data in your subsequent step, use JSON path syntax. For example, say you returned the data from a GET /Agents request in a variable called MyResponse and you wanted to reference the ClientMachine name for the orchestrator in a subsequent email message. To limit the data to the first result and only the ClientMachine name, in the email message you would enter the following:  \$(MyResponse.[0].ClientMachine)
		Verb	A string indicating the HTTP verb for the type of request to perform. Supported values are:  DELETE GET HEAD OPTIONS POST PUT TRACE
		UseBasicAu- th	A Boolean indicating whether Basic authentication should be used for the request (True) or not (False).  If <i>UseBasicAuth</i> is <i>False</i> , Windows authentication in the context of the Keyfactor Command application pool user will be used (see <i>Create Active Directory Service Accounts for Keyfactor</i>

Name	Description			
	Name	Description		
		Value	Description	
			Command in the Ke	yfactor Command Server Installation Guide).
		BasicUser- name	Supported methods  Store the creditable.  A Keyfactor so word that is exercised to be creditable.  Load the creditable creditable.  Load the creditable creditable.  See PAM Province (PAM) in the more information.	dential information in the Keyfactor secrets  derect is a user-defined username or passencrypted and stored securely in the mmand database.  dential information from a PAM provider.  widers and Privileged Access Management Keyfactor Command Reference Guide for ation.  Description
			SecretValue	A string containing the username defined for basic authentication (in DOMAIN\\username format).
			Parameters	An array indicating the parameters to supply for PAM authentication. These will vary depending on the PAM provider.
			Provider	A string indicating the ID of the PAM provider.  Use the GET /PamProviders method (see GET PAM Providers on page 724) to retrieve a list of all the PAM providers to determine the ID.
			For example, the us	sername stored as a Keyfactor secret will look

Name	Description		
	Name	Description	
		Value	Description
			<pre>{     "SecretValue": "KEYEXAMPLE\svc_MyServiceName" }</pre>
			The username stored as a CyberArk PAM secret will look like (where the Provider value—1 in this example—is the Id value from GET PAM Providers on page 724 and the Folder and Object reference the folder name and object name in the CyberArk safe):
			<pre>{     "Provider": "1",     "Parameters":{         "Folder":"MyFolderName",         "Object":"MyWorkflowUsername"     } }</pre>
			The username stored as a Delinea PAM secret will look like (where the Provider value—1 in this example—is the Id value from GET PAM Providers on page 724 and the SecretId is the ID if the secret created in the Delinea secret server for this purpose):
			<pre>{     "Provider": "1",     "Parameters":{         "SecretId":"MyUsernameId"     } }</pre>
			Due to its sensitive nature, this value is not returned in responses.
		BasicPass- word	An array indicating the password information to use for authentication if <i>UseBasicAuth</i> is <i>True</i> . The syntax is the same as for <i>BasicUsername</i> .  Due to its sensitive nature, this value is not returned in

Name	Description			
	Name	Description		
		Value	Description	
			responses.	
		URL	A string containing the URL for the request, including tokens, if desired. For a Keyfactor API request, this might look like:  https://keyfactor.keyexample.com/KeyfactorAP I/Certificates?pq.queryString=CN%20- contains%20%22appsrvr14%22%20AND%20CertStore Path%20-ne%20NULL Or, with tokens: https://keyfactor.keyexample.com/KeyfactorAP I/Certificates/\$(certid)	
			Note: To prevent REST requests from being made to inappropriate locations by malicious users, configure a system environment variable of KEYFACTOR_BLOCKED_OUTBOUND_IPS on your Keyfactor Command server pointing to the IP address or range of addresses in CIDR format that you wish to block. Both IPv4 and IPv6 addresses are supported. More than one address or range may be specified in a comma-delimited list. For example:  192.168.12.0/24,192.168.14.22/24 When a REST request is made where the URL is either configured to a blocked IP address or resolves via DNS to a blocked IP address, the REST request will fail.	
		ContentTyp- e	A string indicating the content type for the request. Supported values are:  • application/json	
		RequestCon- tent	A string containing the body of the REST request, if needed. For a Keyfactor API request, this will vary depending on the request and might look like (for a PUT /Certificates/Metadata request):	
			{     "Id": "\$(certid)",	

## Description Name Name Description Value Description "Metadata":{ "RevocationComment": "\$(cmnt)" Note: This example assumes you have a metadata field called RevocationComment. Tip: Tokens (a.k.a. substitutable special text) may be used in the URL and request content fields. Tokens use a variable in the workflow definition that is replaced by data from the certificate request, certificate, or certificate metadata at processing time. For example, you can take the revocation comment entered when the revocation request is approved—\$(cmnt)—and insert it into a custom metadata field in the certificate by doing a PUT /Certificates/Metadata request for the \$(id). Signals An array of objects containing data used at the point in the workflow step where the workflow needs to continue based on user input. These will vary depending on the type of workflow and the type of step (see ExtensionName). Possible RequireApproval values are: Value **Description** RoleIds An array of integers indicating the security roles whose members are allowed to approve the request. SignalName A string indicating the name of the signal. This value will vary depending on the workflow step. For the built-in Require Approval step, the SignalName is "ApprovalStatus". Important: If all the security roles configured for a workflow step are deleted from Keyfactor Command, no users will be able to submit signals for workflow instances initiated with that workflow definition. To remedy this, update the workflow definition with one or more current security roles, republish it, and then restart any outstanding workflow instances.

Name	Description		
	Name	Description	
	Conditions	An object containing conditions indicating whether the step should run (true) or not (false). Conditions may either have a static value of True or False or a token that will have a value of True or False at the time the step is run. More than one condition may be added. If multiple conditions are used in the same step, all conditions must have a value of True at the time the step is evaluated to be run in order for the step to run. If any single condition evaluates to False, the step will not run. Condition values are:	
		Value	Description
		Id	A string indicating the Keyfactor Command reference ID of the condition.
		Value	A string indicating the value of the condition. This should be one of "true", "false", or a token that will be set to either "true" or "false" in an earlier step in the workflow (see Workflow Definition Operations: Adding or Modifying a Workflow Definition in the Keyfactor Command Reference Guide for an example).
	Outputs	An array indicating the next step in the workflow. Possible values are:	
		Value	Description
		continue	A string indicating the <i>UniqueName</i> of the next workflow step in the chain. This value will be null for the final step in the chain.
DraftVer- sion	An integer indicating the version number of the workflow definition. If this version number does not match the <i>PublishedVersion</i> , changes have been made to the workflow definition that have not yet been published.		
Published- Version	An integer indicating the currently published version number of the workflow definition. For a newly created workflow, this value will be null.		

## 2.2.31.7 GET Workflow Definitions Steps

The GET /Workflow/Definitions/Steps method is used to retrieve the workflow definition step structure for the workflow definition steps. This method returns HTTP 200 OK on a success with information about the structure of the workflow definition steps.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: WorkflowDefinitions: *Read* 

Table 584: GET Workflow Definitions Steps Input Parameters

Name	In	Description	
queryString	Query	A string containing a query to limit the results (e.g. field1 -eq value1 AND field2 -gt value2). The default is to return all records. Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns for the same feature. For querying guidelines, refer to the Keyfactor Command Reference Guide: Using the Workflow Definitions Search Feature. The query fields supported for this endpoint are DisplayName, ExtensionName, and SupportedWorkflowTypes.	
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.	
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.	
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>DisplayName</i> .	
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.	

Table 585: GET Workflow Definitions Steps Response Data

Name	Description
DisplayName	A string indicating the display name of the workflow definition step.
ExtensionName	A string indicating the extension name of the workflow definition step. The built-in extension names are:  • Email—Send an email message. This is a separate email message from those typically sent as part of a RequireApproval step.  • EnrollStep—Enroll for a certificate through Keyfactor Command.  • NOOPStep—An entry or exit step in which no operation occurs. Steps of this type indicate the start and end of the workflow.  • PowerShell—Run a PowerShell script. The script contents are embedded within the step. It does not call out to an external file.  • RequireApproval—Require approval for a workflow step before the step can be completed. This step includes logic to gather the correct number of approvals from the users with the correct security roles and to send an email message indicating whether the step was approved or denied. This step does not include logic to send an email initiating the approval process. Use an Email type for this.  Important: Workflows are not supported with CA delegation when they contain steps that require approval. For more information, see the CA configuration Authorization Methods Tab in the Keyfactor Command Reference Guide.  • RestRequest—Run a REST request. The REST request contents are embedded within the step. It does not call out to an external file.  • RevokeStep—Revoke a certificate through Keyfactor Command.
SupportedWorkflowTypes	An array containing a list of the workflow types supported by the workflow definition step. Possible built-in values are:  • Enrollment • Revocation
ConfigurationParametersDefinition	An object containing the configuration parameters for the workflow definition step. These will vary depending on the step.
SignalsDefinition	An object containing the signals defined for the workflow definition step. These will vary depending on the step.

# 2.2.31.8 GET Workflow Definitions Types

The GET /Workflow/Definitions/Types method is used to retrieve the workflow definition types that have been defined for use. This method returns HTTP 200 OK on a success with information about the defined workflow

#### definition types.



 $\begin{tabular}{ll} \textbf{Tip:} & \textbf{The following permissions (see } \underline{\textbf{Security Overview}}) \textbf{ are required to use this feature:} \\ \textbf{WorkflowDefinitions: } \textit{Read} \\ \end{tabular}$ 

Table 586: GET Workflow Definitions Types Input Parameters

Name	In	Description	
queryString	Query	A string containing a query to limit the results (e.g. field1 -eq value1 AND field2 -gt value2). The default is to return all records. Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns for the same feature. For querying guidelines, refer to the Keyfactor Command Reference Guide: Using the Workflow Definitions Search Feature. The query field supported for this endpoint is Name.	
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.	
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.	
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>WorkflowType</i> .	
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.	

Table 587: GET Workflow Definitions Types Response Data

Name	Description		
WorkflowType	A string indicating the display name of the workflow type.		
КеуТуре	A string indicating the key type for the worl flows use <i>Templates</i> as the key type.	oflow. The built-in enrollment and revocation work-	
ContextParameters	An object containing the tokens that the wo These will vary depending on the workflow	orkflow type provider has the ability to replace. type.	
BuiltInSteps	An object containing the information about enrollment step of the enrollment type). Pe	the built-in step(s) for the workflow type (e.g. the ossible steps include:	
	Name	Description	
	DisplayName	A string indicating the display name for the step.	
	ExtensionName	A string indicating the extension name for the step. The built-in extensions are:  • EnrollStep  • RevokeStep	
	Outputs	An array containing the outputs for the work- flow definition step. For the built-in steps, the only output is an indicator for the next step in the workflow or that the workflow is complete.	
	ConfigurationParametersDefinition	An array containing the configuration parameters for the workflow definition step. These will vary depending on the step.	
	SignalsDefinition	An array containing the signals defined for the workflow definition step. These will vary depending on the step.	

#### 2.2.31.9 PUT Workflow Definitions Definition ID Steps

The PUT /Workflow/Definitions/{definitionid}/Steps method is used to add or update the workflow steps for the workflow definition with the specified GUID. This method returns HTTP 200 OK on a success with details about the updated workflow definition.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: WorkflowDefinitions: *Modify* 



**Note:** If you edit an existing *published* workflow definition, a new version of the workflow definition will be created. If you edit an existing workflow definition which has *never been published*, the existing configuration will be overwritten with the changes you've made—a new version will not be created.



Warning: Any previously populated fields that are not submitted with their full existing data using this method will be cleared of their existing data. When using this method, you should first do a GET to retrieve all the values for the record you want to update, enter corrected data into the field(s) you want to update, and then submit all the fields using PUT, including the fields that contain values but which you are not changing.

Table 588: PUT Workflow Definitions {definitionid} Steps Input Parameters

Nam- e	In	Description
defin- itionId	Pa- th	Required. A string indicating the Keyfactor Command reference GUID of the workflow definition to update.  Use the GET /Workflow/Definitions method (see GET Workflow Definitions on page 1269) to retrieve a list of all the workflow definitions to determine the GUID.

Nam- e	In	Description			
reque- Bo-					
St	dy	Name	Description		
		DisplayName	A string indicating the display name for the step.		
		UniqueName	A string indicating the unique name for the step. This value must be unique among the steps in the particular workflow definition. It is intended to be used as a user-friendly reference ID.		
		ExtensionName	A string indicating the type of step. The currently supported types are:  • Email  Send an email message. This is a separate email message from those typically sent as part of a Require Approval step. You might send an email message as part of an enrollment request to notify approvers that a new request needs approval. The email messages can be customized to provide detailed information about, for example, the certificate request.  • PowerShell  Run PowerShell commands within the confines of the workflow to populate variables with information to pass back to the workflow. The Power-Shell script contents are embedded within the step. This step does not call out to an external file. This provides a high level of security by greatly limiting the number of standard PowerShell cmdlets that can be executed by the workflow step. A small number of PowerShell cmdlets have been white listed to allow them to be included in workflow steps of this type, including:  • Where-Object  • ForEach-Object  • Get-Command  • CustomPowerShell  Run a PowerShell script. The script contents are in a file placed in the ExtensionLibrary\Workflow directory or a subdirectory of it on the Keyfactor Command server under the install directory for Keyfactor Command. By default, this is:  C:\Program Files\Keyfactor\Keyfactor Platform\ExtensionLibrary\Workflow  The file must have an extension of .ps1. A sample PowerShell script is provided in the Workflow directory (CustomPowershellExample.ps1).  • RequireApproval  Require approval for a workflow step before the step can be completed. The require approval step applies to certificate enrollments, renewals, and		
			revocations and can require approval from just one approver or multiple approvers. The workflow will be suspended at this point until the correct number of approvals from users with the correct security roles is received or until one deny is received before continuing to the next step. As part of		
KEŤFAC	CTOR		this step, an email message is sent indicating whether the step was 10.1 Keyfartore Web denie Befeyarcal Ptiothe requester. This step does not include 1294 logic to send an email initiating the approval process (letting users know something needs approval). Use an Email type step for this.		
			Important: Workflows are not supported with CA delegation		

Table 589: PUT Workflow Definitions {definitionid} Steps Response Body

Name	Description				
Id	A string indicating the Keyfactor Command reference GUID of the workflow definition.				
DisplayNa- me	A string indicating	the display name defined for the workflow definition.			
Descrip- tion	A string indicating	the description for the workflow definition.			
Key	field will vary depe	the reference key for the workflow definition. The type of information contained in this nding on the <i>WorkflowType</i> . If the <i>WorkflowType</i> is <i>Enrollment</i> or <i>Revocation</i> , this field yfactor Command reference ID for the certificate template.			
KeyDis- playName	A string indicating	the friendly name defined in Keyfactor Command for the certificate template.			
IsPub- lished	A Boolean indicating whether the workflow definition has been published (true) or not (false). A workflow definition must be published to activate it. For a newly created workflow, this will be <i>false</i> .				
Work- flowType	A string indicating the type of workflow definition. The currently supported types are:  • Enrollment • Revocation				
Steps	An array of objects indicating the steps in the workflow definition. The contents of each step will va depending on the type of workflow and the type of step. For a newly created workflow, there will be in this value. Possible steps include:				
	Name	Description			
	Id A string indicating the Keyfactor Command reference GUID of the workflow definition step.				
	DisplayName A string indicating the display name for the step.				
	UniqueName A string indicating the unique name for the step. This value must be un the steps in the particular workflow definition. It is intended to be use friendly reference ID.				
	Exten- sionName				

Name	Description			
	Name	Description		
		Send an email message. This is a separate email message from those typically sent as part of a <i>Require Approval</i> step. You might send an email message as part of an enrollment request to notify approvers that a new request needs approval. The email messages can be customized to provide detailed information about, for example, the certificate request.  • PowerShell  Run PowerShell commands within the confines of the workflow to populate variables with information to pass back to the workflow. The PowerShell script contents are embedded within the step. This step does not call out to an external file. This provides a high level of security by greatly limiting the number of standard PowerShell cmdlets that can be executed by the workflow step. A small number of PowerShell cmdlets have been white listed to allow them to be included in workflow steps of this type, including:  • Where-Object  • ForEach-Object  • Get-Command  • CustomPowerShell  Run a PowerShell script. The script contents are in a file placed in the ExtensionLibrary\Workflow directory or a subdirectory of it on the Keyfactor Command server under the install directory for Keyfactor Command. By default, this is:  C:\Program Files\Keyfactor\Keyfactor Platform\ExtensionLibrary\Workflow		
		The file must have an extension of .ps1. A sample PowerShell script is provided in the Workflow directory (CustomPowershellExample.ps1).		
		RequireApproval  Require approval for a workflow step before the step can be completed. The		
		require approval step applies to certificate enrollments, renewals, and revocations and can require approval from just one approver or multiple approvers. The workflow will be suspended at this point until the correct number of approvals from users with the correct security roles is received or until one deny is received before continuing to the next step. As part of this step, an email message is sent indicating whether the step was approved or denied—typically to the requester. This step does not include logic to send an email initiating the approval process (letting users know something needs approval). Use an <i>Email</i> type step for this.		
		Important: Workflows are not supported with CA delegation when they contain steps that require approval. For more information, see		

### **Description** Name Name Description the CA configuration Authorization Methods Tab in the Keyfactor Command Reference Guide. Tip: The workflow builder does not include a step to send a notification to the requester of a certificate once the certificate is issued by the CA (as opposed to approved in Keyfactor Command). Use the issued alerts for this (see Issued Request Alert Operations in the Keyfactor Command Reference Guide). RESTRequest Run a REST (API) request. The REST request contents are embedded within the step. It does not call out to an external file. EnrollmentAgent On an enrollment (either CSR or PFX), create a resigned CSR to prepare an updated enrollment request for delivery to a Microsoft CA after a previous step in the workflow has been used to update either the SANs in the initial request, subject (DN) in the initial request or both. This step must be placed later in the workflow than the step(s) to modify the SANs and/or subject. The SANs and subject may be modified with either of the PowerShell step types or a custom step type. The step creates a new CSR using the same public key as the original CSR using the updated SAN and/or subject values. It signs the new CSR with the certificate provided in the step's configuration. For this type of step you will need an enrollment agent certificate available as a PKCS#12 (.PFX) file with included private key to import into Keyfactor Command. This can be a user certificate or a computer certificate (e.g. generated from a copy of the "Enrollment Agent" template or the "Enrollment Agent (Computer)" template) and must have a Certificate Request Agent EKU. Note that the built-in "Enrollment Agent" and "Enrollment Agent (Computer)" templates do not allow private keys to be exported by default. You will need a template that allows private key export or will need to manually override private key export to create a certificate with an exportable private key in order to create a PKCS#12 (.PFX) file. **Important:** This step applies to Microsoft CAs only. If this step is added to workflow for requests directed to an EJBCA CA, it will fail on enrollment. Note that EJBCA supports submission of updated SAN or subject details as part of standard functionality. EnrollStep

Name	Description				
	Name	Description			
		always fall as the la EndNOOP step.  NOOPStep An entry or exit ste the start and end o RevokeStep Revoke a certificate always fall as the la EndNOOP step.  Tip: For steps tha information come	<ul> <li>NOOPStep         An entry or exit step in which no operation occurs. Steps of this type indicate the start and end of the workflow.     </li> <li>RevokeStep         Revoke a certificate through Keyfactor Command. The revoke step must always fall as the last step in the workflow, immediately following the EndNOOP step.     </li> <li>Tip: For steps that send email messages, the SMTP settings and sender information come from the standard Keyfactor Command SMTP configuration (see <u>SMTP on page 1081</u>) and are not configured indi-</li> </ul>		
	Enabled	A Boolean indicating whe	ther the step is enabled to run (true) or not (false).		
	Config- urationPara- meters	An array containing the configuration parameters for the workflow definition step.  These will vary depending on the type of workflow and the type of step (see ExtensionName).			
		Note: There are no ConfigurationParameters for steps of type EnrollStep NOOPStep, or RevokeStep.			
		Possible CustomPowerSh	nell parameters include:		
		Value	Description		
		ScriptParameters	An array of key/value pair strings defining any parameters to be used in the PowerShell script.		
		ScriptName	The path and filename for the script to execute. The script needs to be in the ExtensionLibrary\Workflow directory or a subdirectory of it on the Keyfactor Command server under the install directory. By default, this is:  C:\Program Files\Keyfactor\Keyfactor		

Name	Description	Description				
	Name	Description	Description			
		Value	Description			
			Platform\ExtensionLibrary\Workflow The file must have an extension of .ps1. A sample PowerShell script is provided in the Workflow directory (CustomPowershellExample.ps1).			
		meter replace metace comm	Tip: Tokens (a.k.a. substitutable special text) may be used in the script parameter value field. Tokens use a variable in the workflow definition that is replaced by data from the certificate request, certificate, or certificate metadata at processing time. For example, you can take the revocation comment entered when the revocation request is approved—\$(cmnt)—and append additional data to it using PowerShell.			
		Possible <b>Ema</b>	Possible <b>Email</b> parameters include:			
		Value	Description			
		Subject	A string indicating the subject line for the email message that will be delivered when the workflow definition step is executed.			
		Message	A string indicating the email message that will be delivered when the workflow definition step is executed. The email message is made up of regular text and tokens. If desired, you can format the message body using HTML. For example, for an enrollment pending request notification:			
		"Hello,\n\nA certificate using the \$(template) template was requested by \$(requester:displayname) from \$(CA) on \$(subdate). The certificate details include:\n\n\nCertificate DetailsDetailsCN: \$(request:cn)\$(request:cn)CM: \$(metadata:AppownerFirstName)				
			\$(request:dn)\$(request:dn)\$(metadata:Ap-pOwnerLastName)\$(metadata:Ap-pOwnerLastName)\$(sans)\$(sans)\$(sans)\$(metadata:Ap-pOwnerLastName)\$(metadata:Ap-pO			
			erEmailAddress)\n Business			

Name	Description			
	Name	Description		
		Value	Description	
			Critical: \$(metadata:BusinessCritical)\n\nPlease review this request and issue the certificate as appropriate by going here:\n\n\$(reviewlink)\n\nThanks!\n\nYour Certificate Management Tool\n"  See Table 1: Tokens for Workflow Definitions in the Keyfactor Command Reference Guide for a complete list of available tokens.	
		Recip- ients	An array of strings containing the recipients for the workflow definition email. Each email message can have multiple recipients. You can use specific email addresses and/or use tokens to replace an email address variable with actual email addresses at processing time. Available email tokens include:	
			\$(requester:mail)     The certificate requester, based on a lookup in Active     Directory of the email address associated with the     requester on the certificate.	
			<ul> <li>Your custom email-based metadata field, which would be specified similarly to \$(metadata:AppOwnerEmailAddress).</li> </ul>	
		messa defini certifi quest messa	Tokens (a.k.a. substitutable special text) may be used in the subject line, age and email recipient fields. Tokens use a variable in the workflow ition that is replaced by data from the certificate request, certificate, or icate metadata at processing time. For example, you can select \$(rever) in the workflow definition for an enrollment request and the email age will contain the specific certificate requester name instead of the ole \$(requester).	
		Possible <b>Pow</b>	verShell parameters include:	
		Value	Description	
		ScriptParam	An array of key/value pair strings defining any parameters to be used in the PowerShell script. The key is the name of a custom parameter defined by you and the value is the initial value that should be set for that parameter before the PowerShell is executed, if any.	

Name	Description				
	Name	Description	Description		
		Value	Description		
			Tokens are supported in the <i>value</i> .		
		ScriptContent	A string containing the PowerShell commands to execute. This should be the actual contents of the PowerShell script (the PowerShell commands and supporting components), not a path and filename to an external file.		
		meter value field. replaced by data metadata at proc comment entered	a. substitutable special text) may be used in the script para- Tokens use a variable in the workflow definition that is from the certificate request, certificate, or certificate essing time. For example, you can take the revocation d when the revocation request is approved—\$(cmnt)—and I data to it using PowerShell.		
		Possible RequireApproval parameters include:			
		Value	Description		
		MinimumApprovals	In integer indicating the minimum number of users who must approve the request to allow the request to complete.		
	DenialEmailSubject	A string indicating the subject line for the email message that will be delivered if the request is denied.			
	DenialEmailMessage	A string indicating the email message that will be delivered if the request is denied. The email message is made up of regular text and tokens. If desired, you can format the message body using HTML.  See Table: Tokens for Workflow Definitions in the Keyfactor Command Reference Guide for a complete list of available tokens.			

Name	Description			
	Name	Description		
		Value	Description	
		DenialEmailRecipients	An array of strings containing the recipients for the denial email. Each email message can have multiple recipients. You can use specific email addresses and/or use tokens to replace an email address variable with actual email addresses at processing time. Available email tokens include:  • \$(requester:mail)  The certificate requester, based on a lookup in Active Directory of the email address associated with the requester on the certificate.  • Your custom email-based metadata field, which would be specified similarly to \$(metadata:AppOwnerEmailAddress).	
		Approval Email Subject	A string indicating the subject line for the email message that will be delivered if the request is approved.	
		ApprovalEmailMessage	A string indicating the email message that will be delivered if the request is approved. The email message is made up of regular text and tokens. If desired, you can format the message body using HTML.  See Table: Tokens for Workflow Definitions in the Keyfactor Command Reference Guide for a complete list of available tokens.	
		ApprovalEmailRecipients	An array of strings containing the recipients for the approval email. Each email message can have multiple recipients. You can use specific email addresses and/or use tokens to replace an email address variable with actual email addresses at processing time. Available email tokens include:  • \$(requester:mail)  The certificate requester, based on a	

## **Description** Name Name Description Value Description lookup in Active Directory of the email address associated with the requester on the certificate. · Your custom email-based metadata field, which would be specified similarly to \$(metadata:AppOwnerEmailAddress). Tip: Tokens (a.k.a. substitutable special text) may be used in the subject line, message and email recipient fields. Tokens use a variable in the workflow definition that is replaced by data from the certificate request, certificate, or certificate metadata at processing time. For example, you can select \$(requester) in the workflow definition for an enrollment request and the email message will contain the specific certificate requester name instead of the variable \$(requester). Possible RestRequest parameters include: Value Description Headers An array of key/value pair strings containing the header information for the request. The key is the name of the specific request header (for Keyfactor API request headers, see Table 1: Common Request Headers and the specific documentation for each endpoint) and the value is the value that should be set for that header. For a Keyfactor API request, this might look like: "Headers": { "x-keyfactor-requested-with": [ "APIClient" "x-keyfactor-api-version": [ "2"

Name	Description			
	Name	Description		
		Value	Description	
			Tip: For a Keyfactor API request, version 1 is assumed if no version is specified. Content type and authorization headers do not need to be specified, since those are addressed elsewhere in the configuration.	
		DataBuck- etProperty	A string containing the variable that the response from the request will be returned in, if any. You can then reference this parameter from subsequent steps in the workflow.	
			Tip: The response is stored as a serialized JObject. To make use of only a portion of the response data in your subsequent step, use JSON path syntax. For example, say you returned the data from a GET /Agents request in a variable called MyResponse and you wanted to reference the ClientMachine name for the orchestrator in a subsequent email message. To limit the data to the first result and only the ClientMachine name, in the email message you would enter the following:  \$(MyResponse.[0].ClientMachine)	
		Verb	A string indicating the HTTP verb for the type of request to perform. Supported values are:  • DELETE  • GET  • HEAD  • OPTIONS  • POST  • PUT  • TRACE	
		UseBasicAu- th	A Boolean indicating whether Basic authentication should be used for the request (True) or not (False).  If <i>UseBasicAuth</i> is <i>False</i> , Windows authentication in the context of the Keyfactor Command application pool user will be used (see <i>Create Active Directory Service Accounts for Keyfactor</i>	

Name	Description				
	Name	Description	Description		
		Value	Description		
			Command in the Ko	eyfactor Command Server Installation Guide).	
		BasicUser- name	An array indicating tication if <i>UseBasic</i>	the username information to use for authen- Auth is True.	
			<ul> <li>Store the creatable.</li> <li>A Keyfactor sword that is Keyfactor Co</li> <li>Load the creatable.</li> </ul>	Is to store credential information are: Edential information in the Keyfactor secrets  Secret is a user-defined username or pass- encrypted and stored securely in the emmand database.  Idential information from a PAM provider. Eviders and Privileged Access Management Exeyfactor Command Reference Guide for ation.	
			Value	Description	
			SecretValue	A string containing the username defined for basic authentication (in DOMAIN\\username format).	
			Parameters	An array indicating the parameters to supply for PAM authentication. These will vary depending on the PAM provider.	
			Provider	A string indicating the ID of the PAM provider.  Use the GET /PamProviders method (see GET PAM Providers on page 724) to retrieve a list of all the PAM providers to determine the ID.	
			For example, the u	sername stored as a Keyfactor secret will look	

Name	Description		
	Name	Description	
		Value	Description
			<pre>{     "SecretValue": "KEYEXAMPLE\svc_MyServiceName" }</pre>
			The username stored as a CyberArk PAM secret will look like (where the Provider value—1 in this example—is the Id value from GET PAM Providers on page 724 and the Folder and Object reference the folder name and object name in the CyberArk safe):
			<pre>{     "Provider": "1",     "Parameters":{         "Folder":"MyFolderName",         "Object":"MyWorkflowUsername"     } }</pre>
			The username stored as a Delinea PAM secret will look like (where the Provider value—1 in this example—is the Id value from GET PAM Providers on page 724 and the SecretId is the ID if the secret created in the Delinea secret server for this purpose):
			<pre>{     "Provider": "1",     "Parameters":{         "SecretId":"MyUsernameId"     } }</pre>
			Due to its sensitive nature, this value is not returned in responses.
		BasicPass- word	An array indicating the password information to use for authentication if <i>UseBasicAuth</i> is <i>True</i> . The syntax is the same as for <i>BasicUsername</i> .  Due to its sensitive nature, this value is not returned in

Name	Description			
	Name	Description		
		Value	Description	
			responses.	
		URL	A string containing the URL for the request, including tokens, if desired. For a Keyfactor API request, this might look like:  https://keyfactor.keyexample.com/KeyfactorAP I/Certificates?pq.queryString=CN%20- contains%20%22appsrvr14%22%20AND%20CertStore Path%20-ne%20NULL Or, with tokens: https://keyfactor.keyexample.com/KeyfactorAP I/Certificates/\$(certid)	
			Note: To prevent REST requests from being made to inappropriate locations by malicious users, configure a system environment variable of KEYFACTOR_BLOCKED_OUTBOUND_IPS on your Keyfactor Command server pointing to the IP address or range of addresses in CIDR format that you wish to block. Both IPv4 and IPv6 addresses are supported. More than one address or range may be specified in a comma-delimited list. For example:  192.168.12.0/24,192.168.14.22/24 When a REST request is made where the URL is either configured to a blocked IP address or resolves via DNS to a blocked IP address, the REST request will fail.	
		ContentTyp- e	A string indicating the content type for the request. Supported values are:  • application/json	
		RequestCon- tent	A string containing the body of the REST request, if needed. For a Keyfactor API request, this will vary depending on the request and might look like (for a PUT /Certificates/Metadata request):	
			{     "Id": "\$(certid)",	

## Description Name Name Description Value Description "Metadata":{ "RevocationComment": "\$(cmnt)" Note: This example assumes you have a metadata field called RevocationComment. Tip: Tokens (a.k.a. substitutable special text) may be used in the URL and request content fields. Tokens use a variable in the workflow definition that is replaced by data from the certificate request, certificate, or certificate metadata at processing time. For example, you can take the revocation comment entered when the revocation request is approved—\$(cmnt)—and insert it into a custom metadata field in the certificate by doing a PUT /Certificates/Metadata request for the \$(id). Signals An array of objects containing data used at the point in the workflow step where the workflow needs to continue based on user input. These will vary depending on the type of workflow and the type of step (see ExtensionName). Possible RequireApproval values are: Value **Description** RoleIds An array of integers indicating the security roles whose members are allowed to approve the request. SignalName A string indicating the name of the signal. This value will vary depending on the workflow step. For the built-in Require Approval step, the SignalName is "ApprovalStatus". Important: If all the security roles configured for a workflow step are deleted from Keyfactor Command, no users will be able to submit signals for workflow instances initiated with that workflow definition. To remedy this, update the workflow definition with one or more current security roles, republish it, and then restart any outstanding workflow instances.

Name	Description			
	Name	Description		
	Conditions	An object containing conditions indicating whether the step should run (true) or not (false). Conditions may either have a static value of True or False or a token that will have a value of True or False at the time the step is run. More than one condition may be added. If multiple conditions are used in the same step, all conditions must have a value of True at the time the step is evaluated to be run in order for the step to run. If any single condition evaluates to False, the step will not run. Condition values are:		
		Value	Description	
		Id	A string indicating the Keyfactor Command reference ID of the condition.	
		Value	A string indicating the value of the condition. This should be one of "true", "false", or a token that will be set to either "true" or "false" in an earlier step in the workflow (see Workflow Definition Operations: Adding or Modifying a Workflow Definition in the Keyfactor Command Reference Guide for an example).	
	Outputs	An array indicating the next step in the workflow. Possible values are:		
		Value	Description	
		continue	A string indicating the <i>UniqueName</i> of the next workflow step in the chain. This value will be null for the final step in the chain.	
DraftVer- sion	An integer indicating the version number of the workflow definition. If this version number does not match the <i>PublishedVersion</i> , changes have been made to the workflow definition that have not yet been published.			
Published- Version	An integer indicating the currently published version number of the workflow definition. For a newly created workflow, this value will be null.			

#### 2.2.31.10 POST Workflow Definitions Definition ID Publish

The POST /Workflow/Definitions/{definitionid}/Publish method is used to mark the most recent version of the workflow definition with the specified GUID as the published, active, version. When a definition is published, all new or restarted workflow instances (see <a href="Workflow Instances on page 1325">Workflow Instances on page 1325</a>) will be able to use the updated version of the workflow. This method returns HTTP 200 OK on a success with details about the workflow definition.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: WorkflowDefinitions: *Modify* 

Table 590: POST Workflow Definitions {definitionid} Publish Input Parameters

Name	In	Description
definitionId	Path	Required. A string indicating the Keyfactor Command reference GUID of the workflow definition to publish.  Use the GET /Workflow/Definitions method (see GET Workflow Definitions on page 1269) to retrieve a list of all the workflow definitions to determine the GUID.

Table 591: POST Workflow Definitions {definitionid} Publish Response Body

Name	Description			
Id	A string indicating	the Keyfactor Command reference GUID of the workflow definition.		
DisplayNa- me	A string indicating the display name defined for the workflow definition.			
Descrip- tion	A string indicating the description for the workflow definition.			
Key	field will vary depe	the reference key for the workflow definition. The type of information contained in this ending on the <code>WorkflowType</code> . If the <code>WorkflowType</code> is <code>Enrollment</code> or <code>Revocation</code> , this field effector Command reference ID for the certificate template.		
KeyDis- playName	A string indicating	the friendly name defined in Keyfactor Command for the certificate template.		
IsPub- lished		A Boolean indicating whether the workflow definition has been published (true) or not (false). A workflow definition must be published to activate it. For a newly created workflow, this will be <i>false</i> .		
Work- flowType	A string indicating the type of workflow definition. The currently supported types are:  • Enrollment • Revocation			
Steps	An array of objects indicating the steps in the workflow definition. The contents of each step will vary depending on the type of workflow and the type of step. For a newly created workflow, there will be no data in this value. Possible steps include:			
	Name	Description		
	Id	A string indicating the Keyfactor Command reference GUID of the workflow definition step.		
	DisplayName	A string indicating the display name for the step.		
	UniqueName A string indicating the unique name for the step. This value must be unique among the steps in the particular workflow definition. It is intended to be used as a user-friendly reference ID.			
	Exten- sionName  A string indicating the type of step. The currently supported types are:  • Email			

Name	Description				
	Name	Description			
		Send an email message. This is a separate email message from those typically sent as part of a <i>Require Approval</i> step. You might send an email message as part of an enrollment request to notify approvers that a new request needs approval. The email messages can be customized to provide detailed information about, for example, the certificate request.  • PowerShell  Run PowerShell commands within the confines of the workflow to populate variables with information to pass back to the workflow. The PowerShell script contents are embedded within the step. This step does not call out to an external file. This provides a high level of security by greatly limiting the number of standard PowerShell cmdlets that can be executed by the workflow step. A small number of PowerShell cmdlets have been white listed to allow them to be included in workflow steps of this type, including:  • Where-Object  • ForEach-Object  • Get-Command  • CustomPowerShell  Run a PowerShell script. The script contents are in a file placed in the ExtensionLibrary\Workflow directory or a subdirectory of it on the Keyfactor Command server under the install directory for Keyfactor Command. By default, this is:  C:\Program Files\Keyfactor\Keyfactor Platform\ExtensionLibrary\Workflow  The file must have an extension of .ps1. A sample PowerShell script is			
		provided in the Workflow directory (CustomPowershellExample.ps1).  • RequireApproval			
		Require approval for a workflow step before the step can be completed. The require approval step applies to certificate enrollments, renewals, and revocations and can require approval from just one approver or multiple approvers. The workflow will be suspended at this point until the correct number of approvals from users with the correct security roles is received or until one deny is received before continuing to the next step. As part of this step, an email message is sent indicating whether the step was approved or denied—typically to the requester. This step does not include logic to send an email initiating the approval process (letting users know something needs approval). Use an <i>Email</i> type step for this.			
		Important: Workflows are not supported with CA delegation when they contain steps that require approval. For more information, see			

Name	Description	
	Name	Description
		the CA configuration Authorization Methods Tab in the Keyfactor Command Reference Guide.
		Tip: The workflow builder does not include a step to send a notification to the requester of a certificate once the certificate is issued by the CA (as opposed to approved in Keyfactor Command). Use the issued alerts for this (see Issued Request Alert Operations in the Keyfactor Command Reference Guide).
		RESTRequest
		Run a REST (API) request. The REST request contents are embedded within the step. It does not call out to an external file.
		EnrollmentAgent     On an enrollment (either CSR or PFX), create a resigned CSR to prepare an
		updated enrollment request for delivery to a Microsoft CA after a previous step in the workflow has been used to update either the SANs in the initial request, subject (DN) in the initial request or both. This step must be placed later in the workflow than the step(s) to modify the SANs and/or subject. The SANs and subject may be modified with either of the PowerShell step types or a custom step type. The step creates a new CSR using the same public key as the original CSR using the updated SAN and/or subject values. It signs the new CSR with the certificate provided in the step's configuration.
		For this type of step you will need an enrollment agent certificate available as a PKCS#12 (.PFX) file with included private key to import into Keyfactor Command. This can be a user certificate or a computer certificate (e.g. generated from a copy of the "Enrollment Agent" template or the "Enrollment Agent (Computer)" template) and must have a Certificate Request Agent EKU. Note that the built-in "Enrollment Agent" and "Enrollment Agent (Computer)" templates do not allow private keys to be exported by default. You will need a template that allows private key export or will need to manually override private key export to create a certificate with an exportable private key in order to create a PKCS#12 (.PFX) file.
		Important: This step applies to Microsoft CAs only. If this step is added to workflow for requests directed to an EJBCA CA, it will fail on enrollment. Note that EJBCA supports submission of updated SAN or subject details as part of standard functionality.
		EnrollStep

Name	Description				
	Name	Description			
		Enroll for a certificate through Keyfactor Command. The enroll step m always fall as the last step in the workflow, immediately following the EndNOOP step.  • NOOPStep  An entry or exit step in which no operation occurs. Steps of this type is the start and end of the workflow.  • RevokeStep  Revoke a certificate through Keyfactor Command. The revoke step mis always fall as the last step in the workflow, immediately following the EndNOOP step.  Tip: For steps that send email messages, the SMTP settings and ser information come from the standard Keyfactor Command SMTP configuration (see SMTP on page 1081) and are not configure vidually in the workflow steps.			
	Enabled	A Boolean indicating whether the step is enabled to run (true) or not (false).			
	Config- urationPara- meters	An array containing the co	onfiguration parameters for the workflow definition step.  3 on the type of workflow and the type of step (see <i>Exten</i> -		
		Note: There are NOOPStep, or Rev	no ConfigurationParameters for steps of type EnrollStep, vokeStep.		
		Possible CustomPowerSh	nell parameters include:		
		Value	Description		
		ScriptParameters	An array of key/value pair strings defining any parameters to be used in the PowerShell script.		
		ScriptName	The path and filename for the script to execute. The script needs to be in the ExtensionLibrary\Workflow directory or a subdirectory of it on the Keyfactor Command server under the install directory. By default, this is:  C:\Program Files\Keyfactor\Keyfactor		

Name	Description				
	Name	Description			
		Value	Description		
			Platform\ExtensionLibrary\Workflow The file must have an extension of .ps1. A sample PowerShell script is provided in the Workflow directory (CustomPowershellExample.ps1).		
		meter replace metace comm	Tokens (a.k.a. substitutable special text) may be used in the script pararr value field. Tokens use a variable in the workflow definition that is ced by data from the certificate request, certificate, or certificate data at processing time. For example, you can take the revocation ment entered when the revocation request is approved—\$(cmnt)—and additional data to it using PowerShell.		
		Possible <b>Ema</b>	Possible <b>Email</b> parameters include:		
		Value	Description		
		Subject	A string indicating the subject line for the email message that will be delivered when the workflow definition step is executed.		
		Message	A string indicating the email message that will be delivered when the workflow definition step is executed. The email message is made up of regular text and tokens. If desired, you can format the message body using HTML. For example, for an enrollment pending request notification:		
			"Hello,\n\nA certificate using the \$(template) template was requested by \$(requester:displayname) from \$(CA) on \$(subdate). The certificate details include:\n\n\n Certificate Details Hello,\n\n\n Certificate Details Hello,\n\n\n Certificate Details Hello,\n\n Certificate Details Hello,\n Certificate Details Hello,\n\n Certificate Details Hello,\n Certificate Details Hello,\n Certificate Details Hello,\n Certificate Details Hello,\n Hello,\n<\n<\n<\n<\n<\n<\n<\n<\n<\n<\n<\n<\n<\		
			\$(request:dn)App Owner Last Name: \$(metadata:Ap-pOwnerLastName) notro>\$(sans) d>App Owner Email Address: \$(metadata:Ap-		
			pOwn- erEmailAddress)\n Business		

Name	Description				
	Name	Description	Description		
		Value	Description		
			Critical: \$(metadata:BusinessCritical)\n\nPlease review this request and issue the certificate as appropriate by going here:\n\n\$(reviewlink)\n\nThanks!\n\nYour Certificate Management Tool\n"  See Table 1: Tokens for Workflow Definitions in the Keyfactor Command Reference Guide for a complete list of available tokens.		
		Recip- ients	An array of strings containing the recipients for the workflow definition email. Each email message can have multiple recipients. You can use specific email addresses and/or use tokens to replace an email address variable with actual email addresses at processing time. Available email tokens include:		
			\$(requester:mail)     The certificate requester, based on a lookup in Active     Directory of the email address associated with the     requester on the certificate.		
			<ul> <li>Your custom email-based metadata field, which would be specified similarly to \$(metadata:AppOwnerEmailAddress).</li> </ul>		
		messa defini certifi quest messa	Tokens (a.k.a. substitutable special text) may be used in the subject line, age and email recipient fields. Tokens use a variable in the workflow ition that is replaced by data from the certificate request, certificate, or icate metadata at processing time. For example, you can select \$(rever) in the workflow definition for an enrollment request and the email age will contain the specific certificate requester name instead of the ole \$(requester).		
		Possible <b>PowerShell</b> parameters include:			
		Value	Description		
		ScriptParam	An array of key/value pair strings defining any parameters to be used in the PowerShell script. The key is the name of a custom parameter defined by you and the value is the initial value that should be set for that parameter before the PowerShell is executed, if any.		

Name	Description					
	Name	Description				
		Value	Description			
			Tokens are supported in the <i>value</i> .			
		ScriptContent	A string containing the PowerShell commands to execute. This should be the actual contents of the PowerShell script (the PowerShell commands and supporting components), not a path and filename to an external file.			
		Tip: Tokens (a.k.a. substitutable special text) may be used in the script parameter value field. Tokens use a variable in the workflow definition that is replaced by data from the certificate request, certificate, or certificate metadata at processing time. For example, you can take the revocation comment entered when the revocation request is approved—\$(cmnt)—and append additional data to it using PowerShell.				
		Possible RequireApproval parameters include:				
		Value	Description			
		MinimumApprovals	In integer indicating the minimum number of users who must approve the request to allow the request to complete.			
		DenialEmailSubject	A string indicating the subject line for the email message that will be delivered if the request is denied.			
		DenialEmailMessage	A string indicating the email message that will be delivered if the request is denied. The email message is made up of regular text and tokens. If desired, you can format the message body using HTML.  See Table: Tokens for Workflow Definitions in the Keyfactor Command Reference Guide for a complete list of available tokens.			

Name	Description				
	Name	Description			
		Value	Description		
		DenialEmailRecipients	An array of strings containing the recipients for the denial email. Each email message can have multiple recipients. You can use specific email addresses and/or use tokens to replace an email address variable with actual email addresses at processing time. Available email tokens include:  • \$(requester:mail)  The certificate requester, based on a lookup in Active Directory of the email address associated with the requester on the certificate.  • Your custom email-based metadata field, which would be specified similarly to \$(metadata:AppOwnerEmailAddress).		
		ApprovalEmailSubject	A string indicating the subject line for the email message that will be delivered if the request is approved.		
			ApprovalEmailMessage	A string indicating the email message that will be delivered if the request is approved. The email message is made up of regular text and tokens. If desired, you can format the message body using HTML.  See <i>Table: Tokens for Workflow Definitions</i> in the <i>Keyfactor Command Reference Guide</i> for a complete list of available tokens.	
		ApprovalEmailRecipients	An array of strings containing the recipients for the approval email. Each email message can have multiple recipients. You can use specific email addresses and/or use tokens to replace an email address variable with actual email addresses at processing time. Available email tokens include:  • \$(requester:mail)  The certificate requester, based on a		

### Description Name Name Description Value Description lookup in Active Directory of the email address associated with the requester on the certificate. · Your custom email-based metadata field, which would be specified similarly to \$(metadata:AppOwnerEmailAddress). Tip: Tokens (a.k.a. substitutable special text) may be used in the subject line, message and email recipient fields. Tokens use a variable in the workflow definition that is replaced by data from the certificate request, certificate, or certificate metadata at processing time. For example, you can select \$(requester) in the workflow definition for an enrollment request and the email message will contain the specific certificate requester name instead of the variable \$(requester). Possible RestRequest parameters include: Value Description Headers An array of key/value pair strings containing the header information for the request. The key is the name of the specific request header (for Keyfactor API request headers, see Table 1: Common Request Headers and the specific documentation for each endpoint) and the value is the value that should be set for that header. For a Keyfactor API request, this might look like: "Headers": { "x-keyfactor-requested-with": [ "APIClient" "x-keyfactor-api-version": [ "2"

Name	Description		
	Name	Description	
		Value	Description
			Tip: For a Keyfactor API request, version 1 is assumed if no version is specified. Content type and authorization headers do not need to be specified, since those are addressed elsewhere in the configuration.
		DataBuck- etProperty	A string containing the variable that the response from the request will be returned in, if any. You can then reference this parameter from subsequent steps in the workflow.
			Tip: The response is stored as a serialized JObject. To make use of only a portion of the response data in your subsequent step, use JSON path syntax. For example, say you returned the data from a GET /Agents request in a variable called MyResponse and you wanted to reference the ClientMachine name for the orchestrator in a subsequent email message. To limit the data to the first result and only the ClientMachine name, in the email message you would enter the following:  \$(MyResponse.[0].ClientMachine)
		Verb	A string indicating the HTTP verb for the type of request to perform. Supported values are:  DELETE GET HEAD OPTIONS POST PUT TRACE
		UseBasicAu- th	A Boolean indicating whether Basic authentication should be used for the request (True) or not (False).  If <i>UseBasicAuth</i> is <i>False</i> , Windows authentication in the context of the Keyfactor Command application pool user will be used (see <i>Create Active Directory Service Accounts for Keyfactor</i>

Name	Description				
	Name	Description	Description		
		Value	Description		
			Command in the Ke	ryfactor Command Server Installation Guide).	
		BasicUser- name	An array indicating tication if <i>UseBasicA</i>	the username information to use for authen-	
			<ul> <li>Store the cred table.</li> <li>A Keyfactor so word that is e Keyfactor Cor</li> <li>Load the cred See PAM Prov</li> </ul>	dential information in the Keyfactor secrets  ecret is a user-defined username or passencrypted and stored securely in the mmand database.  dential information from a PAM provider.  viders and Privileged Access Management  Keyfactor Command Reference Guide for ation.	
			Value	Description	
			SecretValue	A string containing the username defined for basic authentication (in DOMAIN\\username format).	
			Parameters	An array indicating the parameters to supply for PAM authentication. These will vary depending on the PAM provider.	
			Provider	A string indicating the ID of the PAM provider.  Use the GET /PamProviders method (see GET PAM Providers on page 724) to retrieve a list of all the PAM providers to determine the ID.	
			For example, the us like:	sername stored as a Keyfactor secret will look	

Name	Description		
	Name	Description	
		Value	Description
			<pre>{     "SecretValue": "KEYEXAMPLE\svc_MyServiceName" }</pre>
			The username stored as a CyberArk PAM secret will look like (where the Provider value—1 in this example—is the Id value from GET PAM Providers on page 724 and the Folder and Object reference the folder name and object name in the CyberArk safe):
			<pre>{     "Provider": "1",     "Parameters":{         "Folder":"MyFolderName",         "Object":"MyWorkflowUsername"     } }</pre>
			The username stored as a Delinea PAM secret will look like (where the Provider value—1 in this example—is the Id value from GET PAM Providers on page 724 and the SecretId is the ID if the secret created in the Delinea secret server for this purpose):
			<pre>{     "Provider": "1",     "Parameters":{         "SecretId":"MyUsernameId"     } }</pre>
			Due to its sensitive nature, this value is not returned in responses.
		BasicPass- word	An array indicating the password information to use for authentication if <i>UseBasicAuth</i> is <i>True</i> . The syntax is the same as for <i>BasicUsername</i> .  Due to its sensitive nature, this value is not returned in

Name	Description		
	Name	Description	
		Value	Description
			responses.
		URL	A string containing the URL for the request, including tokens, if desired. For a Keyfactor API request, this might look like:  https://keyfactor.keyexample.com/KeyfactorAP I/Certificates?pq.queryString=CN%20- contains%20%22appsrvr14%22%20AND%20CertStore Path%20-ne%20NULL Or, with tokens: https://keyfactor.keyexample.com/KeyfactorAP I/Certificates/\$(certid)
			Note: To prevent REST requests from being made to inappropriate locations by malicious users, configure a system environment variable of KEYFACTOR_BLOCKED_OUTBOUND_IPS on your Keyfactor Command server pointing to the IP address or range of addresses in CIDR format that you wish to block. Both IPv4 and IPv6 addresses are supported. More than one address or range may be specified in a comma-delimited list. For example:  192.168.12.0/24,192.168.14.22/24 When a REST request is made where the URL is either configured to a blocked IP address or resolves via DNS to a blocked IP address, the REST request will fail.
		ContentTyp- e	A string indicating the content type for the request. Supported values are:  • application/json
		RequestCon- tent	A string containing the body of the REST request, if needed. For a Keyfactor API request, this will vary depending on the request and might look like (for a PUT /Certificates/Metadata request):
			{     "Id": "\$(certid)",

## Description Name Name Description Value Description "Metadata":{ "RevocationComment": "\$(cmnt)" Note: This example assumes you have a metadata field called RevocationComment. Tip: Tokens (a.k.a. substitutable special text) may be used in the URL and request content fields. Tokens use a variable in the workflow definition that is replaced by data from the certificate request, certificate, or certificate metadata at processing time. For example, you can take the revocation comment entered when the revocation request is approved—\$(cmnt)—and insert it into a custom metadata field in the certificate by doing a PUT /Certificates/Metadata request for the \$(id). Signals An array of objects containing data used at the point in the workflow step where the workflow needs to continue based on user input. These will vary depending on the type of workflow and the type of step (see ExtensionName). Possible RequireApproval values are: Value **Description** RoleIds An array of integers indicating the security roles whose members are allowed to approve the request. SignalName A string indicating the name of the signal. This value will vary depending on the workflow step. For the built-in Require Approval step, the SignalName is "ApprovalStatus". Important: If all the security roles configured for a workflow step are deleted from Keyfactor Command, no users will be able to submit signals for workflow instances initiated with that workflow definition. To remedy this, update the workflow definition with one or more current security roles, republish it, and then restart any outstanding workflow instances.

Name	Description					
	Name	Description				
	Conditions	An object containing conditions indicating whether the step should run (true) or not (false). Conditions may either have a static value of True or False or a token that will have a value of True or False at the time the step is run. More than one condition may be added. If multiple conditions are used in the same step, all conditions must have a value of True at the time the step is evaluated to be run in order for the step to run. If any single condition evaluates to False, the step will not run. Condition values are:				
		Value	Description			
	Outputs	Id	A string indicating the Keyfactor Command reference ID of the condition.			
		Value	A string indicating the value of the condition. This should be one of "true", "false", or a token that will be set to either "true" or "false" in an earlier step in the workflow (see Workflow Definition Operations: Adding or Modifying a Workflow Definition in the Keyfactor Command Reference Guide for an example).			
		An array indicating the next step in the workflow. Possible values are:				
		Value	Description			
		continue A string indicating the <i>UniqueName</i> of the next workflow step in the chain. This value will be null for the final step in the chain.				
DraftVer- sion	-	on integer indicating the version number of the workflow definition. If this version number does not match the <i>PublishedVersion</i> , changes have been made to the workflow definition that have not yet been published.				
Published- Version	An integer indicating the currently published version number of the workflow definition. For a newly created workflow, this value will be null.					

# 2.2.32 Workflow Instances

The Workflow Instances component of the Keyfactor API includes methods necessary to programmatically retrieve, restart, delete and submit data into workflow instances.

Table 592: Workflow Instances Endpoints

Endpoint	Method	Description	Link	
/{instanceId}	DELETE	Delete the workflow instance with he	DELETE Workflow Instances	

Endpoint	Method	Description	Link
		specified GUID.	Instance Id on the next page
/{instanceId}	GET	Retrieve the workflow instance with the specified GUID.	GET Workflow Instances Instance ID on the next page
/	GET	Retrieve a list of the workflow instances.	GET Workflow Instances on page 1348
/My	GET	Retrieve the workflow instances created by the user making the API request.	GET Workflow Instances My on page 1351
/AssignedToMe	GET	Retrieve the workflow instances assigned to the user making the API request.	GET Workflow Instances AssignedToMe on page 1354
/{instanceId}/Stop	POST	Rejects a workflow instance, preventing it from continuing.	POST Workflow Instances Instance Id Stop on page 1357
/{instanceId}/Signals	POST	Input data to the workflow instance with the specified GUID.	POST Workflow Instances Instance ID Signals on page 1358
/{instanceId}/Restart	POST	Restart the specified workflow instance after a failure.	POST Workflow Instances Instance Id Restart on page 1360

### 2.2.32.1 DELETE Workflow Instances Instance Id

The DELETE /Workflow/Instances/{instanceId} method is used to delete the workflow instance with the specified GUID. This endpoint returns 204 with no content upon success.



 $\textbf{Tip: } The following permissions (see \underline{Security\ Overview}) are required to use this feature: \\ WorkflowInstances: \underline{\textit{Manage}}$ 

Table 593: DELETE Workflow Instances {instanceid} Input Parameters

Name	In	Description
instanceId	Path	<b>Required</b> . A string indicating the Keyfactor Command reference GUID of the workflow instance to delete.
		Use the <i>GET /Workflow/Instances</i> method (see <u>GET Workflow Instances on page 1348</u> ) to retrieve a list of all the workflow instances to determine the GUID.

### 2.2.32.2 GET Workflow Instances Instance ID

The GET /Workflow/Instances/{instanceId} method is used to retrieve the initiated workflow with the specified instance GUID. Both in progress and completed workflows will be returned. This method returns HTTP 200 OK on a success with details about the workflow instance.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature:

WorkflowInstances: ReadAll OR

WorkflowInstances: ReadAssignedToMe OR

WorkflowInstances: ReadMy

Users with *ReadMy* or *ReadAssignedToMe* will only be able to retrieve the workflow instances created by them (*ReadMy*) or assigned to them (*ReadAssignedToMe*) unless they also have *ReadAll*.

Table 594: GET Workflow Instances {instanceId} Input Parameters

Name	In	Description
instanceId	Path	Required. A string indicating the Keyfactor Command reference GUID of the workflow instance to retrieve.  Use the GET /Workflow/Instances method (see GET Workflow Instances on page 1348) to retrieve a list of all the workflow instances to determine the GUID.

Table 595: GET Workflow Instances {instanceId} Response Data

Name	Description					
Id	A string indicating the K	eyfactor Command reference GUID of the workflow instance.				
Status	A string indicating the current status of the workflow instance. The possible statuses are:  CanceledForRestart  Complete  Failed  Rejected  Running  Suspended					
CurrentStepID	A string indicating the K	eyfactor Command reference GUID of the workflow instance step.				
StatusMessage	vary and may include:  • Access is denied  • Awaiting # more a  • Either the creden  • Issued  • Issued. The privat  • Post-process Faile  • Pre-process failed  • Revoked  • Step 'Keyfactor-Ei  • Step [custom step]	approval(s) from approval roles.  tials are invalid, or the CA on [CA hostname] is not running  te key was successfully retained.  ed: [Message indicating reason for failure generally from the CA]  d: [Message indicating details of the failure]  evoke' failed: [Message indicating details of the failure]  evoke' failed: [Message indicating details of the failure]  in name] failed: [Message indicating details of the failure]  mission. The certificate template requires manager approval, and is marked  d by user with Id #.				
Signals		e data used at the point in the workflow step where the workflow needs to input. These will vary depending on the type of workflow and the type of Approval values are:				
	Value	Description				
	SignalName	A string indicating the name of the signal. For a RequireApproval step, this				

Name	Description				
	Value	Description			
		is ApprovalStatus.			
	StepSignalId	A string indicating the Keyfactor Command reference GUID of the signal in the step.			
	SignalReceived	A Boolean indicating whether a signal (input) has been received from at least one end user (true) or not (false).  For a RequireApproval workflow that requires approval from more than one user, the SignalReceived may be true while the workflow instance still has a Suspended status indicating further input is needed.			
Definition	An array containing the	e workflow definition. Workflow definition data includes:			
	Name	Description			
	Id	A string indicating the Keyfactor Command reference GUID of the workflow definition.			
	DisplayName	A string indicating the display name defined for the workflow definition.			
	Version	An integer indicating the version number of the workflow definition.			
	WorkflowType	A string indicating the type of workflow definition. The currently supported types are:  • Enrollment • Revocation			
CurrentStepDis- playName	A string indicating the o	display name defined for the workflow instance step.			
CurrentStepU- niqueName	A string indicating the unique name defined for the workflow instance step. This value is unique among the steps in a particular workflow definition. It is intended to be used as a user-friendly reference ID.				
Title	A string indicating a description for the action taking place in the step, made up of the <i>InitiatingUserName</i> (DOMAIN\\username) followed by an indication of the type of action and a specific message about the action. For example:				
	srvr14.keyexamı	jsmith is enrolling for a certificate with CN=apps- ple.com."			
	Or "KEYEXAMPLE\\jsmith is revoking certificate with CN=appsrvr12.keyexample.com."				

Name	Description					
LastModified	A string indicating the date and time on which the initiated instance was last updated. The instance is updated each time a step in the workflow is completed, when signals are received for a step that accepts signals (e.g. a requires approval step), or when an instance is stopped or restarted.					
StartDate	A string indicating the da	ite and time w	when the instance	was initiated.		
InitialData	An array containing the o			nstance when the workflow was initiated.		
	Name	Oper- ation Type	Description			
	CertificateAuthority	Enroll- ment and Revoc- ation	A string indicating the certificate authority that will be used to enroll against, for enrollment requests, or that issued the certificate, for revocation requests in hostname\log name format.			
	CertificateId	Revoc- ation	An integer indicating the Keyfactor Command reference ID for the certificate.			
	SerialNumberString	Revoc- ation	A string indicat revoked.	A string indicating the serial number of the certificate being revoked.		
	Thumbprint	Revoc- ation	A string indicating the thumbprint of the certificate being revoked.			
	RevokeCode	Revoc- ation	_	caining the specific reason that the certi- evoked. Available values are:		
			Value	Description		
			-1	Remove from Hold		
			0	Unspecified		
			1	Key Compromised		
			2	CA Compromised		
			3	Affiliation Changed		

Name	Description				
	Name	Oper- ation Type	Description		
			Value	Description	
			4	Superseded	
			5	Cessation of Operation	
			6	Certificate Hold	
				7	Remove from CRL. Only valid in the case that a cert is already on a CRL in a manner that it can be removed, such as Certificate Hold
			The default is <i>Unspecified</i> .		
	EffectiveDate	Revoc- ation	A string containing the date and time when the certificate will be revoked.		
	Comment	Revoc- ation	A string containing a freeform reason or comment on why the certificate is being revoked.		
	Delegate	Revoc- ation	A Boolean indicating whether delegation is enabled for the certificate authority that issued the certificate (true) or not (false).		
	OperationStart	Revoc- ation	A string indicating the time at which the revocation work flow was initiated.		
	Template	Enroll- ment	A string indicating the certificate template short name used for the enrollment request.		
	IncludeChain	Enroll- ment	A Boolean indicating whether to include the certificate chain in the enrollment response (true) or not (false).		
	SANs	Enroll- ment	ative names (SA	/value pairs indicating the subject altern-ANs) for the certificate requested in the assible values for the key are:	

e	Description				
	Name	Oper- ation Type	Description		
			Value	Description	
			rfc822	RFC 822 Name	
			dns	DNS Name	
			directory	Directory Name	
			uri	Uniform Resource Identifier	
			ip4	IP v4 Address	
			ip6	IP v6 Address	
			registeredid	Registered ID (an OID)	
			ms_ntprincipalname	MS_NTPrincipalName (a string)	
			ms_ntdsreplication	MS_NTDSReplication (a GUID)	
			For example:		
	AdditionalAttributes	Enroll- ment	custom enrollment fields	irs indicating values for any s set on the certificate template to ttributes to the CA during the	
	Metadata	Enroll- ment	An array of key/value pai	irs indicating values for the	

Name	Description				
	Name	Oper- ation Type	Description		
				will be associated with the certificate or Command. The <i>key</i> is the field name walue for the field.	
	Format	Enroll- ment	ficate. A value of STO	ne desired output format for the certi- DRE indicates that the certificate is ered into one or more certificate	
	CustomName	Enroll- ment	A string indicating a ficate.	custom friendly name for the certi-	
	Subject	Enroll- ment	A string containing the subject name of the requested ficate using X.500 format.		
	RenewalCertificate	Enroll- ment	An array containing the certificate information for the certificate that is being renewed. Certificate data includes:		
			Name	Description	
			Certificate	An array containing a key value pair referencing the certificate being renewed in the following format:	
					{     "RawData":"[PEM-encoded     certificate string]" }
			CertificateId	An integer containing the Keyfactor Command reference ID of the certificate being renewed.	
			that are general (see	ield is only populated for enrollments erated by requesting a certificate erange Renew in the Keyfactor Command wide and POST Enrollment Renew on	

Name	Description				
	Name	Oper- ation Type	Description	n	
			page page	e 627).	
	Stores	Enroll- ment	An object containing a comma delimited set of arrays indicating the certificate stores to which the certificate should be distributed. Store details include:		
			Name StoreId	An array of GUIDs indicating the certificate store(s) to which the certificate should be deployed.  Use the GET /CertificateStores method (see GET Certificate Stores on page 377) with a query of "Approved -eq true" to retrieve a list of all your approved certificate stores to determine the GUID(s) of the store(s).  The alias of the certificate upon entry into the store. The format of and requirement for this varies depending on the certificate store type and whether the Overwrite flag is selected. See PFX Enrollment in the Keyfactor Command Reference Guide for more information.	
			Over- write	A Boolean that sets whether a certificate in the store with the <i>Alias</i> provided should be overwritten with the new certificate (true) or not (false). The default is <i>false</i> .  Use the <i>GET /Certificates/Locations/{id}</i> method (see <u>GET Certificates Locations ID on page 216</u> ) to retrieve a list of the locations an existing certificate is in to determine the alias used for the certificate in the certificate store.	

Name	Description				
	Name	Oper- ation Type	Descriptio	n	
			Name	Description	
			Properties Properties	An array of key/value pairs for the unique parameters defined for the certificate store type that need to be populated for the certificate. The key is the name of the specific parameter from the certificate store type definition as returned in the JobProperties on the store type using the GET CertificateStoreTypes method and the value is the value that should be set for that parameter on the certificate in the certificate store. For example, for NetScaler, the key name that is optionally used to associate the certificate with a virtual server is NetscalerVserver and is returned by GET CertificateStoreTypes like so:  "JobProperties": [ "NetscalerVserver"] It can be seen in the Keyfactor Command Management Portal when editing the certificate store type in the field for Management Job Custom Fields.  The setting is referenced using the following format:  "Properties": { "NetscalerVserver": "MyVirt ualServerName"}  Note: The only built-in certificate store type that makes use of properties that can be set on a certificate-by-certificate basis in the store is NetScaler. You may have custom certificate store types that make use of this func-	

Name	Description			
	Name	Oper- ation Type	Description	
			Name Description tionality.	
	Manage- Enroll- mentJobTime ment	An array indicating the schedule for the manage to add the certificate to the certificate store(s). management job time values include:  Name  Description		
			Immediate  A Boolean that indicates a job uled to run immediately (true (false).  Tip: In some instance initially scheduled as diate will appear on a null.	e) or not es, jobs Imme-
			ExactlyOnce e  A dictionary that indicates a juled to run at the time specific the parameter:  Name  Description  Time  The date and next run the date and time be given usin ISO 8601 UTO format YYYY-DDTHH:mm:s (e.g. 2021-05) 19T16:23:012	time to job. The e should g the C time MM-ss.000Z

Name	Description			
	Name	Oper- ation Type	Description	
			Name	Description
				For example, exactly once at 11:45 am:  "ExactlyOnce": {      "Time": "2022-02- 27T11:45:00Z" }
				Tip: In some instances, jobs initially scheduled as <i>Immediate</i> will appear on a GET as <i>ExactlyOnce</i> .
	IsPFX	Enroll- ment		cating whether the certificate enrollment ated the workflow instance was PFX (true) or
	PfxPass- wordSecretIn- stanceId	Enroll- ment		ting the Keyfactor Command reference GUID ssword used to secure the PFX file on down-
	InitiatingUserName	Enroll- ment and Revoc- ation	ent workflow in DOMAIN\\username format. d voc-	
CurrentStateData	,	cripts, REST re	ided in the workflow instance as it progresses. This will include ST requests, and signals along with the initial data. Current st	
	Name	Oper- ation Type	Description	
	CertificateAuthority	Enroll- ment	A string indicating the certificate authority that will be use to enroll against, for enrollment requests, or that issued	

Name	Description			
	Name	Oper- ation Type	Description	
		and Revoc- ation	the certificate,	for revocation requests.
	CertificateId	Revoc- ation		requests only, an integer indicating the mand reference ID for the certificate.
	SerialNumberString	Revoc- ation	A string indicati revoked.	ing the serial number of the certificate being
	Thumbprint	Revoc- ation	A string indicating the thumbprint of the certificate being revoked.	
	RevokeCode	Revoc- ation	An integer containing the specific reason that the ce ficate is being revoked. Available values are:	
			Value	Description
			-1	Remove from Hold
			0	Unspecified
			1	Key Compromised
			2	CA Compromised
			3	Affiliation Changed
			4	Superseded
			5	Cessation of Operation
			6	Certificate Hold
			7	Remove from CRL. Only valid in the case that a cert is already on a CRL in a manner that it can be removed, such as Certificate Hold
			The default is <i>U</i>	Inspecified.

Name	Description				
	Name	Oper- ation Type	Description		
	EffectiveDate	Revoc- ation	A string containing the d will be revoked.	ate and time when the certificate	
	Comment	Revoc- ation	A string containing a free the certificate is being re	eform reason or comment on why evoked.	
	Delegate	Revoc- ation		ether delegation is enabled for the issued the certificate (true) or not	
	OperationStart	Revoc- ation	A string indicating the time at which the revocation workflow was initiated.		
	Template	Enroll- ment	A string indicating the short certificate template name used for the enrollment request.		
	IncludeChain	Enroll- ment		whether to include the certificate response (true) or not (false).	
	SANs	Enroll- ment		irs indicating the subject altern- he certificate requested in the ues for the key are:	
			Value	Description	
			rfc822	RFC 822 Name	
			dns	DNS Name	
			directory	Directory Name	
			uri	Uniform Resource Identifier	
			ip4	IP v4 Address	
			ip6	IP v6 Address	
			registeredid	Registered ID (an OID)	

Name	Description				
	Name	Oper- ation Type	Description		
			Value	Description	
			ms_ntprincipalname	MS_NTPrincipalName (a string)	
			ms_ntdsreplication	MS_NTDSReplication (a GUID)	
			For example:		
	AdditionalAttributes	Enroll- ment	An array of key/value pairs indicating values for any custom enrollment fields set on the certificate template to supply custom request attributes to the CA during the enrollment process.		
	Metadata	Enroll- ment	An array of key/value pairs indicating values for the metadata fields that will be associated with the certificate once it is in Keyfactor Command. The <i>key</i> is the field name and the <i>value</i> is the value for the field.		
	Format	Enroll- ment	A string indicating the desired output format for the certificate. A value of STORE indicates that the certificate is intended to be delivered into one or more certificate stores.		
	CustomName	Enroll- ment	A string indicating a cust ficate.	om friendly name for the certi-	
	Subject	Enroll- ment	A string containing the su ficate using X.500 format	ubject name of the requested certit.	

Name	Description			
	Name	Oper- ation Type	Description	
	RenewalCertificate	Enroll- ment		the certificate information for the certi- renewed. Certificate data includes:
			Name	Description
	that are gene renewal (see	An array containing a key value pair referencing the certificate being renewed in the following format:		
				{     "RawData":"[PEM- encoded certificate string]" }
			CertificateId	An integer containing the Keyfactor Command reference ID of the certificate being renewed.
			that are ge renewal (se Reference (	field is only populated for enrollments nerated by requesting a certificate ee <i>Renew</i> in the <i>Keyfactor Command Guide</i> and POST Enrollment Renew on
	Stores			ng a comma delimited set of arrays indic- e stores to which the certificate should re details include:
			Name Des	cription
			store	rray of GUIDs indicating the certificate e(s) to which the certificate should be oyed.

Name	Description				
	Name	Oper- ation Type	Description		
			Name	Description	
				Use the GET /CertificateStores method (see GET Certificate Stores on page 377) with a query of "Approved -eq true" to retrieve a list of all your approved certificate stores to determine the GUID(s) of the store(s).	
			Alias	The alias of the certificate upon entry into the store. The format of and requirement for this varies depending on the certificate store type and whether the <i>Overwrite</i> flag is selected. See <i>PFX Enrollment</i> in the <i>Keyfactor Command Reference Guide</i> for more information.	
			Over- write	A Boolean that sets whether a certificate in the store with the <i>Alias</i> provided should be overwritten with the new certificate (true) or not (false). The default is <i>false</i> .  Use the <i>GET /Certificates/Locations/{id}</i> method (see <u>GET Certificates Locations ID on page 216</u> ) to retrieve a list of the locations an existing certificate is in to determine the alias used for the certificate in the certificate store.	
			Prop- erties	An array of key/value pairs for the unique parameters defined for the certificate store type that need to be populated for the certificate. The <i>key</i> is the name of the specific parameter from the certificate store type definition as returned in the JobProperties on the store type using the <i>GET CertificateStoreTypes</i> method and the <i>value</i> is the value that should be set for	

Name	Description			
	Name	Oper- ation Type	Description	n
			Name	Description
				that parameter on the certificate in the certificate store. For example, for NetScaler, the key name that is optionally used to associate the certificate with a virtual server is NetscalerVserver and is returned by GET CertificateStoreTypes like so:  "JobProperties": [ "NetscalerVserver" ] It can be seen in the Keyfactor Command Management Portal when editing the certificate store type in the field for Management Job Custom Fields.  The setting is referenced using the following format:  "Properties": { "NetscalerVserver": "MyVirt ualServerName"}  Note: The only built-in certificate store type that makes use of properties that can be set on a certificate-by-certificate basis in the store is NetScaler. You may have custom certificate store types that make use of this functionality.
	Manage- mentJobTime	Enroll- ment	to add the co	icating the schedule for the management job ertificate to any certificate store(s). Possible It job time values include:

Name	Description				
	Name	Oper- ation Type	Description		
			Name	Description	
			Immediate		nt indicates a job sched- nmediately (true) or not
			initial	n some instances, jobs ly scheduled as <i>Imme-</i> will appear on a GET as	
			ExactlyOnc- e	A dictionary that indicates a job scheduled to run at the time specified with the parameter:	
				Name	Description
			Time	The date and time to next run the job. The date and time should be given using the ISO 8601 UTC time format YYYY-MM-DDTHH:mm:ss.000Z (e.g. 2021-05-19T16:23:01Z).	
			"ExactlyOr	: "2022-02-	
				initiall diate	n some instances, jobs ly scheduled as <i>Imme</i> - will appear on a GET as lyOnce.

Name	Description				
	Name	Oper- ation Type	Description		
	IsPFX	Enroll- ment	A Boolean indicating whether type that initiated the workf CSR (false).	er the certificate enrollment flow instance was PFX (true) or	
	PfxPass- wordSecretIn- stanceId	Enroll- ment		ctor Command reference GUID o secure the PFX file on down-	
	InitiatingUserName	Enroll- ment and Revoc- ation	A string indicating the name of the user who initiated the workflow in DOMAIN\\username format.		
	KeyRetention	Enroll- ment	A Boolean indicating whether the private key for the certificate resulting from the enrollment will be retained in Keyfactor Command (true) or not (false).		
	CSR	Enroll- ment	A string containing the CSR generated for the certificate request.		
	(Custom)	Enroll- ment and Revoc- ation	Optional user-generated custom fields returning response data from PowerShell scripts or REST requests.		
	CACertificate	Enroll- ment	An array containing the cert from the CA for the certifica certificate details include:	ificate information returned te that is being requested. CA	
			Name	Description	
			CACertificateId	A string containing the ID assigned to the certificate by the CA.	
			CARequestID	A string containing the	

Name	Description				
	Name	Oper- ation Type	Description		
			Name	Description	
				ID assigned to the certificate request by the CA.	
			Status	An integer indicating the status for the certificate as returned by the CA.	
			Certificate	A string containing the certificate as returned by the CA in base-64 encoded binary format.	
			CertificateTemplate	A string indicating the certificate template used to issue the certificate.	
			RevocationDate	A string indicating the revocation date for the certificate as returned by the CA.	
			RevocationReason	A string indicating the revocation reason for the certificate as returned by the CA.	
			ArchivedKey	A Boolean indicating whether the certificate is configured for key archival on the CA (true) or not (false).	
			Note: This field is o certificate has been	nly populated only after the issued by the CA.	
	DispositionMessage	Enroll- ment	A string indicating a message (e.g. "The private key was su	e about the certificate request uccessfully retained.").	

Name	Description				
	Name	Oper- ation Type	Description		
				is only populated only after the est has been submitted to the CA.	
	CACer- tificateRequest	Enroll- ment	An array containing the certificate information for the certificate that is being requested. Certificate request data includes:		
			Name	Description	
		Enroll-ment Enroll-ment	CARequestId	A string containing the ID assigned to the certificate request by the CA.	
	SerialNumber IssuerDn		CSR	A string containing the certificate signing request for the certificate request as returned by the CA.	
			Status	An integer indicating the status for the certificate as returned by the CA.	
				RequesterName	A string containing the requester name on the certificate request as returned by the CA.
				is populated only if the certificate he CA level or requires manager CA level.	
			A string indicating the se	erial number of the certificate.	
			A string indicating the di	stinguished name of the issuer.	
	Thumbprint	Enroll-	A string indicating the th	numbprint of the certificate.	

Name	Description		
	Name	Oper- ation Type	Description
		ment	
	KeyfactorId	Enroll- ment	An integer indicating the Keyfactor Command reference ID for the certificate.
	KeyStatus	Enroll- ment	An integer indicating the status of the private key retention for the certificate within Keyfactor Command. Possible values are:  • 0—Unknown • 1—Saved • 2—Expected • 3—NoRetention • 4—Failure • 5—Temporary
	Priv- ateKeyConverter	Enroll- ment	An internally used Keyfactor Command field.
ReferenceId	A integer indicating the Keyfactor Command reference ID for the workflow instance.		

## 2.2.32.3 GET Workflow Instances

The GET /Workflow/Instances method is used to retrieve the list of workflows that have been initiated. Both in progress and completed workflows are included. This method returns HTTP 200 OK on a success with details about the workflow instances.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: WorkflowInstances: *ReadAll* 

Table 596: GET Workflow Instances Input Parameters

Name	In	Description
queryString	Query	A string containing a query to limit the results (e.g. field1 -eq value1 AND field2 -gt value2). The default is to return all records. Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns for the same feature. For querying guidelines, refer to the Keyfactor Command Reference Guide: Using the Workflow Instances Search Feature. The query fields supported for this endpoint are:  • DefinitionId (workflow definition ID)  • Id (workflow instance GUID)  • InitiatingUserName (DOMAIN\\username)  • LastModified  • ReferenceId (workflow instance integer ID)  • StartDate  • Status  • Title  • WorkflowType
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>CurrentStepDisplayName</i> .
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.

Table 597: GET Workflow Instances Response Data

Name	Description	
Id	A string indicating the Keyfactor Command reference GUID of the workflow instance.	
Status	A string indicating the current status of the workflow instance. The possible statuses are:  CanceledForRestart  Complete  Failed  Rejected  Running  Suspended	
CurrentStepID	A string indicating the Key	rfactor Command reference GUID of the workflow instance step.
StatusMessage	A string indicating the Keyfactor Command reference GUID of the workflow instance step  A string indicating the current status message for the workflow instance. Possible status messages vary and may include:  • Access is denied  • Awaiting # more approval(s) from approval roles.  • Either the credentials are invalid, or the CA on [CA hostname] is not running  • Issued  • Issued. The private key was successfully retained.  • Post-process Failed: [Message indicating reason for failure generally from the CA]  • Pre-process failed: [Message indicating details of the failure]  • Revoked  • Step 'Keyfactor-Enroll' failed: [Message indicating details of the failure]  • Step 'Keyfactor-Revoke' failed: [Message indicating details of the failure]  • Step [custom step name] failed: [Message indicating details of the failure]  • Taken Under Submission. The certificate template requires manager approval, and is marked as pending.  • Workflow rejected by user with Id #.	
Definition	An array containing the w	orkflow definition. Workflow definition data includes:
	Name	Description
		A string indicating the Keyfactor Command reference GUID of the workflow definition.

Name	Description		
	Name	Description	
	DisplayName	A string indicating the display name defined for the workflow definition.	
	Version	An integer indicating the version number of the workflow definition.	
	WorkflowType	A string indicating the type of workflow definition. The currently supported types are:  • Enrollment • Revocation	
CurrentStepDisplayName	A string indicating the	display name defined for the workflow instance step.	
CurrentStepUniqueName		unique name defined for the workflow instance step. This value is os in a particular workflow definition. It is intended to be used as a EID.	
Title	InitiatingUserName (D	escription for the action taking place in the step, made up of the OMAIN\\username) followed by an indication of the type of action about the action. For example:	
	"KEYEXAMPLE\\jsmith is enrolling for a certificate with CN=apps-srvr14.keyexample.com."		
	Or  "KEYEXAMPLE\\ srvr12.keyexam	jsmith is revoking certificate with CN=apps- ple.com."	
LastModified	The instance is update	date and time on which the initiated instance was last updated. d each time a step in the workflow is completed, when signals are t accepts signals (e.g. a requires approval step), or when an restarted.	
StartDate	A string indicating the date and time when the instance was initiated.		
ReferenceId	A integer indicating the	e Keyfactor Command reference ID for the workflow instance.	

# 2.2.32.4 GET Workflow Instances My

The GET /Workflow/Instances/My method is used to retrieve the list of initiated workflows created by the user making the API request—as a result of enrolling for a certificate, for example, or revoking a certificate. This method returns HTTP 200 OK on a success with details about the workflow instances.



**Note:** If a workflow instance is initiated for a workflow definition that has more than one step requiring input (signals), a user can only provide that input (e.g. approve or deny a require approval request) at the step in the workflow instance where the workflow instance was suspended pending input. The user cannot jump ahead and provide input for future steps in the workflow that have not yet occurred.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature:

WorkflowInstances: ReadAll OR WorkflowInstances: ReadMy

Table 598: GET Workflow Instances My Input Parameters

Name	In	Description
queryString	Query	A string containing a query to limit the results (e.g. field1 -eq value1 AND field2 -gt value2). The default is to return all records. Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns for the same feature. For querying guidelines, refer to the Keyfactor Command Reference Guide: Using the Workflow Instances Search Feature. The query fields supported for this endpoint are:  • DefinitionId (workflow definition ID)  • Id (workflow instance GUID)  • InitiatingUserName (DOMAIN\\username)  • LastModified  • ReferenceId (workflow instance integer ID)  • StartDate  • Status  • Title  • WorkflowType
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>Id</i> .
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.

Table 599: GET Workflow Instances My Response Data

Name	Description	
Id	A string indicating the Keyfactor Command reference GUID of the workflow instance.	
Status	A string indicating the current status of the workflow instance. The possible statuses are:  CanceledForRestart  Complete Failed Rejected Running Suspended	
CurrentStepID	A string indicating the Keyfactor Command reference GUID of the workflow instance step.	
StatusMessage	A string indicating the current status message for the workflow instance. Possible status messages vary and may include:  • Access is denied  • Awaiting # more approval(s) from approval roles.  • Either the credentials are invalid, or the CA on [CA hostname] is not running  • Issued  • Issued. The private key was successfully retained.  • Post-process Failed: [Message indicating reason for failure generally from the CA]  • Pre-process failed: [Message indicating details of the failure]  • Revoked  • Step 'Keyfactor-Enroll' failed: [Message indicating details of the failure]  • Step [custom step name] failed: [Message indicating details of the failure]  • Taken Under Submission. The certificate template requires manager approval, and is marked as pending.  • Workflow rejected by user with Id #.	
Definition	An array containing the workflow definition. Workflow definition data includes:  Name  Description	
	Id A string indicating the Keyfactor Command reference GUID of the workflow definition.	

Name	Description		
	Name	Description	
	DisplayName	A string indicating the display name defined for the workflow definition.	
	Version	An integer indicating the version number of the workflow definition.	
	WorkflowType	A string indicating the type of workflow definition. The currently supported types are:  • Enrollment • Revocation	
CurrentStepDisplayName	A string indicating the	display name defined for the workflow instance step.	
CurrentStepUniqueName		unique name defined for the workflow instance step. This value is os in a particular workflow definition. It is intended to be used as a EID.	
Title	InitiatingUserName (D	escription for the action taking place in the step, made up of the OMAIN\\username) followed by an indication of the type of action about the action. For example:	
	"KEYEXAMPLE\\jsmith is enrolling for a certificate with CN=apps-srvr14.keyexample.com."		
	Or  "KEYEXAMPLE\\ srvr12.keyexam	jsmith is revoking certificate with CN=apps- ple.com."	
LastModified	The instance is update	date and time on which the initiated instance was last updated. d each time a step in the workflow is completed, when signals are t accepts signals (e.g. a requires approval step), or when an restarted.	
StartDate	A string indicating the date and time when the instance was initiated.		
ReferenceId	A integer indicating the	e Keyfactor Command reference ID for the workflow instance.	

# 2.2.32.5 GET Workflow Instances AssignedToMe

The GET /Workflow/Instances/AssignedToMe method is used to retrieve the list of initiated workflows awaiting input from the user making the API request. This method returns HTTP 200 OK on a success with details about the workflow instances.



**Note:** If a workflow instance is initiated for a workflow definition that has more than one step requiring input (signals), a user can only provide that input (e.g. approve or deny a require approval request) at the step in the workflow instance where the workflow instance was suspended pending input. The user cannot jump ahead and provide input for future steps in the workflow that have not yet occurred.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature:

WorkflowInstances: ReadAll OR

WorkflowInstances: ReadAssignedToMe

Table 600: GET Workflow Instances AssignedToMe Input Parameters

Name	In	Description
queryString	Query	A string containing a query to limit the results (e.g. field1 -eq value1 AND field2 -gt value2). The default is to return all records. Fields available for querying through the API for the most part match those that appear in the Keyfactor Command Management Portal search dropdowns for the same feature. For querying guidelines, refer to the Keyfactor Command Reference Guide: Using the Workflow Instances Search Feature. The query fields supported for this endpoint are:  • DefinitionId (workflow definition ID)  • Id (workflow instance GUID)  • InitiatingUserName (DOMAIN\\username)  • LastModified  • ReferenceId (workflow instance integer ID)  • StartDate  • Status  • Title  • WorkflowType
pageReturned	Query	An integer that specifies how many multiples of the returnLimit to skip and offset by before returning results, to enable paging. The default is 1.
returnLimit	Query	An integer that specifies how many results to return per page. The default is 50.
sortField	Query	A string containing the property by which the results should be sorted. Fields available for sorting through the API for the most part match those that appear as sortable columns in the Keyfactor Command Management Portal. The default sort field is <i>CurrentStepDisplayName</i> .
sortAscending	Query	An integer that sets the sort order on the returned results. A value of 0 sorts results in ascending order while a value of 1 sorts results in descending order. The default is ascending.

Table 601: GET Workflow Instances AssignedToMe Response Data

Name	Description
Id	A string indicating the Keyfactor Command reference GUID of the workflow instance.
Status	A string indicating the current status of the workflow instance. The possible statuses are:  CanceledForRestart  Complete  Failed  Rejected  Running  Suspended  Only instances with a Status of Suspended are returned using this method.
CurrentStepID	A string indicating the Keyfactor Command reference GUID of the workflow instance step.
StatusMessage	A string indicating the current status message for the workflow instance. Possible status messages vary and may include:  • Access is denied  • Awaiting # more approval(s) from approval roles.  • Either the credentials are invalid, or the CA on [CA hostname] is not running  • Issued  • Issued. The private key was successfully retained.  • Post-process Failed: [Message indicating reason for failure generally from the CA]  • Pre-process failed: [Message indicating details of the failure]  • Revoked  • Step 'Keyfactor-Enroll' failed: [Message indicating details of the failure]  • Step [Custom step name] failed: [Message indicating details of the failure]  • Taken Under Submission. The certificate template requires manager approval, and is marked as pending.  • Workflow rejected by user with Id #.  Only instances with a StatusMessage of Awaiting # more approval(s) from approval roles. are returned using this method.
Definition	An array containing the workflow definition. Workflow definition data includes:

Name	Description		
	Name	Description	
	Id	A string indicating the Keyfactor Command reference GUID of the workflow definition.	
	DisplayName	A string indicating the display name defined for the workflow definition.	
	Version	An integer indicating the version number of the workflow definition.	
	WorkflowType	A string indicating the type of workflow definition. The currently supported types are:  • Enrollment • Revocation	
CurrentStepDisplayName	A string indicating the display name defined for the workflow instance step.		
CurrentStepUniqueName		unique name defined for the workflow instance step. This value is os in a particular workflow definition. It is intended to be used as a PID.	
Title	A string indicating a description for the action taking place in the step, made up of <i>InitiatingUserName</i> (DOMAIN\\username) followed by an indication of the type of and a specific message about the action. For example:		
	"KEYEXAMPLE\\jsmith is enrolling for a certificate with CN=apps-srvr14.keyexample.com."		
	Or		
	"KEYEXAMPLE\\ srvr12.keyexam	jsmith is revoking certificate with CN=apps- ple.com."	
Last Modified	A string indicating the date and time on which the initiated instance was last updated. The instance is updated each time a step in the workflow is completed, when signals are received for a step that accepts signals (e.g. a requires approval step), or when an instance is stopped or restarted.		
StartDate	A string indicating the	date and time when the instance was initiated.	
ReferenceId	A integer indicating the	e Keyfactor Command reference ID for the workflow instance.	

# 2.2.32.6 POST Workflow Instances Instance Id Stop

The POST /Workflow/Instances/{instanceId}/Stop method is used to stop the workflow instance with the specified GUID, preventing it from continuing. This endpoint returns 204 with no content upon success.



**Note:** Only workflow instances with a Status of *Suspended* can be stopped.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: WorkflowInstances: *Manage* 

Table 602: POST Workflow Instances {instanceid} Stop Input Parameters

Name	In	Description
instanceId	Path	<b>Required</b> . A string indicating the Keyfactor Command reference GUID of the workflow instance to stop.
		Use the <i>GET /Workflow/Instances</i> method (see <u>GET Workflow Instances on page 1348</u> ) to retrieve a list of all the workflow instances to determine the GUID.

### 2.2.32.7 POST Workflow Instances Instance ID Signals

The POST /Workflow/Instances/{instanceId}/Signals method is used to input signals to the workflow instance with the specified GUID. This endpoint returns 204 with no content upon success.



**Note:** If a workflow instance is initiated for a workflow definition that has more than one step requiring input (signals), a user can only provide that input (e.g. approve or deny a require approval request) at the step in the workflow instance where the workflow instance was suspended pending input. The user cannot jump ahead and provide input for future steps in the workflow that have not yet occurred.



**Note:** A locking conflict may occur if two (or more) users attempt to provide input to a workflow instance (e.g. approve a request) at exactly the same time. If this happens, input from only one of the users will be reflected in the Management Portal, and the workflow instance will not be moved along to the next step if it should have been with input from the two users. The other input is still accepted, however, and there is a scheduled task that runs daily and attempts to continue all suspended workflows that may be eligible to continue but have not done so due to locking conflicts.



**Tip:** The following permissions (see <u>Security Overview</u>) are required to use this feature: The user executing the request must hold at least one security role ID configured in the workflow definition step for which signal data is being input.

Table 603: POST Workflow Instances {instanceid} Signals Input Parameters

Name	In	Description		
instanceId	Path	instance to which	ch to input a signal. Forkflow/Instances me	ethod (see GET Workflow Instances on page 1348) to ances to determine the GUID.
signal	signal Body		to continue based or	ta used at the point in the workflow step where the user input. These will vary depending on the type of ireApproval signal values are:
		Value	Description	
		SignalKey  Required. A string indicating the key for the signal. This is me the unique name for the step within the definition plus the type, separated by a period (UniqueName.SignalType). For a Approval step, the key input type will be ApprovalStatus, so SignalKey will look something like:		for the step within the definition plus the signal by a period (UniqueName.SignalType). For a Require e key input type will be ApprovalStatus, so the full
			Use the GET /Wo Workflow Definit details including t of the step for wh methods for work page 1348, GET V	rkflow/Definitions/{definitionid} method (see GET ions Definition ID on page 1238) to return workflow the workflow steps to determine the UniqueName nich you want to input a signal or one of the GET cflow instances (see GET Workflow Instances on Workflow Instances AssignedToMe on page 1354, or stances My on page 1351) to return the
		Data	information for th	ay containing key/value pairs providing the input ne signal. The key(s) will vary depending on the pproval signal data values are:
			Key	Value
			Approved	Required. A Boolean indicating whether the request is approved (true) or denied (false).
			Comment	A string containing a comment to associate with the signal. The maximum comment length is 500 characters.
		For example, to	approve a Require Ap	oproval step called <i>RequireApproval1</i> with a comment:
		{		

Name	In	Description
		"SignalKey": "RequireApproval1.ApprovalStatus",  "Data": {      "Approved": "True",      "Comment": "Here is my comment."  } }

#### 2.2.32.8 POST Workflow Instances Instance Id Restart

The POST /Workflow/Instances/{instanceId}/Restart method is used to restart the workflow instance with the specified GUID. This can be used either after it has reached a failed state and the failure has been corrected (e.g. a CA was not responding when an enrollment was attempted or a PowerShell script failed to run to completion) or midstream while it's still active but in a suspended state waiting for signals to introduce a new version of the workflow definition. The workflow instance will restart from the beginning. This endpoint returns 204 with no content upon success.



**Note:** Only workflow instances with a Status of *Failed* or *Suspended* can be restarted.



**Tip:** The following permissions (see Security Overview) are required to use this feature:

WorkflowInstances: *Manage* WorkflowDefinitions: *Read* 

Table 604: POST Workflow Instances (instanceid) Restart Input Parameters

Name	In	Description
instanceId	Path	Required. A string indicating the Keyfactor Command reference GUID of the workflow instance to restart.  Use the GET / Workflow / Instances method (see GET Workflow Instances on page 1348) to retrieve a list of all the workflow instances to determine the GUID.  Note: When you restart an instance, it will be issued a new instance ID.
version	Body	An integer indicating the version number of the workflow definition. If no version is specified, the workflow will be restarted using the most recently published version.

# 2.3 Classic API

The Keyfactor Classic API, also known as the CMS API, is the Web API that has been provided with Keyfactor Command for several product generations. The Classic API may be needed in your environment if you're upgrading and have written API applications using the Classic API. If you're new to building an API application to work with

Keyfactor Command, Keyfactor strongly recommends that you use the newer Keyfactor API (see <u>Keyfactor API on page 7</u>).

# 2.3.1 Security Role Overview

In order to use the Classic API, certain security role permissions must be granted to the identity used by the client to authenticate to the API. Specifically, the user must have the *API Read* permission to make any requests. Beyond this, different API endpoints have different requirements (see <u>Classic API Security Role Requirements below</u>).

Where the table indicates that *Certificate Store Management* permissions are required, this can either be global permissions to all certificate stores or permissions granted to the specific certificate store using certificate store container security. Likewise, where *Certificates* permissions are required, this can either be global certificate permissions on all certificates or permissions granted to a specific certificate or set of certificates using certificate collection security. See the *Keyfactor Command Reference Guide* for more information about container and collection security.

Table 605: Classic API Security Role Requirements

Endpoint	Security Role Permissions
ApiApp/1/GetApiApps	System Settings: Read
ApiApp/1/AddApiApp	System Settings: Modify
ApiApp/1/EditApiApp	System Settings: Modify
ApiApp/1/DeleteApiApp	System Settings: Modify
CertEnroll/1/Pkcs10	None
CertEnroll/1/Pkcs12	None
CertEnroll/1/Templates	None
CertEnroll/1/Token	None
CertEnroll/2/Pkcs10	None
CertEnroll/2/Pkcs12	None
CertEnroll/2/Templates	None
CertEnroll/2/Token	None
CertEnroll/3/Pkcs10	None
CertEnroll/3/Pkcs12	None
CertEnroll/3/Renew	Certificate Store Management: Read and Schedule

Endpoint	Security Role Permissions
CertEnroll/3/Templates	None
Certificates/1/Metafield	Certificates: Modify and Certificate Metadata Types: Read
Certificates/2/Import	Certificates: Import
Certificates/3/Contents	Certificates: Read
Certificates/3/Count	Certificates: Read
Certificates/3/PublishCRL	PKI Management: Modify
Certificates/3/Recover	Certificates: Recover
Certificates/3/Revoke	Certificates: Revoke
Certificates/3/Search	Certificates: Read
Certstore/1/AddCert	Certificate Store Management: Read and Schedule, and Certificates: Read
Certstore/1/AddCertStore	Certificate Store Management: Modify
Certstore/1/AddCertStoreServer	Certificate Store Management: Modify
Certstore/1/AddPFX	Certificate Store Management: Read and Schedule
Certstore/1/CreateJKS	Certificate Store Management: Modify
Certstore/1/EditCertStore	Certificate Store Management: Modify
Certstore/1/EditCertStoreServer	Certificate Store Management: Modify
Certstore/1/Inventory	Certificate Store Management: Read
Certstore/1/Keystores	Certificate Store Management: Read
Certstore/1/Remove	Certificate Store Management: Schedule and Certificates: Read
Certstore/1/ScheduleInventory	Certificate Store Management: Modify
Metadata/2/Compare	Certificates: Read and Certificate Metadata Types: Read
Metadata/2/Get	Certificates: Read and Certificate Metadata Types: Read
Metadata/2/Set	Certificates: Modify and

Endpoint	Security Role Permissions
	Certificate Metadata Types: Read
Metadata/3/Get	Certificates: Read and Certificate Metadata Types: Read
Metadata/3/GetDefinition	Certificate Metadata Types: Read
Metadata/3/Set	Certificates: Modify and Certificate Metadata Types: Read
Security/1/GetIdentities	Security Settings: Read
Security/1/AddIdentity	Security Settings: Modify
Security/1/DeleteIdentity	Security Settings: Modify
Security/1/GetRoles	Security Settings: Read
Security/1/AddRole	Security Settings: Modify
Security/1/EditRole	Security Settings: Modify
Security/1/DeleteRole	Security Settings: Modify
SSL/1/AddEndpoint	SSL Management: Modify
SSL/1/AddEndpointGroup	SSL Management: Modify
SSL/1/Agents	SSL Management: Read
SSL/1/EndpointGroups	SSL Management: Read
Workflow/1/ApproveRequest	Workflow: Read and Participate
Workflow/1/DenyRequest	Workflow: Read and Participate
Workflow/1/PendingList	Workflow: Read and Participate
Status	None
vSCEP	Configured through the Keyfactor Command Configuration Wizard or through the Application Settings page in the Keyfactor Command Management Portal.

# 2.3.2 ApiApp

The ApiApp component of the Keyfactor Web APIs includes all methods necessary to programmatically add, edit, get and delete API Applications. The complete set of endpoints is shown in 2.3.2 ApiApp.

Table 606: ApiApp Endpoints

Endpoint	Method	Description
/1/GetApiApps	GET	Returns a list of the API applications
/1/AddApiApp	POST	Add an API application to Keyfactor Command
/1/EditApiApp	POST	Edit an API application in Keyfactor Command
/1/DeleteApiApp	POST	Deletes and API application from Keyfactor Command

#### 2.3.2.1 ApiAPP GetApiApps

The GET GetApiApps endpoint returns a list of all API Applications defined in Keyfactor Command with the Id, Name, Key, Secret, CAId, CAConfiguration, TemplateId, TemplateName, TemplateForest and whether the Application is Enabled or not. No parameters or extra headers are required for this method.

#### **Example Request**

GET http://<host>/CMSApi/ApiApp/1/GetApiApps

#### Example Response

Status Code: 200

```
[
    "Id": "<Id>",
    "Name": "<name>",
    "Key": "<hexadecimal key>",
    "Secret": "<hexadecimal secret>",
    "Enabled": "True",
    "CAId": "<CA Id>",
    "CAConfiguration": "<CA Host Name>\\<CA Logical Name>",
    "TemplateId": "<Template Id>",
    "TemplateName": "<Template Common Name>",
    "TemplateForest": "<Template Forest>"
}
```

# 2.3.2.2 ApiApp AddApiApp

The POST AddApiApp endpoint adds an API Application to Keyfactor Command. It returns the Id of the newly added Application. Table 8 - AddApiApp Parameters shows the parameters that are used for the creation of API

#### Applications through the Keyfactor Web APIs.

Table 607: AddApiApp Parameters

Parameter Name	Parameter Description
Name	The name of the API Application. This parameter is required.
Key	The Key used for the API Application. This parameter is required.
Secret	The Secret used for the API Application. This parameter is required.
Enabled	The Enabled parameter tells whether the API Application is enabled or not. This parameter is optional.
CA	The CA parameter sets the CA for the API Application. The format used for this parameter is HostName\\LogicalName. This parameter is optional.
Template	The Template parameter sets the template that is used with the API Application. This should be the template short name. This parameter is optional.

# **Example Request**

POST http://<host>/CMSApi/ApiApp/1/AddApiApp HTTP/1.1

```
"Name": "<Name>",
    "Key": "<hexadecimal key>",
    "Secret": "<hexadecimal secret>",
    "Enabled": true,
    "CA": "<CA Host Name>\\<CA Logical Name>",
    "Template": "<Template Common Name>"
}
```

## **Example Response**

Status Code: 200

```
{
    "Id": <Id>
}
```

## 2.3.2.3 ApiApp EditApiApp

The POST EditApiApp endpoint allows certain aspects of an API Application definition to be updated. The only aspect of the API Application that cannot be updated is the Id. The response has the same elements as the GetApiApps call except for a single Api Application. Table 9 – EditApiApp Request Parameters holds the Parameters for the request.

Table 608: AddApiApp Parameters

Parameter Name	Parameter Description
Id	The Id of the API Application that is to be updated. This parameter is required.
Name	The name that the API Application will be updated to. This parameter is optional.
Key	The Key that the API Application will be updated to. This parameter is optional.
Secret	The Secret that the API Application will be updated to. This parameter is optional.
Enabled	The Enabled state the API Application will be updated to. This parameter is optional.
CAId	The Id of the Certification Authority the API Application will be updated to. This is an alternative to CaConfiguration. This parameter is optional.
CaConfiguration	The CA Configuration the API Application will be updated to. The format for the Configuration is Host.Name\\Logical-Name. This is an alternative to CAId. This parameter is optional.
TemplateId	The Id of the Template that the API Application will be updated to. This is an alternative to TemplateName. This parameter is optional.
TemplateName	The Name of the Template the API Application will be updated to. The name of the template should be the short name. This is an alternative to Template Id. This parameter is optional.

# **Example Request**

POST http://<host>/CMSApi/ApiApp/1/EditApiApp

```
"Id": <Id>,
    "Name": "<Name>",
    "Key": "<hexadecimal key>",
    "Secret": "<hexadecimal secret>",
    "Enabled": true,
    "CAId": <CA Id>,
    "TemplateName": "<Template Common Name>"
}
```

# **Example Response**

Status Code: 200

```
"Id": "<Id>",
    "Name": "<Name>",
    "Key": "<hexadecimal key>",
    "Secret": "<hexadecimal secret>",
    "Enabled": "True",
    "CAId": "<CA Id>",
    "CAConfiguration": "<CA Host Name>\\<CA Logical Name",
    "TemplateId": "<Template Id>",
    "TemplateName": "<Template Common Name>",
    "TemplateForest": " <Template Forest>"
}
```

## 2.3.2.4 ApiApp DeleteApiApp

The POST DeleteApiApp endpoint removes an API Application from Keyfactor Command. The POST request must contain a JSON string containing the Identity Id. This method returns a 200 a message stating the API App was deleted successfully.

#### Example Request

POST http://<host>/CMSApi/ApiApp/1/DeleteApiApp HTTP/1.1

```
{
    "Id": <Id>
}
```

#### **Example Response**

Status Code: 200

```
{
    "Message": "The Api Application was deleted"
}
```

### 2.3.3 CertEnroll

The CertEnroll component of the Keyfactor Web APIs includes all methods necessary to programmatically request and obtain a certificate. Keyfactor Command supports enrollment through Microsoft Active Directory Certificate Services Certificate Authorities, both in the local Active Directory forest and, by using Keyfactor Gateways, in

remote domains and a variety of public CA vendors. Contact your Keyfactor representative for more information about Keyfactor Gateways, including the most recent list of supported Certificate Authorities.) The CertEnroll component allows enrollment through all CAs configured in your Keyfactor Command environment. The API supports two variations of enrollment. The more secure variant allows the client application to generate the certificate's public/private keypair on the device issuing the request, so that the private key is never transmitted or stored anywhere else. This model is useful in scenarios where the key doesn't need to be archived or exported. The second model lets the server generate the keys, returning the resulting cert and keypair as a PFX/PKCS12 blob. This method is suitable when the key does need to be exported or archived, or when the client is not capable of generating a keypair itself.

There are three versions of the CertEnroll API, each with separate methods for the two enrollment variations, and up to three auxiliary methods to help formulate a successful enrollment request or perform related operations. The complete set of endpoints is given here in Table 609: CertEnroll Endpoints.

Table 609: CertEnroll Endpoints

Endpoint	Method	Description
/1/Status	GET	A synonym for GET /Status, included on this path for backwards-compatibility
/1/Templates	GET	Return a list of certificate templates available to this API application
/1/Token	GET	Retrieve a temporary authentication token to be used with an enrollment request
/1/Pkcs10	POST	Obtain a certificate by providing a CSR, using a key generated by the client
/1/Pkcs12	POST	Obtain a certificate and private key from Keyfactor Command by providing certain certificate attributes
/2/Status	GET	A synonym for GET /Status, included on this path for backwards-compatibility
/2/Templates	GET	Return a list of certificate templates available to this API application
/2/Token	GET	Retrieve a temporary authentication token to be used with an enrollment request
/2/Pkcs10	POST	Obtain a certificate by providing a CSR, using a key generated by the client
/2/Pkcs12	POST	Obtain a certificate and private key from Keyfactor Command by providing certain certificate attributes
/3/Templates	GET	Return a list of certificate templates available to this API application
/3/Renew	POST	Obtain a new certificate based on content from an existing certificate in Keyfactor Command
/3/Pkcs10	POST	Obtain a certificate by providing a CSR, using a key generated by the client
/3/Pkcs12	POST	Obtain a certificate and private key from Keyfactor Command by providing certain certificate attributes

For historic reasons, slight differences in the template format necessitated differentiating the methods into a "version 1" and "version 2", with the same set of methods. Then, to allow simplification of the built-in security mechanisms, version 3 of these methods was introduced. In most cases, applications should use the CertEnrollv3 methods if taking advantage of this security mechanism (as described below) and CertEnrollv2 if not.

This Keyfactor Command API component supports an optional application authentication feature to restrict the API to selected third-party software clients. It uses a public application key and a private application secret. The application key identifies the API client application to the server and is sent as part of the HTTP headers for all enrollment endpoints. The application secret is used to compute an HMAC-SHA1 signature that is sent in an HTTP header for certain endpoints. The combination of the application key and the computed signature allows Keyfactor Command to verify the origin and the authenticity of the enrollment request. Although Basic authentication credentials are required in order to connect to the API, this allows a single user to configure different applications for different templates and have the restrictions enforced. The secret allows secure authentication and prevents attackers from attempting to replay successful enrollment requests. The calculation of this HMAC signature differs between v2 and v3 of the API. The different computations are covered in Table 610: CertEnroll Security Headers.

Another difference between v1, v2 and v3 is that v3 will import the certificate immediately and sync the row from the CA database after the certificate has been issued, whereas v1 and v2 require a manual import of the certificate after it has been issued.

Each application should have its own unique application key and secret pair embedded in the application, as well as in secure storage on the server. These keys can be registered in the API Applications section of the System Settings menu on the Keyfactor Command Management Portal. Giving each application its own key and secret pair provides these advantages:

- An application can be restricted to request specific certificate templates and from specific CAs.
- One application key can be disabled while leaving other application keys enabled. This allows insecure or compromised versions of an application to be disabled without affecting up-to-date users.

Table 610: CertEnroll Security Headers

Header Name	Header Value
X-CSS-CMS- AppKey	This header contains the application key assigned to this particular application. This header is a base-64-encoded string created from the key's byte sequence, and not the ASCII/UTF-8 hexadecimal representation of that byte sequence. For example, if the key is entered in the API Applications section as "03030303030303030303FF", this represents the bit pattern "0000011000000110000001100000011000000110000
X-CSS-CMS- Token	This header field contains the temporary token that was previously obtained from the GET Token method. Like the application key, this header is a base-64-encoded string created from the binary form of

Header Name	Header Value
	the token, and not the ASCII/UTF-8 hexadecimal representation actually returned by the response to the GET Token. This is required for the v1 and v2 endpoints only.
X-CSS-CMS- Signature	This header field contains an HMAC-SHA-1 message signature computed from the request. Producing this signature proves that the client has access to the application secret value that is also present in the server's configuration, that the message has been transmitted without modification, and that transmission is recent. This is required for all enrollment endpoints, although this requirement can be disabled through the application settings in the management console. The computation of this signature differs between versions; all versions are a base-64 encoding of a SHA-1 hash, but the content to be hashed varies. In general, v1 and v2 GET methods hash the URL and Token; v1 and v2 POST methods hash the URL, Token, and request body; v3 GET methods do not require a signature; and v3 POST methods hash the request body only. The computation of HMAC signatures is significantly easier for v3 methods. Sample Python code is included in Table 611: CertEnroll HMAC computations in Python for each computation type.

Table 611: CertEnroll HMAC computations in Python

Endpoints	Signature
GET Templates (v1 and v2)	token = json.loads(GET_Token_ResponseBody)["SessionTokenValue"]  URLPath = "/CMSApi/CertEnroll/2/Templates"  requestDataString = URLPath + token;  appSecretBytes = appSecretString.decode("hex")  signature = hmac.new(appSecretBytes, requestDataString, hashlib.sha1).hexdigest();  headers["X-CSS-CMS-Signature"] = base64.b64encode(signature.decode("hex"));
POST /1/Pkcs10, /1/Pkcs12, /2/Pkcs10, /2/Pkcs12	token = json.loads(GET_Token_ResponseBody)["SessionTokenValue"]  URLPath = "/CMSApi/CertEnroll/2/Pkcs12"  body='{"Flags":0,"TemplateName":"User","Pkcs12Password":"lily1234","SubjectNameAttributes":null}'  Note: For these methods, the body must be formatted exactly as above, as far as parameter order, capitalization, and whitespace. This is one reason v3 signatures are easier to use.  requestDataString = URLPath + token + body
	<pre>appSecretBytes = appSecretString.decode("hex") signature = hmac.new(appSecretBytes, requestDataString, hashlib.sha1).hexdigest(); headers["X-CSS-CMS-Signature"] = base64.b64encode(signature.decode("hex"));</pre>
POST /3/Pkcs10 and /3/Pkcs12	data='{"Flags":0,"TemplateName":"User","Pkcs12Password":"lily1234","SubjectNameAttributes":null}' body = '{"Timestamp": "' + datetime.datetime.utcnow().isoformat()+ '", "Request": ' + data + '}'
	Note: For these methods, the request can be formatted in any equivalent json format without

Endpoints	Signature
	regard to capitalization, whitespace, or order of elements. This is one reason v3 signatures are easier to use.
	<pre>appSecretBytes = appSecretString.decode("hex") signature = hmac.new(appSecretBytes, body, hashlib.sha1).hexdigest(); headers["X-CSS-CMS-Signature"] = base64.b64encode(signature.decode("hex"));</pre>

#### 2.3.3.1 CertEnroll Token

The GET Token request returns a session token that is used in subsequent calls to v1 or v2 enrollment endpoints to authenticate the software client to the server. By default, the token has an expiration time of 10 minutes (configurable in the Keyfactor Command Management Portal Application Settings). Using a token after it is expired will result in an error.

#### **Example Request**

GET http://<host>/CMSApi/CertEnroll/1/Token HTTP/1.1

#### **Example Response**

```
{
    "SessionTokenValue":"F715F307DBE0DD5A9894260DBF0643C042173698"
}
```

# 2.3.3.2 CertEnroll Templates

The Templates methods return the list of templates configured and enabled for use by the application (identified by the X-CSS-CMS-AppKey HTTP header). The set of fields returned for a template differs from version 1 to version 2, but versions 2 and 3 return the same content. No parameters are required for these requests—only the app key in the header, formatted as described in <u>Table 610: CertEnroll Security Headers</u>—but the response formats are given in Table 612: GET /2/Templates and /3/Templates Response Body.



**Important:** As of release 9.0 of the Classic API, version 1 of CertEnroll/1/Templates has been removed from the product and is no longer supported.

Table 612: GET /2/Templates and /3/Templates Response Body

Parameter Name	Parameter Value
DisplayName	Long/Friendly name of the template.

Parameter Name	Parameter Value
CommonName	Short name of the template.
Oid	Object Identifier for this template.
KeySize	String representation of Key Size in bits, or Unknown.

#### **Example Request**

GET http://<host>/CMSApi/CertEnroll/3/Templates HTTP/1.1

X-CSS-CMS-AppKey: AAAAAAAAAAAA==

X-CSS-CMS-Token: A0sTeMd9PT6XPw2BdqWb9PkErQk= [Version 2 only]

#### **Example Response**

Version 2 and 3

#### 2.3.3.3 CertEnroll Pkcs10

The PKCS10 method provides enrollment with on-device key generation. The basic workflow with on-device key generation is:

- 1. Client application retrieves list of available certificate templates using the Keyfactor Command API.
- 2. Client generates a public/private key pair based on the key size requirements from the selected template.
- 3. Client creates a PKCS10 Certificate Signing Request (CSR) using the keypair and template attributes.
- 4. Client sends the PKCS10 request and selected template name to the API which submits the request to the enterprise CA and returns the certificates received from the CA to the software client.

If successful, the response from the CA will be a PKCS#7 message containing the issued certificate and (optionally) the certificate chain. Once the response is received, a software client can construct a PKCS12 package with the previously generated key pair and the issued certificates, import the keys and certificates into an application-specific store, such as Apple's KeyChain Services or a Java Keystore, or perform any other processing required. The

flow (for versions 1 and 2) is shown in <u>Figure 6: Pkcs#10-Based Enrollment Request</u>. The version 3 flow is identical except that a token is not required for enrollment, so the initial exchange with the *token* endpoint is not needed. The difference in version 3 is explained in <u>Table 610: CertEnroll Security Headers</u>.




Figure 6: Pkcs#10-Based Enrollment Request

The PKCS10-based method is the most secure way to enroll for certificates with Keyfactor Command. The PKCS10 method utilizes on-device key generation instead of the server-based key generation used for the PKCS12 method. The PKCS10 method also requires the use of a certificate template that populates the subject and/or subject alternate name from Active Directory. This reliance on certificate templates allows Keyfactor Command to utilize the security mechanisms built into the Microsoft CA Services.

To use this method, the following configuration should be present on the Keyfactor Command server and in its domain:

- IIS application pool configured with a non-administrator domain member account
- · API Application with valid key, secret, template, and CA

- Certificate template configured to:
  - Populate subject and/or subject alternate name (SAN) fields from AD as needed. While the PKCS#10
    request may contain data for these fields, the selected certificate template may replace those values with
    information from Active Directory.
  - Not allow private key exportation
  - ° Grant enroll permission to all users who may enroll for a certificate

The request parameters that should be sent for version 1 and 2 of the enrollment are listed in <u>Table 613: POST /1/Pkcs10 and /2/Pkcs10 Request Body</u> and for version 3 in <u>Table 614: POST /3/Pkcs10 Request Body</u>, while the response format (for all versions) is given in Table 615: POST /\*/Pkcs10 Response Body:

Table 613: POST /1/Pkcs10 and /2/Pkcs10 Request Body

Parameter Name	Parameter Value
Flags	Bit flags that determine the enrollment behavior. At this time, the only available bit flag is:  • 0x01 = Include certificate only (default is to return certificate + trust chain)
TemplateName	Name of the certificate template to use for enrollment. This name must match one of the template names configured for this application key in the API Applications page.
Pkcs10Request	Contains a base-64-encoded PKCS#10 request generated on the device. The key sizes used to generate the PKCS#10 request must match the key size specified in the certificate template.
MetadataList	A list of key value pairs for each metadata item that is to be set on the issued certificate in Keyfactor Command. This parameter is optional.

In version 3 of the API, the fields used by versions 1 and 2 are wrapped in an outer envelope and sent along with a timestamp. By including this timestamp in the request body and using this as part of the HMAC signature computation, the need for a current API access token is eliminated without reducing security. The request structure for version 3 of this endpoint is shown in Table 614: POST /3/Pkcs10 Request Body:

Table 614: POST /3/Pkcs10 Request Body

Parameter Name	Parameter Value
Timestamp	ISO 8601 Timestamp in UTC timezone, e.g. "2018-11-22T20:41:08.440Z"
Request	JSON object in the same format as a version 1/2 Pkcs10 enrollment request (see <u>Table 613: POST /1/Pkcs10 and /2/Pkcs10 Request Body</u> ).

Table 615: POST /\*/Pkcs10 Response Body

Parameter Name	Parameter Value
SerialNumber	String containing the hexadecimal serial number of the issued certificate.
IssuerDN	Distinguished Name of the certificate's issuer.
Thumbprint	Thumbprint of the issued certificate.
CMSID	Identifier for this certificate in Keyfactor Command. Can be used to identify the cert in future API requests.
CMSRequestId	Identifier for the certificate request in Keyfactor Command. Can be used if certificate is pending issuance.
Certificates	If the CERT_ONLY flag (0x01) is set in the request, then the response is a base-64 encoding of the DER-encoded cert.  If the CERT_ONLY flag is not set, the response is a base-64 encoding of a PKCS7 containing the cert and its chain.
RequestDisposition	Value returned by the CA in response to this certificate request
DispositionMessage	Message accompanying the disposition value returned by the CA

# **Example Request**

Versions 1 and 2

POST http://<host>/CMSApi/CertEnroll/1/Pkcs10 HTTP/1.1

# **Example Request**

Version 3

```
{
    "Timestamp" : "2017-12-18T19:56:12.365Z",
    "Request": {
```

### **Example Response**

```
"SerialNumber": "2684C97728678A944A67C03E7192785B",
    "IssuerDN": "CN=CorpCA1, DC=keyexample, DC=com",
    "Thumbprint": "FDB3A0F4ADCF9C39A2BB639898EE1670DFDBF5BB",
    "CMSID": 5,
    "CMSRequestId": 3,
    "Certificates": <PEM-encoded certificates>
    "RequestDisposition": "Issued",
    "DispositionMessage": ""
}
```

#### 2.3.3.4 CertEnroll Pkcs12

The PCKS12-based POST enrolls for a certificate with a server-generated private key. It generates a PKCS#12 file that is protected by the password specified in the request and returns a base-64-encoded PKCS#12 response if successful.

The basic workflow with server-based key generation is:

- 1. Third-party software client retrieves a list of available certificate templates using the Keyfactor Command API.
- 2. Third-party software client sends the selected template name and a password to the API. The Keyfactor Command component will:
  - a. Generate the RSA key pair.
  - b. Submit the request to the CA configured for the API application and retrieve the issued certificate.
  - c. Create a PKCS12 blob with the private key, the issued certificate, and the certificate trust chain using the supplied password.
  - d. Return the PKCS12 blob to the API client.




Figure 7: Pkcs#12-Based Enrollment Request

As with the Pkcs10 methods, versions 1 and 2 use the flow shown in Figure 7: Pkcs#12-Based Enrollment Request, while version 3 does not require a token and uses a timestamp instead. For these methods, keys are generated on the server and returned to the client in the form of a P12 (PFX) file. This requires that the certificate's private key is transmitted over the network and temporarily stored on the server, which can present a security risk. For this reason, Keyfactor recommends that clients which are capable of generating their own keypair and submitting a CSR use the Pkcs10 enrollment. When clients do not have the capability or the processing power to do this, the Pkcs12 offers an alternate method. Certificate templates are used on the Microsoft CA; however, the private key must be marked as exportable in the template.

To use this method, the following configuration needs to be present on the Keyfactor Command server:

- Certificate template configured to:
  - Allow the requestor (Keyfactor Command) to supply the subject and subject alternate name details
  - ° Allow the private key to be exported
  - Grant enroll permission to the Keyfactor Command application pool user—no other user needs enroll
    permissions for this template and for best security, none should be granted to other users
- · IIS application pool user configured to be a non-administrative domain member account
- The Load User Profile option configured to true under the advanced settings for the application pool

The format of a Pkcs12 request is given in <u>Table 616: POST /1/Pkcs12 and /2/Pkcs12 Request Body</u> and <u>Table 617: POST /3/Pkcs12 Request Body</u>, while the response format is given in <u>Table 618: POST /\*/Pkcs12 Response Body</u>.

Table 616: POST /1/Pkcs12 and /2/Pkcs12 Request Body

Parameter Name	Parameter Value	
Flags	Bit flags that determine the enrollment flags so this value should be set to "0"	t behavior. At this time, there are no available bit (zero).
TemplateName	Name of the certificate template used allowed template names.	for enrollment. This name must match- one of the
Pkcs12Password	PKCS12 password. Must be 8 or more of	characters.
SubjectNameAttributes	are not provided, Keyfactor Command the requester's AD account. If no attrib include this attribute and set the value similar, SubjectNameAttributes are NO are supplied separately in the SubjectA	ay of key/value pairs or as a dictionary in the form
SubjectAltNameElements	to use when generating the certificate'	at represent the elements for Keyfactor Command s subject alternative name. This parameter is ubject alternative name flag (in string form), asso- alternative name flags are as follows:
	Value	Definition
	0	None
	1	UPN
	2	RFC822
	3	DNS
	4	IP Address
	5	URI
	6	Email
	7	GUID
	8	Registered Id
	9	Directory name
MetadataList	A list of key value pairs for each metad in Keyfactor Command. This parameter	ata item that is to be set on the issued certificate r is optional.

Table 617: POST /3/Pkcs12 Request Body

Parameter Name	Parameter Value
Timestamp	ISO 8601 Timestamp, e.g. "2018-11-22T20:41:08.440000"
Request	JSON object in the same format as a version 1/2 Pkcs10 enrollment request (see <u>Table 616: POST /1/Pkcs12 and /2/Pkcs12 Request Body</u> ).

Table 618: POST /\*/Pkcs12 Response Body

Parameter Name	Parameter Value
SerialNumber	String containing the hexadecimal serial number of the issued certificate.
IssuerDN	Distinguished Name of the certificate's issuer.
Thumbprint	Thumbprint of the issued certificate.
CMSID	Identifier for this certificate in Keyfactor Command. Can be used to identify the cert in future API requests.
CMSRequestId	Identifier for the certificate request in Keyfactor Command. Can be used if certificate is pending issuance.
Pkcs12Blob	Base-64-encoded representation of the Pkcs#12 certificate that was issued, if any.
RequestDisposition	Value returned by the CA in response to this certificate request.
DispositionMessage	Message accompanying the disposition value returned by the CA.

This method allows additional attributes to be included in the certificate's subject name. A common use for this is the inclusion of a device class identifier, such as "iPhone 4S". On the Keyfactor Command server there is a configuration property to define the format of the subject name. An example is:

"CN={cn},OU=Device Model {deviceType}"

For each of the tokens given in {brackets}, Keyfactor Command will replace the value with the corresponding value in the SubjectNameAttributes field of the request, if present. If no value is provided, it will attempt to look up the value in the requester's AD account. In this example, Keyfactor Command might replace the string "{deviceType}" with attribute value "deviceType" supplied in the SubjectNameAttributes key-value-pair structure inside of the JSON request from the API client, and (if "cn" is not specified in the request) the "{cn}" string would be replaced with the value of the "cn" property from the user's Active Directory properties. If a matching token cannot be found either in the request or in AD, no value is substituted.

### **Example Request**

Versions 1 and 2

POST http://<host>/CMSApi/CertEnroll/2/Pkcs12 HTTP/1.1

```
{
    "Flags":0,
    "Pkcs12Password": "12341234",
    "TemplateName": "User",
    "SubjectNameAttributes": {"deviceid":"iPad"}]
}
```

## **Example Request**

Version 3

POST http://<host>/CMSApi/CertEnroll/3/Pkcs12 HTTP/1.1

## **Example Response**

Status Code: 200

```
"SerialNumber": "690003CC096AC71023934747AA00000003CC09",

"IssuerDN": "CN=jdk-CA1, DC=jdk, DC=com",

"Thumbprint": "04259811B3BC522093532FBA5F4C1FA3C0969A87",

"CMSID": 8,

"CMSRequestId": 6,

"Pkcs12Blob": <base64-encoded PKCS#12>,

"RequestDisposition": "Issued",
```

```
"DispositionMessage": ""
}
```

#### 2.3.3.5 CertEnroll Renew

Certificate renewal in Keyfactor Command allows a certificate to be issued based on data from an existing certificate. Some configurations, such as the issuing CA and template, can be made to differ between the original certificate and the renewed one. At renewal time, the new certificate can also be automatically delivered to different certificate stores managed by Keyfactor Command Agents, replacing the old certificates. This provides an easy mechanism to quickly replace expiring or compromised certificates, migrate deployed certificates from one PKI to another, or replace certificates with similar certificates using more secure cryptographic algorithms. The Renew Web API method, along with the web console and expiration alert handlers, allows access to this renewal functionality. The structure of a renew request is given Table 619: POST /3/Renew Request Body, and the response in Table 620: POST /3/Renew Response Body.

Table 619: POST /3/Renew Request Body

Parameter Name	Parameter Value
Lookup	Description of the certificate to be renewed. See <u>Table 4: Classic API Certificate Lookup Structure</u> .
CertStores	Array of GUIDs listing the certificate stores where the new certificate should be delivered. This must be a subset of the CertStores containing the original certificate.
Template	Certificate template to be used for the new certificate request.
CAConfiguration	Certificate authority for the new certificate, in the form "hostname\\logical name" (double-back-slash required for JSON formatting).
Metadata	Optional dictionary of metadata fields and values to be associated with the newly issued certificate.
CustomPassword	Password to protect the private key of the new certificate. This field is optional and Keyfactor Command will use a randomly assigned password if this is not set.

Table 620: POST /3/Renew Response Body

Parameter Name	Parameter Value
Thumbprint	Thumbprint of the issued certificate.
CMSRequestId	Identifier for the certificate request in Keyfactor Command, if certificate is pending issuance.
RequestDisposition	Value returned by the CA in response to this certificate request.

Parameter Name	Parameter Value	
DispositionMessage	Message accompanying the disposition value returned by the CA.	
RenewedCertStores	List of certstores that had a certificate addition job scheduled successfully. The certstores will be listed in the format " <store machine="">-<store path="">".</store></store>	

## **Example Request**

POST http://<host>/CMSApi/CertEnroll/3/Renew HTTP/1.1

```
{
    "Lookup": {"Type" : "CMSID", "CMSID" : 7},
    "CertStores": ["<Guid&gt;"],
    "Template": "UserServer",
    "CAConfiguration" : "CA1.jdk.com\\jdk-CA1",
    "Metadata":{"Email-Contact":"a.b@example.com"}
}
```

#### **Example Response**

```
{
    "RenewedCertStores": ["192.168.41.171-/home/pi/cherry/cherrystore"],
    "Thumbprint": "46CCE7023bce5c434f4206b74473fd614df56218",
    "CMSRequestId": 0,
    "RequestDisposition": "Issued",
    "DispositionMessage": "The certificate renewal has been completed successfully. Agent jobs to install the new certificate have been created."
}
```

# 2.3.4 Certificates

The Certificates component of the Web API supports certificate lifecycle and management tasks apart from enrollment. The complete set of methods in this component is given in <u>Table 621: Certificates Endpoints</u>.

Table 621: Certificates Endpoints

Endpoint	Method	Description
/3/Contents	POST	Return the certificate contents in PEM format
/3/Count	POST	Return the number of certificates in the Keyfactor Command database matching a given search query

Endpoint	Method	Description	
/1/Metafield	POST	Associate a metadata value with a certificate in the Keyfactor Command database.	
/2/Import	POST	Add an existing certificate into the Keyfactor Command database.	
/3/Revoke	POST	Revoke a given certificate.	
/3/Recover	POST	Recover a given certificate	
/3/PublishCRL	POST	Request a CA to publish a new CRL	
/3/Search	POST	Return the full set of certificates in the Keyfactor Command database matching a given search query	

#### 2.3.4.1 Certificates Metafield

The metafield POST method is used to import individual certificate metadata field values into Keyfactor Command. This method offers limited functionality and security measures compared to the Metadata v2 and v3 methods described in the Metadata section (see <a href="Metadata on page 1414">Metadata on page 1414</a>), but is included for backward-compatibility. A JSON string must be submitted with the POST request containing the data shown in <a href="Table 622: POST /1/Metafield Request Body">Table 622: POST /1/Metafield Request Body</a>. This method returns HTTP 200 OK with message body "true" on success or an appropriate 4xx status with an accompanying error message in the body on failure.

Table 622: POST /1/Metafield Request Body

Parameter Name	Parameter Value		
CertificateId	The Keyfactor Command database row identifier associated with the existing certificate.  Many times this will be the certificate id returned by the import API call.		
MetadataFieldTypeName	The string name of the metadata field type for which the value is provided.		
Value	The metadata field value to be associated with the provided certificate identifier.		

# **Example Request**

POST http://<host>/CMSApi/Certificates/1/Metafield HTTP/1.1

```
{
    "CertificateId": 1,
    "MetadataFieldTypeName": "Email-Contact",
```

```
"Value": "support@example.com"
}
```

# 2.3.4.2 Certificates Import

The certificate import POST method is used to import a certificate (.cer) file into Keyfactor Command while also allowing the simultaneous definition of metadata values for the imported certificate. The POST request must contain a JSON string containing the certificate and any metadata items that should be associated with the certificate but does not require the content-disposition or multi-part form found in version 1. This method returns HTTP 200 OK with message body "true" on success or an appropriate 4xx status with an accompanying error message in the body on failure.



**Important:** Support for version 1 of the Classic API certificate import method (Certificates/1/Import) will end in an upcoming release of the product. All applications should be migrated to a newer Import endpoint.

Table 623: POST /2/Import Request Body

Parameter Name	Parameter Value		
X509Base64	String containing the certificate blob. This may include the "BEGIN CERTIFICATE" and "END CERTIFICATE" references or these may be left out.		
MetadataList	A comma-delimited list of metadat	a fields, each containing two parts:	
	Name	Description	
	MetadataFieldTypeName	The metadata field name—e.g. Email-Address	
	Value	The metadata value—e.g. bob.smith@example.com	
	The metadataList parameter is not required, but if you choose to include it, you must include both the name and the value for each metadata value to be imported.		
CertState	Used to manually set the state of the	ne imported certificate. The following values are accepted:	
	Value	Description	
	0	Unknown	
	1	Active	

Parameter Name	Parameter Value		
	Value	Description	
	2	Revoked	
	3	Denied	
	4	Failed	
	5	Pending	
	6	Certificate Authority	
	7	Parent Certificate Authority	

POST http://<host>/CMSApi/Certificates/2/Import HTTP/1.1

#### 2.3.4.3 Certificates Contents

The Contents method retrieves the contents of a specified certificate. The request requires only enough information to identify a certificate in Keyfactor Command, and the body of a successful response will consist solely of the PEM-encoded representation of that certificate. Unlike most methods, for successful requests the response content type will be "text/plain".

Table 624: POST /3/Contents Request Body

Parameter Name	Parameter Value
Lookup	$\label{eq:Description} \textbf{Description of the certificate to be retrieved. See} \ \underline{\textbf{Table 4: Classic API Certificate Lookup Structure}}.$

# **Example Request**

POST http://<host>/CMSApi/Certificates/3/Contents HTTP/1.1

```
{
    "Lookup": {"type": "CMSID", "CMSID": <cms-certificate-id>}
}
```

#### **Example Response**

```
<base64-encoded-certificate-contents>
```

### 2.3.4.4 Certificates PublishCRL

The PublishCRL method will cause Keyfactor Command to make a request to the provided Certificate Authority to publish a new CRL to the locations configured by the CA. This method requires only a single parameter and returns no response body on a successful request. On an unsuccessful request, an appropriate HTTP status code along with a string in the response body describing the error is returned.

Table 625: POST /3/PublishCRL Request Body

Parameter Name	Parameter Value
CertificateAuthority	Certificate authority for the new CRL, in the form "hostname\\logical name" (double-backslash required for JSON formatting).

#### **Example Request**

POST http://<host>/CMSApi/Certificates/3/PublishCRL HTTP/1.1

```
{
    "CertificateAuthority" : "CA1.corp.com\\Issuing-CA1"
}
```

#### 2.3.4.5 Certificates Recover

The Recover method allows a user to recover an archived private key for an issued certificate. For recovery to succeed, the CA that issued the certificate must have been configured to archive the private key, and the Key Recovery Agent certificate must be imported into the personal certificate store of the Keyfactor Command API IIS Application Pool's user account on the Keyfactor Command API server. If successful, the method will return the certificate and recovered private key as a base64-encoded PFX file. On error, an appropriate HTTP status code and message will be returned. See the Configuring Key Recovery for Keyfactor Command section of the Keyfactor Command Reference Guide for information about configuring key recovery.

Table 626: POST /3/Recover Request Body

Parameter Name	Parameter Value		
Lookup	Description of the certificate to be renewed. See <u>Table 4: Classic API Certificate Lookup Structure</u> .		
Details	Information to complete the recovery operation. This contains just a single field:		
	Parameter Name Parameter Value		
	Password	Password for the archived private key.	

POST http://<host>/CMSApi/Certificates/3/Recover HTTP/1.1

```
{
    "Lookup" : {"Type" : "CMSID", "CMSID" : 248852},
    "Details": {"Password": "MyPassword1234"}
}
```

### **Example Response**

```
{
    "pfx" : "<PEM-encoded pfx>"
}
```

#### 2.3.4.6 Certificates Revoke

The Revoke method will attempt to revoke a certificate stored in Keyfactor Command. The certificate to be revoked can be identified using the *lookup* request body parameter (see <u>Table 4: Classic API Certificate Lookup Structure</u>). In addition, the message may contain string parameters describing the revocation. Caution is advised when programmatically revoking certificates as the operation generally cannot be undone. The method returns a 200 OK response if successful or an appropriate HTTP code and error message if unsuccessful.

Table 627: POST /3/Revoke Request Body

Parameter Name	Parameter Value
Lookup	Criteria to specify the certificate to be revoked. See <u>Table 4: Classic API Certificate Lookup Structure</u> .
Details	Details used to define the revocation operation. See <u>Table 628</u> : <u>Certificate Revocation Details</u> .

Table 628: Certificate Revocation Details

Parameter Name	Parameter Value			
Reason	Integer code for certificate revocation reason, as per IETF RFC 5280 ReasonFlags. This field is optional and will default to "0" (zero - unspecified). Allowed values are listed below:			
	Value	Definition		
	0	Unspecified		
	1	Key Compromised		
	2	CA Compromised		
	3	Affiliation Changed		
	4	Superseded		
	5	Cessation of Operation		
	6	Certificate Hold		
Comment	Explanation of revocation reason. Optional and will default to the empty string "".			
EffectiveDate	Date on which the revocation will take effect. Optional and will default to the current time if not specified.			
noCRL	If provided and set to "true", Keyfactor Command will not attempt to have the CA publish a new CRL. Optional and treated as "false" by default.			

POST http://<host>/CMSApi/Certificates/3/Revoke HTTP/1.1

```
{
    "Lookup": {"Type": "CMSID", "CMSID": 45},
    "Details": {"Reason":4, "EffectiveDate" : "2017-12-29", "Comment": "Reissued 12-27"}
}
```

#### 2.3.4.7 Certificates Search and Count

The Search method will return the set of certificates known to Keyfactor Command that satisfy certain criteria. The criteria that can be searched on and the syntax by which queries are formed is the same as in the Advanced Certificate Search within the Keyfactor Command Management Portal. This is largely consistent with PowerShell comparison notation, but Keyfactor does not publish a complete specification of this query language. Instead,

developers are encouraged to examine the query strings formed in the Keyfactor Command Management Portal and model their API queries based on this. The response will contain a JSON body with an array whose entries each represent a single matching certificate. The Count method expects the same parameters as the Search query but simply returns a count of the records that would be returned if the same parameters were provided to the Search endpoint. For Count, the sorting parameters will have no effect.

Table 629: POST /3/Search and /3/Count Request Body

Parameter Name	Parameter Value	
IncludeRevoked	Boolean denoting if revoked certificates should be included in the search results.	
IncludeExpired	Boolean denoting if expired certificates should be included in the search results.	
Query	Search query criteria, as defined above.	
SortField	Name of the result field by which the results should be sorted. The field must be one returned within the results. This parameter is optional and the Keyfactor Command certificate id will be used if not provided. The available fields are the same as in <a href="Table 630: POST/3/Search Response Body">Table 630: POST/3/Search Response Body</a> .	
SortAscending	Boolean value denoting if the SortField should be sorted in ascending order. This parameter is optional and ascending will be used if not provided.	
SkipCount	Number of records that should be skipped in the results, starting from the beginning of the records (for pagination). This field is optional and no records will be skipped if not provided.	
ReturnLimit	Numeric value of the limit of records to be returned. This field is optional and 5000 will be used if not provided.	

Table 630: POST /3/Search Response Body

Parameter Name	Parameter Value
Id	Certificate ID assigned by Keyfactor Command, which can be used for service chaining to other many other Web API requests by providing this value as a <i>CMSID</i> in the <i>Lookup</i> section of the request. See <u>Table 4</u> : Classic API Certificate <u>Lookup Structure</u> .
IssuedCN	Issued Common Name
IssuedDN	Issued Distinguished Name
NotBefore	Beginning date for certificate validity
NotAfter	Ending (expiration) date for certificate validity
IssuerDN	Issuer Distinguished Name

Parameter Name	Parameter Value		
PrincipalName	Subject Principal Name		
RequesterName	Requester Name		
TemplateName	Certificate Template Name		
CertState	Certificate State. Will take one of the following values:		
	Value	Definition	
	0	Unknown	
	1	Active	
	2	Revoked	
	3	Denied	
	4	Failed	
	5 Pending		
	6	CertificateAuthority	
	7	ParentCer	tificateAuthority
KeySize	Bit-length of the public/private keys.		
КеуТуре	Cryptographic algorithm used	for the publi	c/private key. Will take one of the following values:
	Value		Definition
	0		Unknown
	1		RSA
	2		DSA
	3		ECC
	4		DH
SerialNumber	The hexadecimal serial number of the certificate.		
Thumbprint	The hexadecimal thumbprint of the certificate.		

POST http://<host>/CMSApi/Certificates/3/Search HTTP/1.1

```
{
    "includeRevoked": true,
    "includeExpired": true,
    "query": "(ExpirationDate -eq \"2018-05-10\")"
}
```

#### **Example Response**

```
[{
    "Id":<certificate-id>,
    "IssuedCN": "<cn>",
    "IssuedDN": "<dn>",
    "NotBefore": "2017-05-10T18:59:57",
    "NotAfter": "2018-05-10T18:59:57",
    "IssuerDN": "<issuer-dn>",
    "PrincipalName": null,
    "RequesterName": null,
    "TemplateName": null,
    "CertState": 0,
    "KeySize": 4096,
    "KeyType": 1
}]
```

#### 2.3.5 Certstore

The Certstore Web API (formerly known as the Jks API) provides a set of methods to support management of certificate locations. Keyfactor Command currently supports management of certificates in the following remote locations:

- Java Keystore
- PEM file
- F5 BigIP Web Server
- F5 BigIP SSL Profiles
- Windows Machine Personal, Revoked, and Trusted Roots stores
- Citrix NetScaler virtual servers

Keyfactor Command can, through different Keyfactor Command Agents and Orchestrators, inventory, install, and remove certificates for each of these store types. For certain store types, additional actions are supported as well. The certstore API provides a way to programmatically schedule jobs for these stores. For more information about certificate stores and their support within Keyfactor Command, see the <u>Reference Guide</u> and <u>Installing Orches</u>-trators guide, or contact your Keyfactor representative. This API component currently has only one version, but for

backward-compatibility, it can be accessed through the component name "Certstore" (e.g. /CMSApi/Certstore/1/AddCert) or the legacy name "Jks" (e.g. /CMSApi/Jks/1/AddCert). The set of methods in this API component that can be used to manage certificate stores and their scheduled jobs is listed below in <a href="Table 631: Certstore Endpoints">Table 631: Certstore Endpoints</a>.

Table 631: Certstore Endpoints

Endpoint	Method	Description
AddCert	POST	Add given certificate (without private key) to a given certificate store (as well as Keyfactor Command)
AddCertStore	POST	Define a new certstore in Keyfactor Command
AddCertStoreServer	POST	Define a new remote server (e.g. F5, NetScaler) in Keyfactor Command to be managed by a Keyfactor Command agent
AddPFX	POST	Add a PFX file (with private key) to a given certificate store (as well as Keyfactor Command)
AddCertStoreType	POST	Add a Certificate Store Type to be used by a certificate store
CreateJKS	POST	Create a Java Keystore on the file system on target machine
EditCertStore	POST	Update a definition of an existing certificate store in Keyfactor Command
EditCertStoreServer	POST	Update a definition of an existing remote server managed by a Keyfactor Command agent
GetCertStoreTypes	GET	List all certificate store types
Inventory	POST	Retrieve the inventory of a given certificate store
Keystores	GET	Get a list of certificate stores defined in Keyfactor Command
Remove	POST	Remove a certificate from a certificate store
ScheduleInventory	POST	Schedule a certificate store inventory job schedule
ScheduleJob	POST	Schedule a certificate store management job
Status	GET	A synonym for GET /Status, included on this path for backwards-compatibility

#### 2.3.5.1 CertStore AddCert

The POST AddCert method will schedule the addition of the provided certificate to the specified alias/name within the provided certificate stores. The request and response objects will contain the fields shown in <u>Table 632: POST</u>/AddCert Response Body.

Table 632: POST /AddCert Request Body

Parameter Name	Parameter Value
Keystores	Array of the certificate stores to which the provided entry should be added, with the same format as the response to GET /Keystores (see <u>Table 647: GET /Keystores Response Body</u> ).
Alias	Name of the entry to which the certificate should be added. This parameter can also take a list of Certificate Store Type and Alias entries. If just a name is given, the certificate will have the same alias in all certificate stores it is added to. If a list is given, the certificate will have the same alias for each given store with the same certificate store type.
Overwrite	Boolean denoting if the entry should be overwritten, if one exists. An error will be returned if this is set to false, and an entry with the same alias/name exists.
Contents	PEM of the certificate to be added. This field is optional if a CertificateId is provided.
CertificateId	Database identifier within Keyfactor Command of the certificate to be added. This field is optional if the Contents are provided.

Table 633: POST /AddCert Response Body

Parameter Name	Parameter Value	
Result	Numerical code indicating the result of the operation, as described in <u>Table 637: POST /AddCertStoreServer Response Body</u> .	
Message	Description of the result	of the operation, e.g. "The operation completed successfully".
InvalidKeystores	Array of certstores provided in the request for which the operation could not be completed. Entries will be formatted as follows:	
	Parameter Name	Parameter Value
	KeystoreId	Guid of the certstore
	ClientMachine	Machine hosting the certstore
	StorePath	File path to the store on its machine
	Alias	Alias for certificate to be added
	Reason	Numerical code for the failure. Will take one of the following values:

Parameter Name	Parameter Value		
	Parameter Name	Parameter Value	
		Value	Error Message
		0	The certificate store was not found.
		1	A job to add this certificate to this alias already exists.
		2	No agent is available to perform this job.
	Explanation	A description o	f the failure encountered.

Multiple Alias entries

POST http://<host>/CMSApi/CertStore/1/AddCert HTTP/1.1

# **Example Request**

String Alias

POST http://<host>/CMSApi/CertStore/1/AddCert HTTP/1.1

```
{
    "Keystores":
```

```
[
    {"Id": "", "ClientMachine": "<client-machine>", "StorePath": "<store-path>"},
    {"Id": "", "ClientMachine": "<client-machine>", "StorePath": "<store-path>"}
],
    "Alias": "<alias>",
    "Overwrite":true,
    "CertificateId":"<certificate-id>",
    "Contents": "----BEGIN CERTIFICATE-----
    <base64-encoded-certificate-contents>
    -----END CERTIFICATE-----"
}
```

# **Example Response**

```
{
    "Result": 1,
    "Message" : "The operation completed successfully.",
    "InvalidKeystores": []
}
```

#### 2.3.5.2 CertStore AddCertStore

The AddCertStore method allows a client to define a new certificate store within Keyfactor Command. The structure is as follows:

Table 634: POST /AddCertStore Request Body

Parameter Name	Parameter Value	
StoreType	Type of certificate store to be defined. This field is required and allowed values are:	
	Parameter Name	Parameter Value
	0	Java Keystore
	2	PEM file
	3	F5 SSL Profiles
	4	IIS Trusted Root Certificates

Parameter Name	Parameter Value	
	Parameter Name	Parameter Value
	5	NetScaler
	6	IIS Personal Certificates
	7	F5 Web Server
	8	IIS Revoked Certificates
	100	Amazon Web Services
	101	File Transfer Protocol
ClientMachine	Machine where the certificate store resides (or will reside). Required.	
StorePath	Path on the client machine where the store should be defined. Required for Java Keystore, PEM file, F5 SSL Profiles, and NetScaler (categories 0, 2, 3, and 5).	
AgentId	Identifier of agent that will service the request. Either AgentId or AgentName must be provided for F5 (categories 3 and 7), IIS (categories 4, 6, and 8), and NetScaler stores (category 5).	
AgentName	Machine name of agent that will service the request. Either AgentId or AgentName must be provided for F5 (categories 3 and 7), IIS (categories 4, 6, and 8), and NetScaler stores (category 5).	
Container	Certificate store container that should contain the certificate store. This is optional and no certstore container will be assigned if it is not provided. See the <i>Keyfactor Command Reference Guide</i> for information on certificate store containers.	
Password	Password used to access the store. Required for Java Keystore and optional for PEM file.	
PrivateKeyPath	Path on the client machine where the private key should be stored. Supported only for PEM files, and is optional in that case. If no path is provided for a PEM file, the private key will be stored in the same PEM file as the certificate.	

Table 635: POST /AddCertStore Response Body

Parameter Name	Parameter Value
Message	Description of the result of the operation, e.g. "The operation completed successfully".
Result	Numerical code for the outcome of the operation, as given in Table 637: POST /AddCertStoreServer

Parameter Name	Parameter Value
	Response Body.
Id	GUID of the created store, if successful.

POST http://<host>/CMSApi/CertStore/1/AddCertStore HTTP/1.1

```
{
    "ClientMachine": "192.168.41.171",
    "StorePath": "/opt/cms-java-agent/config/trust.jks",
    "StoreType": 0,
    "Password": "changeit"
}
```

#### **Example Response**

```
{
    "Result": 1,
    "Message": "The operation completed successfully.",
    "Id": "b195c1f9-1957-4bdb-a15d-f45159482611"
}
```

#### 2.3.5.3 CertStore AddCertStoreServer

Some certificate stores are managed by agents accessing the store through a third-party Web API. This currently includes F5 BigIP devices and Citrix NetScaler devices. These stores require the definition of a certstore server before the store itself can be defined in Keyfactor Command. Each server can be configured with a location and user credentials to access the client machine via the appropriate third-party API. This Keyfactor Command Web API method allows such configuration. The structure shown in <a href="Table 636: POST /AddCertStoreServer Request Body">Table 636: POST /AddCertStoreServer Request Body</a> should be used for requests.

Table 636: POST /AddCertStoreServer Request Body

Parameter Name	Parameter Value
Name	Hostname of the machine the agent will connect to.
ServerType	Platform for this server, defining what certstore types are supported. Allowed values are:

Parameter Name	Parameter Value		
	Parameter Name	Parameter Value	
	0	F5	
	1	NetScaler	
UseSSL	Boolean denoting whether the agent should	connect to the client API using https or http.	
Username	Username to provide to the client API.		
Password	Password corresponding to the login for the	given Username to access the client API.	

Table 637: POST /AddCertStoreServer Response Body

Parameter Name	Parameter Value	
Result	Status code for the operation. Will take one of the following values:	
	Value	Description
	1	Success
	2	Failure
	3	Warning
Message	Description of the operation outco	me, e.g. "The operation completed successfully".

POST http://<host>/CMSApi/CertStore/1/AddCertStoreServer HTTP/1.1

```
{
    "Name": "192.168.23.100",
    "UseSSL" : true,
    "Username": "nsroot",
    "Password": "nsroot",
    "ServerType": 1
}
```

# **Example Response**

```
{
    "Result": 1,
    "Message": "The operation completed successfully."
}
```

# 2.3.5.4 CertStore AddCertStoreType

The POST /AddCertStoreType method will create a certificate store type that will be used for a custom certificate store that extends the Keyfactor Command Agent's Any Agent functionality. The parameters that can be used for this endpoint are shown in <u>Table 638: POST /AddCertStoreType Request Body</u>, while the response format can be found in <u>Table 639: POST /AddCertStoreType Response Body</u>.

Table 638: POST /AddCertStoreType Request Body

Parameter Name	Parameter Value
Name	The name the certificate store type will have in Keyfactor Command. This parameter is <b>required</b> .
ShortName	The short name of the certificate store type. This parameter is <b>required</b> .
AddSupported	A Boolean that sets if the certificate store of this certificate store type is allowed to be added to. This parameter is <b>required</b> .
CreateSupported	A Boolean that sets if the certificate store of this certificate store type is allowed to be created if missing. This parameter is <b>required</b> .
DiscoverySupported	A Boolean that sets if the certificate store of this certificate store type is allowed to be discovered in a discovery scan. This parameter is <b>required</b> .
RemoveSupported	A Boolean that sets if the certificate store of this certificate store type allows certificates to be removed from it. This parameter is <b>required</b> .
EnrollmentSupported	A Boolean that sets if the certificate store of this certificate store type supports reenrollment. This parameter is <b>required</b> .
EntryPasswordSupported	A Boolean that sets if the certificate store of this certificate store type supports an entry password. This parameter is <b>required</b> .
PrivateKeyAllowed	A parameter that sets requirements on the private key of a certificate being entered into the certificate store. This parameter is <b>required</b> . Valid values are:

Parameter Name	Parameter Value		
	Value	Name	
	0	Forbidden	
	1	Optional	
	2	Required	
LocalStore	A Boolean that sets if the certification ficate store server. This parameter	ate store of this certificate store type requires a certier is <b>required</b> .	
StorePasswordRequired	A Boolean that sets if the certification meter is <b>required</b> .	ate store of this type requires a password. This para-	
StorePathType	The type used for the certificate	store path.	
	Option	Description	
	Empty Path will be a free form field.		
	String	Path will only be the specified string.	
	Comma Separated String	Path will need to be chosen from the list given.	
CustomAliasAllowed	A Boolean that sets whether the certificate store of this type allows a custom alias. This parameter is optional.		
Powershell	A Boolean that sets whether the certificate store of this type uses PowerShell. This parameter is optional.		
ServerRegistration	A Boolean that sets whether Keyfactor Command needs to prompt for credentials for each client machine that has that certificate store type. This parameter is optional.		
JobProperties	A comma separated string defining properties that are required when performing management jobs on a certificate store of this type. This parameter is optional.		
Properties	A dictionary of any extra properties a certificate store of this type would need. This parameter is optional. If this property is provided, a type is required. Parameters of a property are:		
	Field Description		
	DisplayName The name of the property. This parameter is optional.		

Parameter Name	Parameter Value	2
	Field	Description
	Туре	The type of the property. This parameter is <b>required</b> . Valid values are: String, Bool, MC, and Secret
	Required	A Boolean that sets whether the property is required in the certificate store.
	Depends	If this is not the first property, this property can depend on another property. The property name is used to determine which property is being depended on.
	Value	A default Value of the property.

Table 639: POST /AddCertStoreType Response Body

Parameter Name	Parameter Value	
Message	Description of the operation outcome, e.g. "The operation completed successfully".	
Result	Status code for the operation. Will take one of the following values:	
	Value	Description
	1	Success
	2	Failure
	3	Warning
Data	Value	Description
	Name	The name of the type.
	ShortName	The ShortName of the type.
	StoreType	The Id of the store
	LocalStore	A Boolean if the certificate store is on the local server of the agent.
	ServerRegistration	Tells whether server registration is needed by

Parameter Name	Parameter Value		
	Value	Description	
		Keyfactor Command.	
	ImportType	A value to indicate the source of a certificate record in the Keyfactor Command audit logs.	
	InventoryJobType	The GUID of the inventory job type that is used to register with the Any Agent.	
	ManagementJobType	The GUID of the management job type that is used to register with the Any Agent.	
	AddSupported	A Boolean stating whether an add job will be supported by the certificate store.	
	RemoveSupported	A Boolean stating whether a remove job will be supported by the certificate store.	
	CreateSupported	A Boolean stating whether a create job will be supported by the certificate store.	
	DiscoverySupported	A Boolean stating whether a discovery job will be supported by the certificate store.	
	EnrollmentSupported	A Boolean stating whether an enrollment job will be supported by the certificate store.	
	InventoryEndpoint	The endpoint that will be hit by the agent.	
	Properties	A list of properties that reflect those given in the request.	
	EntryPasswordSupported	A Boolean stating whether an entry password will be supported by the certificate store.	
	StorePasswordRequired	A Boolean stating whether a store password will be required by the certificate store.	
	PrivatekeyAllowed	An integer notifying the state of the private keys in the certificate store.	

Parameter Name	Parameter Value		
	Value	Description	
		Value	Name
		0	Forbidden
		1	Optional
		2	Required
	StorePathType	The value of the stor empty string, the field	
	CustomAliasAllowed	A Boolean stating whether a custom alias will be supported by the certificate store.	
	JobProperties		will be required when ement job on the certitype.

POST http://<host>/CMSApi/CertStore/1/AddCertStoreType HTTP/1.1

```
{
       "Name": "<Type Name>",
       "ShortName": "<Type Short Name>",
       "AddSupported": true,
       "CreateSupported": false,
       "DiscoverySupported": true,
       "RemoveSupported": true,
       "EnrollmentSupported": true,
       "EntryPasswordSupported": true,
       "PrivateKeyAllowed": <integer 0-2>,
       "LocalStore": true,
       "StorePasswordRequired": true,
       "Powershell":false,
       "CustomAliasAllowed":false,
       "JobProperties":"<List of Job Properties>",
       "ServerRegistration": false,
       "Properties": {
               "<Property Name>": {
                       "type":"<Property Type>",
```

```
"DisplayName": "<Discplay Name>"
},

"<Property Name>":{

    "type":"<Type>",

    "displayName":"<Display Name>"

    "value": "<Value>"

}

},

"StorePathType": <Path Type>
}
```

#### **Example Response**

Status Code: 200

```
{
       "Message": "The operation completed successfully.",
      "Result": 1,
       "Data": {
               "Name": "<Name>",
               "ShortName": "<Short Name>",
               "StoreType": <Store Type Id>,
               "LocalStore": true,
               "ServerRegistration": null,
               "ImportType": <Import Type>,
               "InventoryJobType": "<Inventory Job Type Guid>",
               "ManagementJobType": "<Management Job Type Guid>",
               "AddSupported": false,
               "RemoveSupported": true,
               "CreateSupported": false,
               "DiscoveryJobType": "<Discovery Job Type Guid>",
               "EnrollmentJobType": "<Enrollment Job Type Guid>",
               "InventoryEndpoint": "<Inventory Endpoint>",
               "Properties": {
                       "<Property Name>": {
                               "Type": "<Type>",
                               "DisplayName": "<Discplay Name>",
                               "Required": false,
                               "Depends": null,
                               "Value": <Value>
                       },
                       "<Property Name>": {
                               "Type": "<Type>",
                               "DisplayName": "<Display Name> ",
```

#### 2.3.5.5 CertStore AddPFX

The POST AddPfx method will schedule the addition of the provided PFX(s) to the specified alias/name within the provided certificate store(s). The request should contain the fields shown in <u>Table 640: POST /AddPfx Request Body</u>, while the response format will be the same as for AddCert (see <u>Table 633: POST /AddCert Response Body</u>).

Table 640: POST /AddPfx Request Body

Parameter Name	Parameter Value
Keystores	Array of certificate stores to which the provided entry should be added, with the same format as the response to GET /Keystores (see <u>Table 647: GET /Keystores Response Body</u> ).
Alias	Name of the entry to which the certificate should be added.
Overwrite	Boolean denoting if the entry should be overwritten, if one exists. An error will be returned if this is set to false but an entry with the same alias/name exists.
Contents	PEM of the PFX to be added. Do not include theBEGIN ANDEND lines.
PfxPassword	Password of the PFX.
HasEntryPassword	Boolean denoting if the password required for the entry is different than that of the certificate store itself.
EntryPassword	Password for the certificate store entry. Required if the HasEntryPassword is set to true.

# **Example Request**

POST http://<host>/CMSApi/CertStore/1/AddPfx HTTP/1.1

```
{
       "Keystores":
       "Id": "<keystore-id>",
       "ClientMachine": "<client-machine>",
       "StorePath": "<store-path>"
       },
       "Id": "<keystore-id>",
       "ClientMachine": "<client-machine>",
       "StorePath": "<store-path>"
       "Alias": "<alias>",
       "Overwrite": "true",
       "HasEntryPassword": "true",
       "EntryPassword": "<entry-password>",
       "PfxPassword": "<pfx-password>",
       "Contents": "<base64-encoded PFX>"
}
```

#### 2.3.5.6 CertStore CreateJKS

In most cases, certificate stores will already exist on the client machine prior to configuration within Keyfactor Command. For example, the IIS Personal Store exists on each windows machine independently of Keyfactor Command installation. In other cases, such as PEM files, the file can be created when a certificate is added. However, with a Java Keystore, creating the store on the file system and adding certificates to it are different operations. The CreateJKS method supports scheduling creation of a Java Keystore as a Keyfactor Command Agent job. The structure of this request is given in <a href="Table 641: POST / CreateJKS Request Body">Table 641: POST / CreateJKS Request Body</a> while the response is the same as for AddCertStore (see Table 635: POST /AddCertStore Response Body).

Table 641: POST /CreateJKS Request Body

Parameter Name	Parameter Value
ClientMachine	Machine on which the certificate store will reside.
StorePath	Path and filename of the certificate store to be created.
Password	Password to use for the new store.

#### **Example Request**

POST http://<host>/CMSApi/CertStore/1/CreateJKS HTTP/1.1

```
{
    "ClientMachine" : "192.168.41.171",
    "StorePath" : "/opt/cms-java-agent/config/trust.jks",
    "Password" : "changeit"
}
```

#### 2.3.5.7 CertStore EditCertStore

The EditCertStore method allows certain aspects of a cert store definition to be updated. Some aspects, such as the store type and client machine, cannot be updated. The format of the request given in <a href="Table 642: POST /EditCertStore Request Body">Table 642: POST /EditCertStore Request Body</a>, while the response will be as it is for <a href="Table 637: POST /AddCertStoreServer Response Body">Table 642: POST /EditCertStoreServer Response Body</a>.

Table 642: POST /EditCertStore Request Body

Parameter Name	Parameter Value
Id	Guid – Unique identifier of the certificate store. This field is the most specific, and does not require either the ClientMachine or StorePath fields to be provided.
ClientMachine	Machine on which the store resides. This field is required if the Id field is not provided.
StorePath	Path and filename of the certificate store. This field is required if the Id field is not provided.
NewStorePath	New path on the machine filesystem where the certstore resides.
NewContainer	Reassign the certstore container in Keyfactor Command where this store is configured.
NewPassword	Change the password used by the agent to access the store.
NewPrivateKeyPath	Change the path of a private key stored separately from a PEM file certificate
NewAgentId	Change the agent managing a remote certstore by providing its GUID. Cannot be used with NewAgentName.
NewAgentName	Change the agent managing a remote certstore by providing the name it reports to Keyfactor Command. Cannot be used with NewAgentId.

### **Example Request**

POST http://<host>/CMSApi/CertStore/1/EditCertStore HTTP/1.1

```
{
    "ClientMachine": "192.168.23.100",
    "StorePath" : "/nsconfig/ssl",
    "NewStorePath" : "/nsconfig/ssl/vserver1",
```

```
"NewContainer": "NetScaler"
}
```

#### 2.3.5.8 CertStore EditCertStoreServer

A cert store server is a machine that hosts a store that is remotely managed by a Keyfactor Command Agent, such as a NetScaler or F5 device. The CertStoreServer configuration contains the data that allows the agent to connect to the host via the host platform's API. This method allows configuration of an existing CertStoreServer to be updated. The request format is shown in <u>Table 643: POST /EditCertStoreServer Request Body</u>, while the response format is the same as for AddCertStoreServer (see Table 637: POST /AddCertStoreServer Response Body).

Table 643: POST /EditCertStoreServer Request Body

Parameter Name	Parameter Value
Name	Hostname of the machine the agent will connect to. Required if Id is not provided.
Id	Identifier of the certstore server to update. Required if Name is not provided.
UseSSL	Boolean denoting whether the agent should connect to the client API using https or http.
NewUsername	Username to provide to the client API. Required if NewPassword is provided.
NewPassword	Password corresponding to the login for the given Username to access the client API. Required if NewUsername is provided.

#### **Example Request**

POST http://<host>/CMSApi/CertStore/1/EditCertStoreServer HTTP/1.1

```
"Name": "192.168.23.100",
    "UseSSL" : true,
    "newUsername" : "myNetScalerAdmin",
    "newPassword": "S1deways-Grassh0pper4979"
}
```

# 2.3.5.9 CertStore GetCertStoreTypes

The GET CertStoreTypes method returns a list of all certificate store types. The format for each element in the list can be found in Table 644: GET /GetCertStoreTypes Response Body.

Table 644: GET /GetCertStoreTypes Response Body

Parameter Name	Parameter Value
Name	The name of the type.
ShortName	The short name of the type.
StoreType	The Id of the type.
LocalServer	A Boolean stating if the certificate store server is the same machine as the agent.
ServerRegistration	A Boolean stating whether Keyfactor Command needs to prompt for credentials for each client machine that has this certificate store type.
InventoryJobType	The GUID of the Inventory Job.
ManagementJobType	The GUID of the management job.
DiscoveryJobType	The GUID of the discovery job.
EnrollmentJobType	The GUID of the enrollment job.
InventoryEndpoint	The server endpoint to which the agent publishes its inventory results.
Properties	The added properties of the certificate store that uses this type.
EntryPasswordSupported	A Boolean stating if an entry password is supported by the certificate store that uses this type.
StorePasswordRequired	A Boolean stating if a store password is required by the certificate store that uses this type.
PrivateKeyAllowed	A Boolean stating if a private key is allowed by the certificate store that uses this type.
StorePathType	The value for the store path. Can be null, a string or a comma-separated string for free form, the specified path or a list of paths to choose from respectively.

# 2.3.5.10 CertStore Inventory

The POST Inventory method returns a list of the entries within the provided certificate store. The request body is formatted the same as the response to GET /Keystores (see <u>Table 647: GET /Keystores Response Body</u>).

Table 645: POST /Inventory Response Body

Parameter Name	Parameter Value
Alias	Alias/name of the certificate store entry.

Parameter Name	Parameter Value
PrivateKeyEntry	Boolean value denoting if the entry has an associated private key.
Certificates	Array of the certificates contained within the certificate store (see <u>Table 646: POST /Inventory</u> <u>Response Certificates Fields</u> ).

Table 646: POST /Inventory Response Certificates Fields

Parameter Name	Parameter Value
ChainLevel	Position of the certificate within the chain. This is only applicable for private key entries.
CertificateId	Database identifier of the certificate within Keyfactor Command.
Thumbprint	Thumbprint of the certificate.

POST http://<host>/CMSApi/CertStore/1/Inventory HTTP/1.1

```
{
    "Id": "<certificate-store-id>",
    "ClientMachine": "<client-machine>",
    "StorePath": "<store-path>"
}
```

# **Example Response**

```
{"ChainLevel": 2,"CertificateId": <id>,"Thumbprint": "<thumbprint>"}
]
}
```

# 2.3.5.11 CertStore Keystores

The GET Keystores method returns a list of the certificate stores within Keyfactor Command. This method requires no parameters. An array of the certificate stores is returned. The information shown in <u>Table 647: GET /Keystores</u> <u>Response Body</u> is returned for each certificate store in the array.

Table 647: GET /Keystores Response Body

Parameter Name	Parameter Value
Id	The Keyfactor Command request database identifier of the certificate store.
ClientMachine	Host name of the machine on which the certificate store resides.
StorePath	Path or other identifier of the certificate store (e.g. "IIS Personal" for IIS Personal stores).

### **Example Request**

GET http://<host>/CMSApi/Certstore/1/Keystores

# **Example Response**

```
{
    "Id": "<certificate-store-id>",
    "ClientMachine": "<client-machine>",
    "StorePath": "<store-path>"
    },
    {
      "Id": "<certificate-store-id>",
      "ClientMachine": "<client-machine>",
      "StorePath": "<store-path>"
    }
}
```

#### 2.3.5.12 CertStore Remove

The POST Remove method will schedule the removal of the provided entry associated with the specified alias/name within the provided certificate store(s). The request should contain the fields shown in <a href="Table 648: POST">Table 648: POST</a> /Remove Request Body, while the response will be formatted as it is for AddCert and AddPfx (see <a href="Table 633: POST">Table 633: POST</a> /AddCert Response Body).

Table 648: POST /Remove Request Body

Parameter Name	Parameter Value
Keystores	Array of the certificate stores from which the provided entry should be removed, formatted as with the GET /Keystores response (see <u>Table 647: GET /Keystores Response Body</u> ).
Alias	Name of the entry from which the certificate should be removed.
Thumbprint	Thumbprint of the certificate to be removed. This field is optional if the CertificateId is provided.
CertificateId	Database identifier within Keyfactor Command of the certificate to be removed. This field is optional if the Thumbprint is provided.

### **Example Request**

POST http://<host>/CMSApi/CertStore/1/Remove HTTP/1.1

```
"Keystores":
    [{
        "Id": "<keystore-id>",
        "ClientMachine": "<client-machine>",
        "StorePath": "<store-path>"
        },
        {
        "Id": "<keystore-id>",
        "ClientMachine": "<client-machine>",
        "StorePath": "<store-path>"
        }],
        "Alias": "<alias>",
        "CertificateId": "<certificate-id>",
        "Thumbprint": "<thumbprint>"
}
```

# 2.3.5.13 CertStore ScheduleInventory

Keyfactor Command Agents typically monitor the contents of cert stores they manage on a pre-configured interval, either once per day or every n minutes. The ScheduleInventory endpoint allows this interval configuration to be updated or switched on and off. Requests are formatted as follows, while the response is formatted as for AddCertStoreServer (see Table 637: POST /AddCertStoreServer Response Body):

Table 649: POST /ScheduleInventory Request Body

Parameter Name	Parameter Value		
Id	Guid – Unique identifier of the certificate store. This field is the most specific, and does not require either the ClientMachine or StorePath fields to be provided.		
ClientMachine	Machine on which the certificate store resides. The required if used in conjunction with the ClientMachine.		
StorePath	Path and filename of the certificate store. This fie required if used in conjunction with the ClientMac	·	
ScheduleType	Value indicating whether inventory should be off, on an interval, or daily. Possible values are:		
	Parameter Name	Parameter Value	
	0	Off	
	1	Interval	
	2	Daily	
ScheduleTime	Time of day (hour and minute) that the inventory	should run. Used for ScheduleType "Daily".	
ScheduleInterval	Integer number of minutes that should elapse between inventories. Used for ScheduleType "Interval".		
Overwrite	Boolean indicating whether a previous schedule configuration, if it exists, should be overwritten with the provided schedule configuration.		

# **Example Request**

POST http://<host>/CMSApi/CertStore/1/ScheduleInventory HTTP/1.1

```
{
    "ID": "832f87c7-0af7-4043-9840-3022faeeae45",
    "ClientMachine": "192.168.41.171",
    "StorePath": "/home/pi/cherry/cherrystore",
    "ScheduleType": 2,
```

```
"ScheduleTime: "23:00",
"Overwrite": true
}
```

# **Example Response**

Status Code: 200

```
{
    "Message": "The operation completed successfully.",
    "Result": 1
}
```

#### 2.3.6 Metadata

Metadata in Keyfactor Command allows dynamic information about a certificate, or other data associated with a certificate that isn't included in the cert itself, to be associated with the certificate within Keyfactor Command. A metadata field can be defined within Keyfactor Command of a given type with a variety of other attributes, such as default values and security constraints. Currently, the supported metadata types are:

- String
   Alphanumeric text field limited to 400 characters.
- Integer
   Supports whole numbers only.
- Date
- Multiple Choice
- Big Text

Big Text fields are limited to 4000 characters. String fields support additional indexing, and so may be preferable to Big Text fields for large databases where possible.

 Boolean True/False

Every certificate in Keyfactor Command can be assigned a value for each metadata field defined. The Metadata Web API component supports assignment, retrieval, and comparison of metadata values associated with a certificate, as well as retrieval of metadata field definitions. The supported methods are listed in <u>Table 650: Metadata Endpoints</u>.

NOTE: Since the Certificates/1/Metafield endpoint (see <u>Certificates Metafield on page 1383</u>) is considered "Version 1" of this API component, version numbering here starts at 2.

Table 650: Metadata Endpoints

Endpoint	Method	Description
/2/Compare	POST	Compare the stored value for a metadata field associated with a given certificate against the value given in the request, and return a Boolean indicating whether the values match.
/2/Get	POST	Return the value for a metadata field associated with a given certificate.
/2/Set	POST	Assign a value for a metadata field to a given certificate.
/3/Get	POST	Return the value for a metadata field associated with a given certificate.
/3/GetDefinition	POST	Return the definition for the metadata field with given name.
/3/Set	POST	Assign a value for a metadata field to a given certificate.

#### 2.3.6.1 Metadata V2

The Metadata/2/... calls all have a common request format and set of response codes. The request body is always a JSON-formatted string containing a set of fields used to identify the certificate the operation is to be performed on and a list of key-value pairs defining the metadata fields of interest. In the case of the Set method, the values to which each field should be set must also be provided.

Table 651: POST Metadata/2/\* Request Body

Parameter Name	Parameter Value
Key	The key value can either be "Thumbprint" or "Serial" to identify the certificate. If you choose serial, you must include both the SerialNumber and the IssuerDN fields.
SerialNumber	The serial number of the certificate. Required only if Key is set to "Serial".
IssuerDN	The issuer of the certificate. Required only if Key is set to "Serial".
Thumbprint	The thumbprint of the certificate. Required only if Key is set to "Thumbprint".
metadatalist	Metadata field/value entries in one of the following forms:  • [{"MetadataFieldTypeName" : " <field1-name>", "Value" : "<field1-value>"}, {}, {}]  • {"<field1-name>" : "<field1-value>", "<field2-name>" : "<field2-value>"}</field2-value></field2-name></field1-value></field1-name></field1-value></field1-name>

#### Metadata V2 Set

The Metadata V2 Set POST method is used to set metadata value on a certificate in Keyfactor Command. The POST request body must consist of a JSON string containing the parameters used to set a certificate's metadata. If the

request is successful, a 200 OK will be returned with "true" in the message body. If it is not, an appropriate 4xx HTTP status code is returned, and the body will contain a JSON object with a message about the error.

#### **Example Request**

Using thumbprint

POST http://<host>/CMSApi/Metadata/2/Set

```
{
    "Key": "Thumbprint",
    "Thumbprint": "<thumbprint>",
    "metadatalist" : [{"EmailAddress":"bob.smith@example.com"}]
}
```

#### **Example Request**

Using serial

POST http://<host>/CMSApi/Metadata/2/Set HTTP/1.1

```
{
    "Key": "Serial",
    "SerialNumber": "<serial-number>",
    "SerialIssuer": "<issuing-ca>",
    "metadatalist": [{"EmailAddress": "bob.smith@example.com"}]
}
```

#### **Example Response**

(Unsuccessful)

```
{
    "Message": "The following metadata errors were found: 'myInvalidField' was not a valid
MetadataFieldTypeName."
}
```

#### Metadata V2 Get

The Metadata V2 Get POST method is used to get metadata value on a certificate in Keyfactor Command. Despite the "Get" in the Keyfactor Command method name, the HTTP method must be POST and not GET. As with metadata/2/set (see Metadata V2 Set on the previous page), the POST request body must consist of a JSON string

containing the parameters used to get a certificate's metadata. The "value" attribute for each entry in the metadatalist is not used, but must be present and can be set to null or an empty string.

#### Example Request

Using thumbprint

POST http://<host>/CMSApi/Metadata/2/Get HTTP/1.1

```
{
    "Key": "Thumbprint",
    "Thumbprint": "<thumbprint>",
    "metadatalist": [{"MetadataFieldTypeName": "EmailAddress", "Value": ""}]
}
```

### **Example Response**

```
{
    "EmailAddress" : "bob.smith@example.com"
}
```

### Metadata V2 Compare

The Metadata V2 Compare method takes a collection of metadata and returns a true/false response depending on whether the values for the fields provided match the values stored in Keyfactor Command. This can be used to prevent exposing sensitive data while still providing functionality. For example, with this method a metadata attribute can be used along with the certificate itself as a second authentication factor to third-party applications.

# **Example Request**

POST http://<host>/CMSApi/Metadata/2/Compare HTTP/1.1

```
{
    "Key": "Thumbprint",
    "Thumbprint": <Thumbprint>
    "metadatalist": [{"MetadataFieldTypeName": "EmailAddress",
    "Value": "example@example.com"}]
}
```

#### 2.3.6.2 Metadata V3

Version 3 of the metadata API allows more flexibility in certificate lookup and security measures than version 2, while allowing more to be done in a single API call and with a more concise JSON representation. Requests to metadata v3 API methods include 3 parts as shown in Table 652: Metadata V3 Request Body.

Table 652: Metadata V3 Request Body

Parameter Name	Parameter Value
Lookup	Given in Table 4: Classic API Certificate Lookup Structure.
Security	Given in Table 653: Metadata V3 Security Bitflags
Metadata	Dictionary of key-value pairs, where the key represents the metadata field and (for the set method) the value represents the value to be associated to the certificate referenced in the "Lookup" value. For Get and GetDefinition methods, the same structure is used but the value is not considered.

The security parameter includes a set of required flags, certain of which necessitate the inclusion of other parameters. The flags should be passed as integers, combined together using bitwise OR. The flags defined in Keyfactor Command are described in Table 653: Metadata V3 Security Bitflags.

Table 653: Metadata V3 Security Bitflags

Value	Definition
0000001	Fail if certificate has been revoked or denied.
0000010	Fail if certificate has expired.
00000100	Fail if certificate status is pending or unknown.
00001000	Fail if metadata values provided for authentication do not match the values stored in Keyfactor Command.  Must be paired with an "authmetadata" field, the value of which is a dictionary formatted with {"MetadataFieldName" : "AssociatedCertificateValue" pairs}. This effectively supplants the "Compare" method found in v2.
00100000	Overwrite flag — update value even if field is configured to require explicit overwrites and a value has been associated with the certificate (applies to Set method only).

The metadata argument is a JSON dictionary containing 0 or more key-value pairs. In each pair, the key must correspond to the name of a metadata field. The value, if present, must be of a data type matching the type of the field. For Boolean and integer metadata field values, this is the JSON Boolean or integer type, respectively, while all other metadata field types are to be represented as strings. Dates should be passed in the "YYYY-M-D" format. Multi-valued entries should have a value that exactly matches one of the pre-defined values. For the Get method, values need not be provided and the empty string can be used as the value for each key. In the case where there

are 0 metadata arguments, the "Metadata" key must still be present and mapped to an empty object "{}". Note that this syntax is different than previous Metadata API versions, and uses a more concise format. An example is:

```
"Metadata" : {"Email-Contact" : "user@example.com", "Contact-Name" : "John Doe", "ID-number" : 738}
```

#### Metadata V3 Set

The Metadata V3 Set POST method is used to set metadata value on a certificate in Keyfactor Command. It returns a "200 OK" response with no further content on success.

### **Example Request**

Using thumbprint

POST http://<host>/CMSApi/Metadata/3/Set HTTP/1.1

#### **Example Request**

Using serial

POST http://<host>/CMSApi/Metadata/3/Set HTTP/1.1

```
"Lookup":

{
        "Type": "Serial",
        "SerialNumber": "<serial-number>",
        "IssuerDN": "<issuer-dn>"
},
        "Security": {"Flags" : 3},
        "Metadata": {"Email-Contact": "bob.smith@example.com"}
}
```

#### Metadata V3 Get

The Metadata V3 Get POST method is used to get metadata value on a certificate in Keyfactor Command. Despite the "Get" in the Keyfactor Command method name, the HTTP method must be POST and not GET. As with metadata/3/set (see Metadata V3 Set on the previous page), the POST request body must consist of a JSON string containing the parameters used to get a certificate's metadata. The "value" attribute for each metadata entry is not used, but must be present and can be set to null or an empty string. The method returns a JSON dictionary in a format identical to the metadata parameter, with key-value pairs containing the fields and values requested.

#### **Example Request**

POST http://<host>/CMSApi/Metadata/3/Get HTTP/1.1

#### **Example Response**

```
{
    "Email-Contact": "bob.smith@example.com"
}
```

#### Metadata V3 GetDefinition

The Metadata V3 GetDefinition API endpoint will return the definition of a metadata field. Note that, while this does not operate on a certificate, the same request structure is used so the fields must be supplied, but the value will not be used. The structure of the response is given below.

Table 654: POST / GetDefinition Response Body

Parameter Name	Parameter Value
Name	Name of the metadata field.

Parameter Name	Parameter Value
Description	Purpose or intended usage of the field.
Hint	Sample value to be shown when users enter a value for this field in the Keyfactor Command Management Portal.
Validation	Regular Expression string capturing acceptable values for this field.
Required	Boolean indicating whether certificates added to Keyfactor Command must include a value for this field.
Message	Error message to be returned for values that do not conform to the regular expression.
Options	Comma-separated list of allowed values for "multi-valued" metadata fields.
DefaultValue	Initial value to be assigned for new certificates if a value is not provided at addition time.
AllowAPI	Boolean indicating whether values for this field are exposed through API Get and Set requests.
ExplicitUpdate	Boolean indicating whether updates require an appropriate flag to overwrite previous values.

POST http://<host>/CMSApi/Metadata/3/GetDefinition HTTP/1.1

```
{
    "Lookup": { "Type": "CMSID", "CMSID" : 1},
    "Security": {"Flags": 0},
    "Metadata ": {"Email-Contact": ""}
}
```

```
"Name": "Email-Contact",
   "Description": "Email contact for the certificate.",
   "Hint": "contact@domain.com",
   "Validation": null,
   "Required": false,
   "Message": null,
   "Options": null,
   "DefaultValue": null,
   "AllowAPI": true,
```

```
"ExplicitUpdate": true
}
```

# 2.3.7 Security

The Security component of the Keyfactor Web APIs includes all methods necessary to programmatically add, get and delete security identities as well as get, add, edit and delete the security roles defined in Keyfactor Command. The complete set of methods in the component is given in 2.3.7 Security.

Table 655: Security Endpoints

Endpoint	Method	Description
/1/GetIdentities	GET	Return a list of the identities in Keyfactor Command, the roles they are assigned to and their validity
/1/AddIdentity	POST	Add an identity to Keyfactor Command
/1/DeleteIdentities	POST	Remove an identity from Keyfactor Command
/1/GetRoles	GET	Retrieve all the security roles currently defined in Keyfactor Command with all of their permissions, a description and who they are assigned to
/1/AddRole	POST	Add a security role to Keyfactor Command
/1/EditRole	POST	Edit a security role in Keyfactor Command
/1/DeleteRole	POST	Delete a security role from Keyfactor Command

### 2.3.7.1 Security GetIdentities

The GET GetIdentities request returns a list of identities known to Keyfactor Command with the type of identity (user or group), whether the identity is valid or not and the roles associated with the identity. No parameters or extra headers are necessary for this method.

### **Example Request**

GET http://<host>/CMSApi/Security/1/GetIdentities HTTP/1.1

### **Example Response**

Status Code: 200

### 2.3.7.2 Security AddIdentity

The POST AddIdentities request adds an identity to Keyfactor Command. The POST request must contain a JSON string containing the AD account name. This method returns a 200 with the Id, account name, type, roles, and validity of the identity. The request parameters can be found in <u>Table 656</u>: <u>POST AddIdentity Request Parameter</u>.

Table 656: POST AddIdentity Request Parameter

Parameter Name	Parameter Value
Account	The name of the account that is to be added to CMS. This parameter is required.

### **Example Request**

For a user

POST http://<host>/CMSApi/Security/1/AddIdentity HTTP/1.1

```
{
    "Account": "<Domain>\\<User>"
}
```

### **Example Request**

For a group

POST http://<host>/CMSApi/Security/1/AddIdentity HTTP/1.1

```
{
    "Account": "<Domain>\\<Group>"
}
```

Status Code: 200

```
{
    "Id": <Id>,
    "AccountName": "<Domain>\\<Identity>",
    "Type": "<Identity Type>",
    "Roles": "<List of Roles>",
    "Valid": true
}
```

### 2.3.7.3 Security DeleteIdentity

The POST AddIdentities request removes an identity from Keyfactor Command. The POST request must contain a JSON string containing the identity Id. This method returns a 200 a message stating the identity was deleted successfully. The request parameters can be found in <u>Table 657</u>: <u>POST DeleteIdentity Request Parameter</u>

Table 657: POST DeleteIdentity Request Parameter

Parameter Name	Parameter Value
Id	The Id of the identity that is to be deleted

#### **Example Request**

POST http://<host>/CMSApi/Security/1/DeleteIdentity HTTP/1.1

```
{
    "Id": <Id>
}
```

### **Example Response**

Status Code: 200

```
{
    "Message": "ADIdentity deleted successfully"
}
```

# 2.3.7.4 Security GetRoles

The GET GetRoles endpoint retrieves all the current security roles defined in Keyfactor Command and returns the Id, name, description, validity, permissions and associated identities. The response parameters can be found in

#### Table 658: POST /GetRoles Response Body.

Table 658: POST /GetRoles Response Body

Parameter Name	Parameter Value
Id	The Id of the security role.
Name	The name of the security role.
Description	The description of the security role.
Valid	The validity of the security role.
Permissions	The permissions of the security role.
Identities	The security identities of the security role.

### **Example Request**

GET http://<host>/CMSApi/Security/1/GetRoles HTTP/1.1

### **Example Response**

Status Code: 200

### 2.3.7.5 Security AddRole

The POST AddRole endpoint creates a security role in Keyfactor Command. This endpoint can be used to assign a role to an identity and permissions to a role.

The list of available permissions can be found in <u>Table 659: Keyfactor Command Perm</u>issions List.

Request parameters can be found in <u>Table 660: POST /AddRole Request Parameters</u>.

Response parameters can be found in <u>Table 658: POST /GetRoles Response Body</u>.

Table 659: Keyfactor Command Permissions List

Permission Name	Permission Value
AgentAutoRegistrationModify	Permission to modify agent auto registrations.
AgentAutoRegistrationRead	Permission to read agent auto registrations.
AgentManagementModify	Permission to modify agents.
APIRead	Permission to use the Keyfactor Web APIs.
CertificateCollectionsModify	Permission to modify certificate collections.
CertificateMetadataTypesModify	Permission to modify metadatatypes.
CertificateMetadataTypesRead	Permission to read metadata types.
CertificatesImport	Permission to import certificates.
CertificatesModify	Permission to modify certificates' metadata.
CertificatesRead	Permission to read certificates.
CertificatesRecover	Permission to recover certificates.
CertificatesRevoke	Permission to revoke certificates.
CertificateStoreManagementModify	Permission to modify certificate stores.
CertificateStoreManagementRead	Permission to read certificate stores.
CertificateStoreManagementSchedule	Permission to schedule certificate stores.
MacAutoEnrollManagementModify	Permission to modify Mac auto enrollment settings.
MacAutoEnrollManagementRead	Permission to read Mac auto enrollment settings.
ManagementPortalRead	Permission to read the Keyfactor Command Management Portal.
MonitoringModify	Permission to modify monitoring settings.
MonitoringRead	Permission to read monitoring settings.
MonitoringTest	Permission to test monitoring.
PKIManagementModify	Permission to modify PKI management settings.
PKIManagementRead	Permission to read PKI management settings.
ReportsModify	Permission to modify reports.

Permission Name	Permission Value
ReportsRead	Permission to read reports.
SecuritySettingsModify	Permission to modify security settings.
SecuritySettingsRead	Permission to read security settings.
SSLManagementModify	Permission to modify SSL management settings.
SSLManagementRead	Permission to read SSL management settings.
SystemSettingsModify	Permission to modify system settings.
SystemSettingsRead	Permission to read system settings.
WorkflowModify	Permission to modify alert definitions.
WorkflowParticipate	Permission to approve/deny pending certificates.
WorkflowRead	Permission to read certificates in a pending state and alert definitions.
WorkflowTest	Permission to test alerts.

Table 660: POST /AddRole Request Parameters

Parameter Name	Parameter Value
Name	The name of the security role. This parameter is <b>required</b> .
Description	A description of the security role. This parameter is <b>required</b> .
Permissions	A list of permissions for the security role. This parameter is optional.
Identities	A list of security identities that will be associated with the security role. This parameter is optional.

POST http://<host>/CMSApi/Security/1/AddRole

```
{
    "Name":"<Name>",
    "Description":"<Description>",
    "Permissions": ["<Permission>","<Permission>"],
```

```
"Identities": ["<Domain>\\<Identity>", "<Domain>\\<Identity>"]
}
```

Status Code: 200

```
{
    "Id": <Id>, "Name": "<Name>",
    "Description": "<Description>",
    "Valid": true, "Permissions": "<List of permissions>",
    "Identities": "<List of identities>"
}
```

### 2.3.7.6 Security EditRole

The POST EditRole endpoint modifies existing security roles. The parameters for the EditRole endpoint can be found in <u>Table 661: POST /EditRole Request Parameters</u>. The administrator role's name, description and permissions cannot be changed.

Table 661: POST /EditRole Request Parameters

Parameter Name	Parameter Value
Id	The Id of the security role to be edited. This parameter is <b>required</b> .
Name	The name to which the security role will be changed. This parameter is optional.
Description	The description of which the security role will be changed. This parameter is optional.
Permissions	The permissions to which the security role will be changed. This parameter is optional.
Identities	The identities to which the security role will be changed. This parameter can take either the Id of a security identity or the identity name. This parameter is optional.

### **Example Request**

POST http://<host>/CMSApi/Security/1/EditRole

```
{
    "Id":<Id>,
```

```
"Identities":[<List of Identities>]
}
```

Status Code: 200

```
"Id": <Id>,
    "Name": "<Name>",
    "Description": "<Description>",
    "Valid": true,
    "Permissions": "<List of Permissions>",
    "Identities": "List of Identities>"
}
```

## 2.3.7.7 Security DeleteRole

The POST DeleteRole endpoint can be used to delete a security role from Keyfactor Command. A role can be deleted by name or Id. The administrator role cannot be deleted.

### **Example Request**

POST http://<host>/CMSApi/Security/1/DeleteRole

```
{
    "Id": <Id>
}
```

### **Example Response**

Status Code: 200

```
{
    "Message": "Successfully deleted Role: <Name of Role>"
}
```

#### 2.3.8 SSL

Keyfactor Command allows, through the Keyfactor Command Windows Agent, various network segments to be scanned for endpoints serving SSL certificates as well as endpoints presenting a certificate to be monitored for changes in status. An SSL scan is executed against an Endpoint Group, which is a collection of network endpoints, along with a scan schedule. Two types of endpoint groups exist:

- Discovery
   A Discovery endpoint group contains endpoints to be scanned for certificates.
- Monitoring
   A Monitoring group allows endpoints that presented a certificate in a discovery scan to be repeatedly scanned for changes.

The SSL Web API component allows SSL scan configuration to be retrieved and updated in order to facilitate rapid configuration of large numbers of network endpoints. The methods included in this component are given in <u>Table 662: SSL Endpoints</u>. As with the Certstore API component, the SSL component only has 1 version and all endpoints can be accessed through a URL path including /SSL/1/.

Table 662: SSL Endpoints

Endpoint	Method	Description
AddEndpoint	POST	Add a new endpoint to an endpoint group
AddEndpointGroup	POST	Add a new endpoint group to an agent.
Agents	GET	Return a list of Agents that can perform SSL scans.
EndpointGroups	GET	Returns a list of established endpoint groups for a particular agent

### 2.3.8.1 SSL AddEndpoint

The AddEndpoing method allows an endpoint to be added to an endpoint group. It returns HTTP 200 OK with response body "true" for successful requests or an appropriate 4xx error with a message on a failure.

Table 663: POST /AddEndpoint Request Body

Parameter Name	Parameter Value
EndpointGroupId	GUID of the endpoint group to which the endpoint should be added, which can be obtained through a combination of the GET SSL/1/Agents and GET SSL/1/EndpointGroups methods.
ItemType	Format in which the network endpoint is defined. Possible values are:

Parameter Name	Parameter Value	
	Value	Description
	1	IPAddress
	2	DnsName
	3	NetworkNotation
Value	ItemType, e.g. "192.168.41.171:443"	ould be formatted to match the expected format of the for IPAddress, "www.example.com:443" for DnsName, or otation (corresponding to the IP address range 192.168.0.1-endpoints).

POST http://<host>/CMSApi/SSL/1/AddEndpoint HTTP/1.1

```
{
    "EndpointGroupId": <GUID>,
    "ItemType": 3,
    "Value": "192.168.0.0/24:443"
}
```

# 2.3.8.2 SSL AddEndpointGroup

The AddEndpoint Group method allows a new endpoint group to be added for an agent. This requires the two fields shown in <u>Table 664: POST /AddEndpointGroup Request Body</u>. When successful, the GUID and Name of the created endpoint group are returned.

Table 664: POST /AddEndpointGroup Request Body

Parameter Name	Parameter Value
AgentId	GUID of the Agent that will scan endpoints in this group.
FriendlyName	Name of the group to be created.

Table 665: POST /AddEndpointGroup Response Body

Parameter Name	Parameter Value
Guid	Identifier for this endpoint group within Keyfactor Command.
Name	Name of the endpoint group used by Keyfactor Command.

### **Example Request**

POST http://<host>/CMSApi/SSL/1/AddEndpointGroup HTTP/1.1

```
{
    "AgentId": <GUID>,
    "FriendlyName": "local-endpoints"
}
```

### **Example Response**

```
{
    "Guid": "0a44f8af-6808-40ad-9816-d08c2c45d45a",
    "Name": "local-endpoints"
}
```

### 2.3.8.3 SSL Agents

The Agents HTTP Get method takes no parameters and returns a list of agents that can perform SSL scans. The result will be an array of structures, each with a GUID and name.

Table 666: GET /Agents Response Body

Parameter Name	Parameter Value
Guid	Identifier for this agent within Keyfactor Command.
Name	Hostname of the agent used by Keyfactor Command.

### **Example Request**

GET http://<host>/CMSApi/SSL/1/Agents

#### 2.3.8.4 SSL EndpointGroups

The EndpointGroups method returns the list of endpoint groups that have been defined for a particular agent. Unlike most methods in the Keyfactor Web APIs, this is a GET request that takes a parameter as part of the URL query string. The "agentId" required argument is the GUID of the agent for the endpoint groups that should be listed. This value can be retrieved from the GET /CMSApi/SSL/1/Agents response (see SSL Agents on the previous page). The response returned from this method will be an array of endpoint groups with the same structure as the response to AddEndpointGroup (see Table 665: POST /AddEndpointGroup Response Body).

#### **Example Request**

GET http://<host>/CMSApi/SSL/1/EndpointGroups?agentId=956282ef-f01b-4ae3-8cd2-57327749e15c HTTP/1.1

#### **Example Response**

## 2.3.9 Workflow

Workflow in Keyfactor Command refers to the process through which pending certificate requests are approved or denied. The Workflow API provides the ability to obtain a list of pending certificate enrollment requests, and approve or deny current requests. This component, like several others, currently encompasses only one version, and methods can all be accessed with the /Workflow/1/ prefix. The methods within this component are listed in Table 667: Workflow Endpoints

Table 667: Workflow Endpoints

Endpoint	Method	Description
Approve	POST	Approve a given pending certificate request

Endpoint	Method	Description
Deny	POST	Deny a given pending certificate request
PendingList	POST	Retrieve a list of outstanding pending certificate requests
Status	GET	Synonym for GET CMSApi/Status (see Status on page 1450)

### 2.3.9.1 Workflow Approve and Deny

The Approve POST method will attempt to approve the provided pending certificate enrollment request(s), while POST Deny will attempt to deny the request(s). In both cases, the structure of the pending request(s) is the same—an array of pending certificate enrollment requests must be provided in the format given in <a href="Table 669: POST">Table 669: POST</a> /Approve and /Deny PendingRequests Details. If only one request is to be sent, it should be provided as a list with one element. The one difference between the request formats for the two methods is that Deny supports an optional "Comments" field, which provides an opportunity to describe the reason for the request denial, shown in <a href="Table 668: POST">Table 668: POST /Approve and /Deny Request Body</a>. In both cases, an array of successful, failed and forbidden requests will be returned. The method will accept various inputs used to qualify the request to be approved, as shown in <a href="Table 669: POST /Approve">Table 669: POST /Approve and /Deny PendingRequests Details</a>.

Table 668: POST /Approve and /Deny Request Body

Parameter Name	Parameter Value
PendingRequests	Array of requests to be approved or denied. Required for both methods.
Comments	String describing the reason for the request denial. Optional for Deny and not permitted for Approve.

Table 669: POST /Approve and /Deny PendingRequests Details

Parameter Name	Parameter Value
CMSRequestId	The Keyfactor Command request database identifier. This parameter is the most specific, and can be used without any other parameters provided. An exception will be returned if this identifier is not found within Keyfactor Command.
CAHost	Host name of the certificate authority against which the certificate enrollment request was submitted. This parameter also requires the CALogicalName and CARequestId parameters to be provided in the request. An exception will be returned if a certificate authority with this host, logical name and request ID is not found within Keyfactor Command.
CALogicalName	Logical name of the certificate authority against which the certificate enrollment request was submitted. This parameter also requires the CAHost and CARequestId parameters to be provided in the request. An exception will be returned if a certificate authority with this host, logical name and

Parameter Name	Parameter Value
	request ID is not found within Keyfactor Command.
CARequestId	Request/row identifier of the request for certificate authority defined by CAHost and CALogicalName. This parameter also requires the CALogicalName and CAHost parameters to be provided in the request. An exception will be returned if a certificate authority with this host, logical name and request ID is not found within Keyfactor Command.

Table 670: POST / Approve and / Deny Response Body

Parameter Name	Parameter Value
Successes	An array of the successful approval response details (see table below in this section).
Failures	An array of the failed approval response details (see table below in this section). Failures of this type are generally exceptions.
Denials	An array of the approval requests that were denied (see table below in this section). Denials are usually created by insufficient user permissions required to perform the approval.

Table 671: POST /Approve and /Deny Result Details

Parameter Name	Parameter Value
CAHost	Host name of the certificate authority against which the certificate enrollment request was submitted.
CALogicalName	Logical name of the certificate authority against which the certificate enrollment request was submitted.
CMSRequestId	The Keyfactor Command request database identifier.
CARequestId	Request/row identifier of the request for certificate authority defined by CAHost and CALogicalName.
Comment	Brief description of the reason for the failure or denial, or simply 'Success' if the request succeeded.

Providing only a CMSRequestId

POST http://<host>/CMSApi/Workflow/1/Approve HTTP/1.1

Providing the certificate authority information

POST http://<host>/CMSApi/Workflow/1/Approve HTTP/1.1

```
{
    "PendingRequests":
    [{
        "CAHost":"<ca-host>","CALogicalName":"<ca-name>","CARequestId":<ca-request-id>
    }]
}
```

### **Example Request**

Providing both types of information

POST http://<host>/CMSApi/Workflow/1/Approve HTTP/1.1

### **Example Response**

(Successful)

```
{
    "Successes":
[{
```

```
"CAHost": "<ca-host>",
    "CALogicalName": "<ca-name>",
    "CARequestId": <ca-request-id>,
    "Comment": "Successful"
    }],
    "Failures": [],
    "Denials": []
```

(Invalid identifier)

```
"Successes": [],
    "Failures": [{
        "CAHost": "<ca-host>",
        "CALogicalName": "<ca-name>",
        "CMRequestId": <ca-request-id>,
        "CMSRequestId": <cms-request-id>,
        "Comment": "Unable to approve the request: <ca request id> for the certificate authority: '<ca-host-name>\<ca-logical-name>' \r\nfor the current user: '<requester>': No request for: CMS Request Id: 0,
CA Host: <ca-host>, CA Logical Name: <ca-name>, CA Request Id: <ca-request-id>"
        }],
        "Denials": []
}
```

### 2.3.9.2 PendingList

The POST PendingList method will return the current set of pending certificate enrollment requests stored within Keyfactor Command matching the provided parameters. The response will be a JSON object with a single field , PendingRequests, mapped to an array where each entry represents a single pending certificate request that matches the parameters provided in the HTTP request. Each of these entries will have the format given in <a href="Table-673">Table-673</a>: POST /PendingList Response Body.

Table 672: POST /PendingList Request Body

Parameter Name	Parameter Value
CAHost	Host name of the certificate authority against which the certificate enrollment request was submitted. This parameter also requires the CALogicalName parameter to be provided in the request. An exception will be returned if a certificate authority with this host and logical name is not found within Keyfactor Command.

Parameter Name	Parameter Value
CALogicalName	Logical name of the certificate authority against which the certificate enrollment request was submitted. This parameter also requires the CAHost parameter to be provided in the request. An exception will be returned if a certificate authority with this host and logical name is not found within Keyfactor Command.
LowerDate	Any pending requests prior to this date should be ignored. Optional.
UpperDate	Any pending requests after this date should be ignored. Optional.

Table 673: POST / PendingList Response Body

Parameter Name	Parameter Value	
CAHost	Host name of the certificate authority against which the certificate enrollment request was submitted.	
CALogicalName	Logical name of the certificate authority against which the certificate enrollment request was submitted.	
CARequestId	Identifier associated with the request within the certificate authority.	
CertificateAuthority	Combination of the CAHost and CALogicalName (CAHost\\CALogicalName).	
CMSRequestId	Database identifier associated with the request within Keyfactor Command.	
CommonName	Common name requested for the certificate.	
DistinguishedName	Distinguished name requested for the certificate.	
TemplateName	Certificate template for which the certificate was requested.	
KeySize	Number of bits in the certificate's private key.	
Requester	User or principal who requested the certificate, generally formatted "DOMAIN\\user".	
SubmissionDate	ISO-8601 formatted timestamp at which the certificate request was received.	
SubjectAlternativeName	Array of SANs requested for the certificate. The entries each correspond to one requested SAN element, and each one will be in the form given in <a href="Table 674: POST / PendingList_SubjectAlternativeName Details">Table 674: POST / PendingList_SubjectAlternativeName Details</a>	

Table 674: POST /PendingList SubjectAlternativeName Details

Parameter Name	Parameter Value	
Туре	Type of this SAN element on the certificate request. Will take one of the following values:	
	Value	Description
	0	Other
	1	RFC 822 name (e-mail address)
	2	DNS name
	3	X400 address
	4	Directory Name
	5	Edi Party Name
	6	URI
	7	IP address
	8	Registered ID
	100	Microsoft NT Principal Name
	101	Microsoft NTDS Replication
	999	Unknown
Value	String representation of the	e value requested for this SAN element.

POST http://<host>/CMSApi/Workflow/1/PendingList HTTP/1.1

```
{
    "CAHost": "<ca-host>",
    "CALogicalName": "<ca-name>",
    "LowerDate": <date or null or left out completely>,
    "UpperDate": <date or null or left out completely>}
}
```

```
{
    "PendingRequests":
    [{
        "CAHost":"<ca-host>",
        "CALogicalName":"<ca-name>",
        "CARequestId":<ca-request-id>,
        "CMSRequestId":<cms-request-id>}]
}
```

# 2.3.10 Workflow Expiration Alerts

Workflow in Keyfactor Command refers to the process through which pending certificate requests are approved or denied. The Workflow Expiration Alert APIs provides the ability to manage expiration alerts, event handlers, registered event handlers and schedules.

### 2.3.10.1 Workflow Expiration Alerts Endpoints

The Workflow Expiration Alert API provides the ability to list, create, update and delete expiration alerts for Keyfactor Command via the Keyfactor API. The methods within this component are listed in <a href="Table 675">Table 675</a>: Workflow Expiration Alerts Endpoints

Table 675: Workflow Expiration Alerts Endpoints

Endpoint	Method	Description
ExpirationAlerts	GET	List all Expiration Alerts or a get a single expiration alert definition.
ExpirationAlerts	POST	Create a new expiration alert definition.
ExpirationAlerts	PUT	Update an existing expiration alert definition.
ExpirationAlerts	DELETE	Delete an existing expiration alert definition.

### **Workflow Expiration Alerts**



**Note:** For the GET (single), PUT, and DELETE methods you will need the expiration alert ID. You will need to run the GET (list) method to acquire the ID in order to proceed with those methods.



**Note:** For the POST and PUT methods, if you are using Registered Event Handlers, you will need to run the Event handler GET (list) method to acquire the ID prior to issuing the expiration alert method (see <u>Workflow Expiration Alert Handler Parameters Endpoints on page 1445).</u>

Table 676: Workflow Expiration Alert Parameters

Parameter Name	Parameter Value
Id/Alert ID	The database ID of the Alert
DisplayName	Alert display name
Subject	The subject field of the alert
Message	The message field of the alert
UseHandler	True/False, whether or not the Use Handler checkbox is checked for the alert
Days	The number of days to alert before expiration
RegisteredEventHandlerId	Id of the Event Handler to use. See ( Workflow Expiration Alert Handler Parameters Endpoints on page 1445)
CertificateQuery	Name, and/or Id, of the certificate collection of the alert
ExpirationAlertRecipients	Id and/or Recipient email address in a comma separated list of objects. So there could be multiple addresses chunks in curly brackets{}, comma separated in the array in the square brackets []

# LIST all expiration alerts:

### **Example Request**

GET ~/ExpirationAlerts/1/List?page=<page number>&returnlimit=<max results to get>&sortname=<field to sort by>&sortorder=<asc or desc>

```
no body
```

```
[
    "Id": <id>,
    "DisplayName": "Alert display name",
    "QueryName": "Certificate query name",
    "Days": <number of days to alert before expiration>,
    "HandlerName": "Name of the Event Handler if any"
```

```
}
]
```

## Get a single alert definition

### **Example Request**

GET ~/ExpirationAlerts/1/<Alert Id>

```
no body
```

### **Example Response**

```
[
    "Id": <id>,
    "DisplayName": "Alert display name",
    "Subject": "Alert Subject",
    "Message": "Alert message body",
    "UseHandler": <true/false>,
    "Days": <number of days to alert before expiration>,
    "RegisteredEventHandlerId": <Id of the Event Handler to use>,
    "CertificateQuery": { "Id": <Cert query id>, "Name": "Cert query name" },
    "ExpirationAlertRecipients": [ { "Id": <recipient Id>, "Email": "Recipient email address" } ]
}
```

### **Create New Expiration Alert**

### **Example Request**

POST ~/ExpirationAlerts/1/

```
{
    "DisplayName": "Alert display name",
    "Subject": "Alert Subject",
```

```
"Message": "Alert message body",
"UseHandler": <true/false>,
"Days": <number of days to alert before expiration>,
"RegisteredEventHandlerId": <Id of the Event Handler to use>,
"CertificateQuery": { "Id": <Cert query id> },
"ExpirationAlertRecipients": [ { "Email": "Recipient email address" } ]
}
```

```
{
  "Id": <id>,
  "DisplayName": "Alert display name",
  "Subject": "Alert Subject",
  "Message": "Alert message body",
  "UseHandler": <true/false>,
  "Days": <number of days to alert before expiration>,
  "RegisteredEventHandlerId": <Id of the Event Handler to use>,
  "CertificateQuery": { "Id": <Cert query id>, "Name": "Cert query name" },
  "ExpirationAlertRecipients": [ { "Id": <recipient Id>, "Email": "Recipient email address" } ]
}
```

### **Update Existing Expiration Alert**

#### **Example Request**

PUT ~/ExpirationAlerts/1/<Alert Id>

```
"DisplayName": "Alert display name",
    "Subject": "Alert Subject",
    "Message": "Alert message body",
    "UseHandler": <true/false>,
    "Days": <number of days to alert before expiration>,
    "RegisteredEventHandlerId": <Id of the Event Handler to use>,
    "CertificateQuery": { "Id": <Cert query id> },
    "ExpirationAlertRecipients": [ { "Email": "Recipient email address" } ]
}
```

```
{
  "Id": <id>,
  "DisplayName": "Alert display name",
  "Subject": "Alert Subject",
  "Message": "Alert message body",
  "UseHandler": <true/false>,
  "Days": <number of days to alert before expiration>,
  "RegisteredEventHandlerId": <Id of the Event Handler to use>,
  "CertificateQuery": { "Id": <Cert query id>, "Name": "Cert query name" },
  "ExpirationAlertRecipients": [ { "Id": <recipient Id>, "Email": "Recipient email address" } ]
}
```

### **Delete Expiration Alert**

#### **Example Request**

DELETE ~/ExpirationAlerts/1/<Alert Id>

```
no body
```

#### **Example Response**

204 No Content

# 2.3.10.2 Workflow Expiration Alert Event Handler Parameters API

The Workflow Expiration Alert Event Handler Parameter API provides the ability to list, create, update and delete expiration alert event handler parameters for specific Keyfactor Command expiration alerts via the Keyfactor API. The methods within this component are listed in <a href="Table 677">Table 677</a>: Workflow Expiration Alerts Event Handler Parameters <a href="Endpoints">Endpoints</a>

Table 677: Workflow Expiration Alerts Event Handler Parameters Endpoints

Endpoint	Method	Description
HandlerParameters	GET	List all, or a given, expiration alert Handler Parameter(s) for an expiration alert.
HandlerParameters	POST	Create a new handler parameter for an expiration alert.
HandlerParameters	PUT	Update an existing expiration alert handler parameter for an expiration alert.
HandlerParameters	DELETE	Delete an existing expiration alert handler parameter for an expiration alert.

# **Workflow Expiration Alert Handler Parameters Endpoints**



**Note:** For the GET (single), PUT, and DELETE methods you will need the handler parameter ID. You will need to run the GET (list) method to acquire the ID in order to proceed with those methods.

Table 678: Workflow Expiration Alert Handler Parameters

Parameter Name	Parameter Value	
Id/Alert ID	The database ID of the handler	parameter
Key	The parameter name	
DefaultValue	The given value for the handler	parameter
ParameterType	The event handler parameter t	ype number
	Туре	Number
	Special Text	0
	Static Value	1
	PowerShell Script Name	2
	Logging Target Machine	3
	Renewal URL	4
	Renewal Template	5
	Renewal Certificate Authority	6
ExpirationAlertDefinitionId	The database ID of the expirati	on alert definition

# List All Handler Parameters for an Expiration Alert:

### **Example Request**

GET ~/ExpirationAlerts/1/<Alert Id>/HandlerParameters/List?page=<page number>&returnlimit=<max results to get>&sortname=<field to sort by>&sortorder=<asc or desc>

no body

### Get Handler Parameter by Id

### **Example Request**

GET ~/ExpirationAlerts/1/<Alert Id>/HandlerParameters/<handler param Id>

```
no body
```

# **Example Response**

#### Create New Handler Parameter

### **Example Request**

POST ~/ExpirationAlerts/1/<Alert Id>/HandlerParameters

```
{
  "Key": "Parameter Key name",
  "DefaultValue": "default value for parameter",
  "ParameterType": <Event Handler Parameter Type number>,
}
```

```
{
  "Id": <id>,
  "Key": "Parameter Key name",
  "DefaultValue": "default value for parameter",
  "ParameterType": <Event Handler Parameter Type number>,
}
```

### **Update Existing Handler Parameter**

### **Example Request**

PUT ~/ExpirationAlerts/1/<Alert Id>/HandlerParameters/<handler param Id>

```
{
  "Key": "Parameter Key name",
  "DefaultValue": "default value for parameter",
  "ParameterType": <Event Handler Parameter Type number>,
}
```

```
{
  "Id": <id>,
  "Key": "Parameter Key name",
  "DefaultValue": "default value for parameter",
  "ParameterType": <Event Handler Parameter Type number>,
}
```

#### **Delete Handler Parameter**

#### **Example Request**

DELETE ~/ExpirationAlerts/1/<Alert Id>/HandlerParameters/<handler param Id>

no body

### **Example Response**

204 No Content

### 2.3.10.3 Workflow Expiration Alert Registered Event Handlers API

The Workflow Expiration Alert Registered Event Handlers API provides the ability to list expiration alert registered event handlers: for Keyfactor Command via the Keyfactor API. The methods within this component are listed in Table 679: Workflow Expiration Alerts Registered Event Handlers Endpoints

Table 679: Workflow Expiration Alerts Registered Event Handlers Endpoints

Endpoint	Method	Description
RegisteredEventHandlers	GET	Get list of Registered Event Handlers

# **Workflow Expiration Alert Registered Event Handlers Parameters**

Table 680: Workflow Expiration Alert Registered Event Handlers Parameters

Parameter Name	Parameter Value
Id	The database ID of the registered event handler
Classname	Fully qualified class name of the registered event handler implementation in the associated assembly
DisplayName	The display name of registered event handler
Enabled	True/False, whether or not the Use Handler checkbox is checked for the alert
RegisteredEventAssemblyId	The Id of the registered event handler assembly

### **LIST all Registered Event Handlers:**

GET ~/ExpirationAlerts/1/RegisteredEventHandlers/List?page=<page number>&returnlimit=<max results to get>

```
no body
```

#### **Example Response**

```
{
  "Id": <registered event handler Id>,
  "ClassName": "class name of event handler",
  "DisplayName": "display name of event handler",
  "Enabled": <true/false>,
  "RegisteredEventAssemblyId": <id of the registered event assembly>
}
```

### 2.3.10.4 Workflow Expiration Alert Schedule API

The Workflow Expiration Alert Schedule API provides the ability to list, create, and set expiration alert schedules for Keyfactor Command via the Keyfactor API. The methods within this component are listed in <u>Table 681: Workflow Expiration Alerts Schedule Endpoints</u>

Table 681: Workflow Expiration Alerts Schedule Endpoints

Endpoint	Method	Description
Schedule	GET	Get the schedule set for all expiration alerts.
Schedule	POST	Create a new schedule for an expiration alert.

# **Workflow Expiration Alert Schedule Parameters**

Table 682: Workflow Expiration Alert Schedule Parameters

Parameter Name	Parameter Value
Daily	The display name of registered event handler
Time	The ISO string of time to schedule run

# **LIST Expiration Alert Schedule**

GET ~/ExpirationAlerts/1/Schedule

```
no body
```

#### **Example Response**

```
{
   "Daily": {
    "Time":"ISO string of time to schedule run"
   }
}
```

#### **Set Alerts Schedule**

### **Example Request**

POST ~/ExpirationAlerts/1/Schedule

```
{
   "Daily": {
    "Time":"ISO string of time to schedule run"
   }
}
```

#### **Example Response**

204 No Content

### 2.3.11 Status

The Status Web API component provides a single method to retrieve various aspects of the Keyfactor Command server state. This method is an HTTP GET Status request with no parameters required. As of Keyfactor Command 5.0, the Status endpoint generally is not needed by a Web API client application, as the Keyfactor Command version is passed back in an HTTP header with every response to every Web API request. However, it is included to preserve compatibility with applications already using it or applications requiring more information.

# **Example Request**

Status Code: 200

```
{
       "ApiMajorRev": 2,
       "ApiMinorRev": 0,
       "ProductMajorVersion": 5,
       "ProductMinorVersion": 0,
       "ProductBranchVersion": 0,
       "ProductBuildVersion": 1,
       \verb"LicenseStatus": \verb"Licensed",\\
       "Modules": [{
               "Name": "CertEnroll",
               "Versions": [1, 2, 3]
       },
       {
               "Name": "Certificates",
               "Versions": [1, 2, 3]
       },
       {
               "Name": "CertStore",
               "Versions": [1]
       },
       {
               "Name": "Metadata",
               "Versions": [2, 3]
       },
       {
               "Name": "Ssl",
               "Versions": [1]
       },
       {
               "Name": "Status",
               "Versions": null
       },
       {
               "Name": "Workflow",
                "Versions": [1]
       }]
}
```

#### 2.3.12 vSCEP

The vSCEP API method supports enrollment through the Keyfactor Command implementation of the SCEP protocol. The single method—GET CMSValidation/api/vSCEP—is used to retrieve a SCEP challenge, while also associating that challenge with the specified certificate subject information. This method differs from the other Web API methods in that it is not included in the CMSApi virtual directory, but in the separate "CMSValidation/api" directory. It also differs in that, while it is a GET method, it does take request parameters, which means that these parameters must be URL-encoded in the query string. Like the other Web API methods, however, it requires the Accept and Authorization headers, and returns a 200 OK status if a connection was successfully made to the vSCEP server or an appropriate 4XX status if a connection could not be made. The request and response formats are given in the below tables and example. All fields in the request are optional, and all but the Subject parameter may be submitted multiple times (for example, to include two different DNS SANs in the same certificate).

Table 683: GET /CMSValidation/api/vSCEP Query String Parameters

Parameter Name	Parameter Value
Subject	Distinguished Name that should be used as the certificate subject.
DNS	Subject Alternative Name representing a DNS record.
IP	Subject Alternative Name representing an IP address.
RFC822	Subject Alternative Name representing an RFC822 Name (email address).
NTPrincipal	Subject Alternative Name representing an NT Principal Name.

Table 684: GET /CMSValidation/api/vSCEP Response Body

Parameter Name	Parameter Value
Status Code	HTTP Status Code vSCEP received from the SCEP server. This will be 200 if the request was successful.
Message	Status message for the request. In the case of an error retrieving a SCEP challenge, this will provide more detailed error information.
Challenge	SCEP Challenge represented as a hex string. In the case of an error, this will be null.
Hash	MD5 hash of the CA certificate associated with the SCEP server. In the case of an error, this will be null.

#### **Example Request**

GET http://<host>/CMSValidation/api/vSCEP?subject=CN%3DBob%20Smith%2CO%3DExample%20Company& RFC822=bob.smith%40mail.example.com HTTP/1.1

Status Code: 200

```
{
    "Challenge":"247FAFEEABA1F9B7",
    "Hash":"01940B86 9C6C03DC 79BF2E5B 741779DF",
    "StatusCode":200,
    "Message":"Request stored successfully"
}
```

# 2.4 API Change Log

In this section you will find the change history for the Keyfactor Command API endpoints from version 9.0 on.

Find the change log for Keyfactor API below.

# 2.4.1 v9 API Change Log

Find the version 9 change log for Keyfactor API below.

Link to Change Logs				
API Change Log v9.0 on the next page				
API Change Log v9.1 on page 1455				
API Change Log v9.2 on page 1456				
API Change Log v9.3 on page 1456				
API Change Log v9.4 on page 1457				
API Change Log v9.5 on page 1457				
API Change Log v9.6 on page 1457				
API Change Log v9.7 on page 1457				
API Change Log v9.8 on page 1457				
API Change Log v9.9 on page 1458				

# 2.4.1.1 API Change Log v9.0

API changes for Keyfactor Command version 9.0 Major release

Table 685: API Change Log v9.0

Endpoint	Method	Action	Notes
/Agents/Approve	POST	Add	
/Agents/Disapprove	POST	Add	
/CertificateCollections	PUT	Add	
/CertificateCollections/Copy	POST	Add	
/Certificates/{id}/History	GET	Add	
/Certificates/{id}/Security	GET	Add	
/Certificates/{id}/Validate	GET	Add	
/Certificates/Locations/{id}	GET	Add	
/Certificates/Metadata/Compare	GET	Add	
/Certificates/Metadata/All	PUT	Add	
/Certificates/RevokeAll	POST	Add	
/CertificateStoreContainers	GET	Add	
/CertificateStoreContainers/{id}	GET	Add	
/CertificateStores/Certificates/Add	POST	Add	
/CertificateStores/Certificates/Remove	POST	Add	
/Enrollment/CSR/Context/My	GET	Add	
/Enrollment/PFX/Context/My	GET	Add	
/JobTypes/Custom	GET, POST, PUT	Add	
/JobTypes/Custom/{id}	GET, DELETE	Add	
/OrchestratorJobs/Custom	POST	Add	

Endpoint	Method	Action	Notes
/OrchestratorJobs/JobHistory	GET	Add	
/OrchestratorJobs/JobStatus/Data	GET	Add	
/Reports	GET, PUT	Add	
/Reports/{id}	GET	Add	
/Reports/{id}/Parameters	GET, PUT	Add	
/Reports/{id}/Schedules	GET, POST, PUT	Add	
/Reports/Custom	GET, POST, PUT	Add	
/Reports/Custom/{id}	GET, DELETE	Add	
/Reports/Schedules/{id}	GET, DELETE	Add	
/Security/Identities	GET, POST	Add	
/Security/Identities/{id}	DELETE	Add	
/Security/Identities/Lookup	GET	Add	
/Security/Roles	GET, POST, PUT	Add	
/Security/Roles/{id}	GET, DELETE	Add	
/SSH/Keys/Unmanaged	DELETE	Add	
/SSH/ServiceAccounts	DELETE	Add	
/SSH/Users/Access	POST	Add	
/SSL/Networks/{id}/Scan	POST	Add	

# 2.4.1.2 API Change Log v9.1

API changes for Keyfactor Command version 9.1 incremental release

Table 686: API Change Log v9.1

Endpoint	Methods	Action	Notes
/CertificateStores/{id}/Inventory	GET	Add	

Endpoint	Methods	Action	Notes
/Enrollment/PFX/Replace	POST	Fix	SuccessfulStores collection now only includes lds of stores that were successfully processed.
/Enrollment/PFX/Deploy	POST	Update	Now allows for multiple stores of the same type with different parameters.
/CertStoreTypes	POST/PUT	Update	EntryParameters can now be set via these methods.
/CertificateStores/Certificates/Add	POST	Update	Now allows for multiple stores of the same type with different parameters.
/CertificateStores/Certificates/Remove	POST	Update	Now allows for multiple stores of the same type with different parameters.
/CertificateCollections/{id}/Permissions	GET	Deprecate	

# 2.4.1.3 API Change Log v9.2

API changes for Keyfactor Command version 9.2 incremental release

Table 687: API Change Log v9.2

Endpoint	Methods	Action	Notes
/Certificates	GET	Fix	No longer fails if a collection id is not provided.
/OrchestratorJobs/JobHistory	GET	Fix	Request no longer fails for 'Dynamic' job types.
/Reports/Schedules/{id}	DELETE	Fix	Response code is now 200 when the user role does not have <i>Modify – Report</i> permission.

## 2.4.1.4 API Change Log v9.3

API changes for Keyfactor Command version 9.3 incremental release

Table 688: API Change Log v9.3

Endpoint	Methods	Action	Notes
/JobTypes/Custom	POST	Fix	No longer requires default field values.

## 2.4.1.5 API Change Log v9.4

API changes for Keyfactor Command version 9.4 incremental release

Table 689: API Change Log v9.4

Endpoint	Methods	Action	Notes
/Workflow/Certificates/Pending	GET	Update	Now returns the associated metadata.

## 2.4.1.6 API Change Log v9.5

API changes for Keyfactor Command version 9.5 incremental release

Table 690: API Change Log v9.5

Endpoint	Methods	Action	Notes
/Enrollment/PFX	POST	Update	No longer requires a certificate authority name to be provided.

# 2.4.1.7 API Change Log v9.6

API changes for Keyfactor Command version 9.6 incremental release.

No API endpoint changes were made in this release.

## 2.4.1.8 API Change Log v9.7

API changes for Keyfactor Command version 9.7 incremental release

Table 691: API Change Log v9.7

Endpoint	Methods	Action	Notes
/KeyfactorAPI/License	GET	Add	

# 2.4.1.9 API Change Log v9.8

API changes for Keyfactor Command version 9.8 incremental release.

No API endpoint changes were made in this release.

## 2.4.1.10 API Change Log v9.9

API changes for Keyfactor Command version 9.9 incremental release

Table 692: API Change Log v9.9

Endpoint	Methods	Action	Notes
/Reports/ <any></any>	GET	Fix	Spaces within the sortField no longer results in an exception.
/Reports/{id}/Sched- ules	GET	Fix	An invalid sortField no longer results in an exception.
/Agents	GET	Update	New query parser to support the Agentid GUID.

# 2.4.2 v10 API Change Log

Find the version 10 change log for Keyfactor API below.

Link to Change Logs

API Change Log v10.0 below

# 2.4.2.1 API Change Log v10.0

API changes for Keyfactor Command version 10.0 Major release

Table 693: API Change Log v10.0

Endpoint	Methods	Action	Notes
/Agents/{id}	GET	Add	
/Agents/Reset	POST	Add	
/AgentBlueprint	GET	Add	

Endpoint	Methods	Action	Notes
/AgentBlueprint/{id}	GET, DELETE	Add	
/AgentBlueprint/{id}/Jobs	GET	Add	
/AgentBlueprint/{id}/Stores	GET	Add	
/AgentBluePrint/ApplyBlueprint	POST	Add	
/AgentBluePrint/GenerateBluePrint	POST	Add	
/Alerts/Denied	GET, PUT, POST	Add	
/Alerts/Denied/{id}	GET, DELETE	Add	
/Alerts/Expiration	GET, PUT, POST	Add	
/Alerts/Expiration/{id}	GET, DELETE	Add	
/Alerts/Expiration/Schedule	GET, PUT	Add	
/Alerts/Expiration/Test	POST	Add	
/Alerts/Expiration/TestAll	POST	Add	
/Alerts/IssuedAlerts	GET, PUT, POST	Add	
/Alerts/IssuedAlerts/{id}	GET, DELETE	Add	
/Alerts/Issued/Schedule	GET, PUT	Add	
/Alerts/KeyRotation	GET, PUT, POST	Add	
/Alerts/KeyRotation/{id}	GET, DELETE	Add	
/Alerts/KeyRotation/Schedule	GET, PUT	Add	
/Alerts/KeyRotation/Test	POST	Add	
/Alerts/KeyRotation/TestAll	POST	Add	
/Alerts/Pending	GET, PUT, POST	Add	

Endpoint	Methods	Action	Notes
/Alerts/Pending/{id}	GET, DELETE	Add	
/Alerts/Pending/Schedule	GET, PUT	Add	
/Alerts/Pending/Test	POST	Add	
/Alerts/Pending/Test/{id}	POST	Add	
/CertificateAuthorities	GET	Update	Schedules are now included in the results.
/CertificateAuthorities	POST	Update	Ability to turn off schedules, sessions are abandoned properly, and threshold monitoring schedule is included.
/CertificateAuthorities/{id}	PUT	Update	Ability to turn off schedules, sessions are abandoned properly, and threshold monitoring schedule is included.
/CertificateAuthorities/{id}	DELETE	Update	Deletion is now prevented if schedules are associated.
/CertificateCollections	POST	Update	Query parameter no longer needed when a valid CopyFromId is provided.
/CertificateCollections/{id}/Permissions	POST	Deprecated	Replaced by /Security/Roles/{id}/Permissions/Collection.
/Certificates/Analyze	POST	Add	
/Certificates/IdentityAudit/{id}	GET	Add	
/CertificateStoreContainers	POST	Add	
/CertificateStoreContainers/{id}	PUT, DELETE	Add	
/CertificateStores/Server	GET, POST, PUT	To Be Deprecated	Server usernames, server passwords, and the UseSSL flag are managed by the /CertificateStores API endpoints directly as JobProperties using the Properties parameter, replacing the deprecated /CertificateStores/Server API endpoints.

Endpoint	Methods	Action	Notes
/CertificateStores	GET, POST, PUT	Updated	Server usernames, server passwords, and the UseSSL flag are managed by the /CertificateStores API endpoints directly as JobProperties using the Properties parameter, replacing the deprecated /CertificateStores/Server API endpoints.
/Enrollment/PFX (v2)	POST	Add	
/Enrollment/Settings/{id}	GET	Add	
/JobTypes/Custom	POST	Update	DefaultValue property is no longer required, validation is now performed on the JobTypeFields/DefaultValue property, validation prevents names containing spaces.
/JobTypes/Custom/{id}	DELETE	Update	Includes validation so that deletion is prevented if at least one associated approved orchestrator implements the capability.
/MacEnrollment	GET, PUT	Add	
/Monitoring/Revocation	GET, POST	Update	Renamed from /Work- flow/RevocationMonitoring
/Monitoring/Revocation/{id}	GET, PUT, DELETE	Update	Renamed from /Work-flow/RevocationMonitoring/{id}
/Monitoring/Revocation/Test	POST	Add	
/Monitoring/Revocation/TestAll	POST	Add	
/Orchestrators/JobHistory	GET	Update	Added Jobid field.
/Orchestrators/ScheduledJobs	GET	Add	
/OrchestratorJobs/Reschedule	POST	Add	
/OrchestratorJobs/Unschedule	POST	Add	
/OrchestratorJobs/Acknowledge	POST	Add	
/Security/Identities/{id}	GET	Add	

Endpoint	Methods	Action	Notes
/Security/Roles/{id}/Identities	GET, POST	Add	
/Security/Roles/{id}/Containers	GET, POST	Add	
/Security/Roles/{id}/Copy	POST	Add	
/Security/Roles/{id}/Permissions	GET	Add	
/Security/Roles/{id}/Permissions/Global	GET, POST, PUT	Add	
/Security/Roles/{id}/Per- missions/Collections	GET, POST, PUT	Add	Replaced the /CertificateCollections/ {id}/Permissions endpoint functionality.
/Security/Roles/{id}/Per- missions/Containers	GET, POST, PUT	Add	Returns only containers that have a permission set for the selected security role.
/SMTP	GET, PUT	Add	
/SMTP/Test	POST	Add	
/Templates	GET, PUT	Update	Includes template-specific policy information.
/Templates/{id}	GET	Update	Includes template defaults.
/Templates/Settings	GET, PUT	Update	Includes global template policies.
/Template/SubjectParts	GET	Add	
/Templates/Global/Settings	GET, PUT	Add	
/Templates/Import	POST	Add	
/Workflow/Certificates/Pending	GET	Update	Now supports query fields of Requester and RequestType.
/Workflow/Definitions/Steps/{extensionName}	GET	Add	
/Workflow/Definitions/{definitionId}	GET, PUT, DELETE	Add	
/Workflow/Definitions	GET, POST	Add	

Endpoint	Methods	Action	Notes
/Workflow/Definitions/Steps	GET	Add	
/Workflow/Definitions/Types	GET	Add	
/Workflow/Definitions/{definitionId}/Steps	PUT	Add	
/Workflow/Definitions/{definitionId}/Publish	POST	Add	
/Workflow/Instances/{instanceId}	GET, DELETE	Add	
/Workflow/Instances	GET	Add	
/Workflow/Instances/My	GET	Add	
/Workflow/Instances/AssignedToMe	GET	Add	
/Workflow/Instances/{instanceId}/Stop	POST	Add	
/Workflow/Instances/{instanceId}/Signals	POST	Add	
/Workflow/Instances/{instanceId}/Restart	POST	Add	

#### Α

## AIA

The authority information access (AIA) is included in a certificate--if configured--and identifies a location from which the chain certificates for that certificate may be retrieved.

## **AnyAgent**

The AnyAgent, one of Keyfactor's suite of orchestrators, is used to allow management of certificates regardless of source or location by allowing customers to implement custom agent functionality via an API.

## **AnyGateway**

The Keyfactor AnyGateway is a generic third party CA gateway framework that allows existing CA gateways and custom CA connections to share the same overall product framework.

## API

A set of functions to allow creation of applications. Keyfactor offers the Keyfactor API, which allows third-party software to integrate with the advanced certificate enrollment and management features of Keyfactor Command.

#### **Argument**

A parameter or argument is a value that is passed into a function in an application.

## **Authority Information Access**

The authority information access (AIA) is included in a certificate--if configured--and identifies a location from which the chain certificates for that certificate may be retrieved.

## В

## **Bash Orchestrator**

The Bash Orchestrator, one of Keyfactor's suite of orchestrators, is used to discover and manage SSH keys across an enterprise.

## **Blueprint**

A snapshot of the certificate stores and scheduled jobs on one orchestrator, which can be used to create matching certificate stores and jobs on another orchestrator with just a few clicks.

## C

#### CA

A certificate authority (CA) is an entity that issues digital certificates. Within Keyfactor Command, a CA may be a Microsoft CA or a Keyfactor gateway to a cloud-based or remote CA.

## **Certificate Authority**

A certificate authority (CA) is an entity that issues digital certificates. Within Keyfactor Command, a CA may be a Microsoft CA or a Keyfactor gateway to a cloud-based or remote CA.

## **Certificate Revocation List**

A Certificate Revocation List (CRL) is a list of digital certificates that have been revoked by the issuing Certificate Authority (CA) before their scheduled expiration date and should no longer be trusted.

## **Certificate Signing Request**

A CSR or certificate signing request is a block of encoded text that is submitted to a CA when enrolling for a certificate. When you generate a CSR within Keyfactor Command, the matching private key for it is stored in Keyfactor Command in encrypted format and will be married with the certificate once returned from the CA.

## CN

A common name (CN) is the component of a distinguished name (DN) that represents the primary name of the object. The value varies depending on the type of object. For a user object, this would be the user's name (e.g. CN=John Smith). For SSL certificates, the CN is typically the fully qualified domain name (FQDN) of the host where the SSL certificate will reside (e.g. servername.keyexample.com or www.keyexample.com).

#### Collection

The certificate search function allows you to query the Keyfactor Command database for certificates from any available source based on any criteria of the certificates and save the results as a collection that will be available in other places in the Management Portal (e.g. expiration alerts and certain reports).

#### **Common Name**

A common name (CN) is the component of a distinguished name (DN) that represents the primary name of the object. The value varies depending on the type of object. For a user object, this would be the user's name (e.g. CN=John Smith). For SSL certificates, the CN is typically the fully qualified domain name (FQDN) of the host where the SSL certificate will reside (e.g. servername.keyexample.com or www.keyexample.com).

## **Configuration Tenant**

A grouping of CAs. The Microsoft concept of forests is not used in EJBCA so to accommodate the new EJBCA functionality, and to avoid confusion, the term forest needed to be renamed. The new name is configuration tenant. For EJBCA, there would be one configuration tenant per EJBCA server install. For Microsoft, there would be one per forest. Note that configuration tenants cannot be mixed, so Microsoft and EJBCA cannot exist on the same configuration tenant.

## CRL

A Certificate Revocation List (CRL) is a list of digital certificates that have been revoked by the issuing Certificate Authority (CA) before their scheduled expiration date and should no longer be trusted.

## **CSR**

A CSR or certificate signing request is a block of encoded text that is submitted to a CA when enrolling for a certificate. When you generate a CSR within Keyfactor Command, the matching private key for it is stored in Keyfactor Command in encrypted format and will be married with the certificate once returned from the CA.

#### Г

## DER

A DER format certificate file is a DER-encoded binary certificate. It contains a single certificate and does not support storage of private keys. It sometimes has an extension of .der but is often seen with .cer or .crt.

## **Distinquished Name**

A distinguished name (DN) is the name that uniquely identifies an object in a directory. In the context of Keyfactor Command, this directory is generally Active Directory. A DN is made up of attribute=value pairs, separated by commas. Any of the attributes defined in the directory schema can be used to make up a DN.

## DN

A distinguished name (DN) is the name that uniquely identifies an object in a directory. In the context of Keyfactor Command, this directory is generally Active Directory. A DN is made up of attribute=value pairs, separated by commas. Any of the attributes defined in the directory schema can be used to make up a DN.

## DNS

The Domain Name System is a service that translates names into IP addresses.

#### F

## **ECC**

Elliptical curve cryptography (ECC) is a public key encryption technique based on elliptic curve theory that can be used to create faster, smaller, and more efficient cryptographic keys. ECC generates keys through the properties of the elliptic curve equation instead of the traditional method of generation as the product of very large prime numbers.

## **Endpoint**

An endpoint is a URL that enables the API to gain access to resources on a server.

#### Enrollment

Certificate enrollment refers to the process by which a user requests a digital certificate. The user must submit the request to a certificate authority (CA).

## **EOBO**

A user with an enrollment agent certificate can enroll for a certificate on behalf of another user. This is often used when provisioning technology such as smart cards.

## F

## **Forest**

An Active Directory forest (AD forest) is the top most logical container in an Active Directory configuration that contains domains, and objects such as users and computers.

## G

## **Gateway Connector**

The Keyfactor Gateway Connector is installed in the customer forest to provide a connection between the on-premise CA and the Azure-hosted, Keyfactor managed Hosted Configuration Portal to provide support for synchronization, enrollment and management of certificates through the Azure-hosted instance of Keyfactor Command for the on-premise CA. It is supported on both Windows and Linux.

#### Н

## **Host Name**

The unique identifier that serves as name of a computer. It is sometimes presented as a fully qualified domain name (e.g. servername.keyexample.com) and sometimes just as a short name (e.g. servername).

## **Hosted Config Portal**

The Keyfactor Hosted Configuration Portal is used to configure connections between on-premise instances of the Keyfactor Gateway Connector and and on-premise CAs to make them available to Azure-hosted instance of Keyfactor Command.The portal is Azure-hosted and managed by Keyfactor.

## **Hosted Configuration Portal**

The Keyfactor Hosted Configuration Portal is used to configure connections between on-premise instances of the Keyfactor Gateway Connector and and on-premise CAs to make them available to Azure-hosted instance of Keyfactor Command.The portal is Azure-hosted and managed by Keyfactor.

## Hostname

The unique identifier that serves as name of a computer. It is sometimes presented as a fully qualified domain name (e.g.

servername.keyexample.com) and sometimes just as a short name (e.g. servername).

#### J

## **Java Agent**

The Java Agent, one of Keyfactor's suite of orchestrators, is used to perform discovery of Java keystores and PEM certificate stores, to inventory discovered stores, and to push certificates out to stores as needed.

#### Java Keystore

A Java KeyStore (JKS) is a file containing security certificates with matching private keys. They are often used by Java-based applications for authentication and encryption.

#### JKS

A Java KeyStore (JKS) is a file containing security certificates with matching private keys. They are often used by Java-based applications for authentication and encryption.

## K

#### **Key Length**

The key size or key length is the number of bits in a key used by a cryptographic algorithm.

## **Key Pair**

In asymmetric cryptography, public keys are used together in a key pair with a private key. The private key is retained by the key's creator while the public key is widely distributed to any user or target needing to interact with the holder of the private key.

## **Key Size**

The key size or key length is the number of bits in a key used by a cryptographic algorithm.

## **Key Type**

The key type identifies the type of key to create when creating a symmetric or asymmetric key. It references the signing algorithm and often key size (e.g. AES-256, RSA-2048, Ed25519).

## **Keyfactor CA Management Gateway**

The Keyfactor CA Management Gateway is made up of the Keyfactor Gateway Connector, installed in the customer forest to provide a connection to the local CA, and the Azure-hosted and Keyfactor managed Hosted Configuration Portal. The solution is used to provide a connection between a customer's on-premise CA and an Azure-hosted instance of Keyfactor Command for synchronization, enrollment, and management of certificates.

## **Keyfactor Gateway Connector**

The Keyfactor Gateway Connector is installed in the customer forest to provide a connection between the on-premise CA and the Azure-hosted, Keyfactor managed Hosted Configuration Portal to provide support for synchronization, enrollment and management of certificates through the Azure-hosted instance of Keyfactor Command for the on-premise CA. It is supported on both Windows and Linux.

## **Keyfactor Universal Orchestrator**

The Keyfactor Universal Orchestrator, one of Keyfactor's suite of orchestrators, is used to interact with Windows servers (a.k.a. IIS certificate stores) and FTP capable devices for certificate management, run SSL discovery and management tasks, and manage synchronization of certificate authorities in remote forests. With the addition of custom extensions, it can run custom jobs to provide certificate management capabilities on a variety of platforms and devices (e.g. F5 devices, NetScaler devices, Amazon Web Services (AWS) resources) and execute tasks outside the standard list of certificate management functions. It runs on either Windows or Linux.

## **Keystore**

A Java KeyStore (JKS) is a file containing security certificates with matching private keys. They are often used by Java-based applications for authentication and encryption.

#### ī

## **Logical Name**

The logical name of a CA is the common name given to the CA at the time it is created. For Microsoft CAs, this name can be seen at the top of the Certificate Authority MMC snap-in. It is part of the FQDN\Logical Name string that is used to refer to CAs when using command-line tools and in some Keyfactor Command configuration settings (e.g. ca2.keyexample.com\Corp Issuing CA Two).

## M

#### **MAC Agent**

The MAC Agent, one of Keyfactor's suite of orchestrators, is used to manage certificates on any keychains on the Mac on which the Keyfactor MAC Agent is installed.

#### Metadata

Metadata provides information about a piece of data. It is used to summarize basic information about data, which can make working with the data easier. In the context of Keyfactor Command, the certificate metadata feature allows you to create custom metadata fields that allow you to tag certificates with tracking information about certificates.

## 0

## **Object Identifier**

Object identifiers or OIDs are a standardized system for identifying any object, concept, or

"thing" with a globally unambiguous persistent name.

## OID

Object identifiers or OIDs are a standardized system for identifying any object, concept, or "thing" with a globally unambiguous persistent name.

#### Orchestrator

Keyfactor orchestrators perform a variety of functions, including managing certificate stores and SSH key stores.

#### P

#### P12

A PFX file (personal information exchange format), also known as a PKCS#12 archive, is a single, password-protected certificate archive that contains both the public and matching private key and, optionally, the certificate chain. It is a common format for Windows servers.

## **P7B**

A PKCS #7 format certificate file is a base64-encoded certificate. Since it's presented in ASCII, you can open it in any text editor. PKCS #7 certificates always begin and end with entries that look something like ---- BEGIN CERTIFICATE---- and ---- END CERTIFICATE----. Unlike PEM files, PKCS #7 files can contain only a certificate and its certifiate chain but NOT its private key. Extensions of .p7b or .p7c are usually seen on certificate files of this format.

## P7C

A PKCS #7 format certificate file is a base64encoded certificate. Since it's presented in ASCII, you can open it in any text editor. PKCS #7 certificates always begin and end with entries that look something like ---- BEGIN CERTIFICATE---- and ----END CERTIFICATE----. Unlike PEM files, PKCS #7 files can contain only a certificate and its certifiate chain but NOT its private key. Extensions of .p7b or .p7c are usually seen on certificate files of this format.

#### **Parameter**

A parameter or argument is a value that is passed into a function in an application.

#### **PEM**

A PEM format certificate file is a base64-encoded certificate. Since it's presented in ASCII, you can open it in any text editor. PEM certificates always begin and end with entries like ---- BEGIN CERTIFICATE---- and ----END CERTIFICATE----. PEM certificates can contain a single certificate or a full certifiate chain and may contain a private key. Usually, extensions of .cer and .crt are certificate files with no private key, .key is a separate private key file, and .pem is both a certificate and private key.

## PFX

A PFX file (personal information exchange format), also known as a PKCS#12 archive, is a single, password-protected certificate archive that contains both the public and matching private key and, optionally, the certificate chain. It is a common format for Windows servers.

## **PKCS #7**

A PKCS #7 format certificate file is a base64-encoded certificate. Since it's presented in ASCII, you can open it in any text editor. PKCS #7 certificates always begin and end with entries that look something like ---- BEGIN CERTIFICATE---- and ---- END CERTIFICATE----. Unlike PEM files, PKCS #7 files can contain only a certificate and its certifiate chain but NOT its private key. Extensions of .p7b or .p7c are usually seen on certificate files of this format.

#### PKCS#12

A PFX file (personal information exchange format), also known as a PKCS#12 archive, is a single, password-protected certificate archive that contains both the public and matching private key and, optionally, the certificate chain. It is a common format for Windows servers.

#### PKI

A public key infrastructure (PKI) is a set of roles, policies, and procedures needed to create, manage, distribute, use, store and revoke digital certificates and manage public-key encryption.

## **Private Key**

Private keys are used in cryptography (symmetric and asymmetric) to encrypt or sign content. In asymmetric cryptography, they are used together in a key pair with a public key. The private or secret key is retained by the key's creator, making it highly secure.

## **Public Key**

In asymmetric cryptography, public keys are used together in a key pair with a private key. The private key is retained by the key's creator while the public key is widely distributed to any user or target needing to interact with the holder of the private key.

## **Public Key Infrastructure**

A public key infrastructure (PKI) is a set of roles, policies, and procedures needed to create, manage, distribute, use, store and revoke digital certificates and manage public-key encryption.

#### R

## **Rogue Key**

A rogue key, in the context of Keyfactor Command, is an SSH public key that appears in an authorized\_keys file on a server managed by the SSH orchestrator without authorization.

#### **Root of Trust**

A root of trust (RoT) is a source within a cryptographic system that can always be trusted. It is typically a hardened hardware module. HSMs (hardware security modules) and TPMs (trusted platform modules) are examples of RoTs.

#### RoT

A root of trust (RoT) is a source within a cryptographic system that can always be trusted. It is typically a hardened hardware module. HSMs (hardware security modules) and TPMs (trusted platform modules) are examples of RoTs.

#### RPC

Remote procedure call (RPC) allows one program to call a function from a program located on another computer on a network without specifying network details. In the context of Keyfactor Command, RPC errors often indicate Kerberos authentication or delegation issues.

#### rsyslog

Rsyslog is an open-source software utility used on UNIX and Unix-like computer systems for forwarding log messages in an IP network.

#### S

#### SAN

The subject alternative name (SAN) is an extension to the X.509 specification that allows you to specify additional values when enrolling for a digital certificate. A variety of SAN formats are supported, with DNS name being the most common.

#### server name indication

Server name indication (SNI) is an extension to TLS that provides for including the hostname of the target server in the initial handshake request to allow the server to respond with the correct SSL certificate or allow a proxy to forward the request to the appropriate target.

#### **SMTP**

Short for simple mail transfer protocol, SMTP is a protocol for sending email messages between servers.

#### SNI

Server name indication (SNI) is an extension to TLS that provides for including the hostname of the target server in the initial handshake request to allow the server to respond with the correct SSL certificate or allow a proxy to forward the request to the appropriate target.

## SSH

The SSH (secure shell) protocol provides for secure connections between computers. It provides several options for authentication, including public key, and protects the communications with strong encryption.

## SSL

TLS (Transport Layer Security) and its predecessor SSL (Secure Sockets Layer) are protocols for establishing authenticated and encrypted links between networked computers.

## **Subject Alternative Name**

The subject alternative name (SAN) is an extension to the X.509 specification that allows you to specify additional values when enrolling for a digital certificate. A variety of SAN formats are supported, with DNS name being the most common.

#### Т

## **Template**

A certificate template defines the policies and rules that a CA uses when a request for a certificate is received.

## TLS

TLS (Transport Layer Security) and its predecessor SSL (Secure Sockets Layer) are protocols for establishing authenticated and encrypted links between networked computers.

## **Trusted CA**

A certificate authority in the forest in which Keyfactor Command is installed or in a forest in a two-way trust with the forest in which Keyfactor Command is installed.

#### U

#### **Untrusted CA**

A certificate authority in a forest in a one-way trust with the forest in which Keyfactor Command is installed or in a forest that is untrusted by the forest in which Keyfactor Command is installed. Non-domain-joined standalone CAs also fall into this category.

## W

## Web API

A set of functions to allow creation of applications. Keyfactor offers the Keyfactor API, which allows third-party software to integrate with the advanced certificate enrollment and management features of Keyfactor Command.

#### **Windows Orchestrator**

The Windows Orchestrator, one of Keyfactor's suite of orchestrators, is used to manage

synchronization of certificate authorities in remote forests, run SSL discovery and management tasks, and interact with Windows servers as well as F5 devices, NetScaler devices, Amazon Web Services (AWS) resources, and FTP capable devices, for certificate management. In addition, the AnyAgent capability of the Windows Orchestrator allows it to be extended to create custom certificate store types and management capabilities regardless of source platform or location.

## Workflow

A workflow is a series of steps necessary to complete a process. In the context of Keyfactor Command, it refers to the workflow builder, which allows you automate event-driven tasks when a certificate is requested or revoked.

## X

## x.509

In cryptography, X.509 is a standard defining the format of public key certificates. An X.509 certificate contains a public key and an identity (e.g. a host name or an organization or individual name), and is either signed by a certificate authority or self-signed. When a certificate is signed by a trusted certificate authority it can be used to establish trusted secure communications with the owner of the corresponding private key. It can also be used to verify digitally signed documents and emails.

# 4.0 Copyright Notice

User guides and related documentation from Keyfactor are subject to the copyright laws of the United States and other countries and are provided under a license agreement that restricts copying, disclosure, and use of such documentation. This documentation may not be disclosed, transferred, modified, or reproduced in any form, including electronic media, or transmitted or made publicly available by any means without the prior written consent of Keyfactor and no authorization is granted to make copies for such purposes.

Information described herein is furnished for general information only, is subject to change without notice, and should not be construed as a warranty or commitment by Keyfactor. Keyfactor assumes no responsibility or liability for any errors or inaccuracies that may appear in this document.

The software described in this document is provided under written license agreement, contains valuable trade secrets and proprietary information, and is protected by the copyright laws of the United States and other countries. It may not be copied or distributed in any form or medium, disclosed to third parties, or used in any manner not provided for in the software licenses agreement except with written prior approval from Keyfactor.